WINDOWS



The Microsoft® Guide to Programming for the MS-DOS®

Presentation Manager: Windows 2.0 and Windows/386.

PLESPETZOLD

WINDOWS



PROGRAMMING

WINDOWS

The Microsoft® Guide to Programming for the MS-DOS®

Presentation Manager: Windows 2.0 and Windows/386



CHARIES PETZOLD

PUBLISHED BY

Microsoft Press

A Division of Microsoft Corporation

16011 NE 36th Way, Box 97017, Redmond, Washington 98073-9717

Copyright @ 1988 by Charles Petzold

All rights reserved. No part of the contents of this book may

be reproduced or transmitted in any form or by any means without

the written permission of the publisher.

Library of Congress Cataloging in Publication Data

Petzold, Charles, 1953-

Programming Windows.

Includes index.

1. IBM Personal Computer-Programming. 2. Microsoft Windows (Computer programs) I. Title.

OA76.8.I2594P474 1988 005.36'9 87-28132

ISBN 1-55615-100-4 (cloth)

ISBN 0-914845-91-8 (paper)

Printed and bound in the United States of America

456789 MLML 89098

Distributed to the book trade in the

United States by Harper & Row.

Distributed to the book trade in

Canada by General Publishing Company, Ltd.

Distributed to the book trade outside the

United States and Canada by Penguin Books Ltd.

Penguin Books Ltd., Harmondsworth, Middlesex, England

Penguin Books Australia Ltd., Ringwood, Victoria, Australia

Penguin Books N.Z. Ltd., 182-190 Wairau Road, Auckland 10, New Zealand

British Cataloging in Publication Data available

IBM® is a registered trademark of International Business Machines Incorporated. Microsoft® and MS-DOS® are registered trademarks of Microsoft Corporation.

Project Editor: Dean Holmes

Technical Editor: Roger Shanafelt

CONTENTS

	Preface	vii
	I. Basic Concepts	
1.	Windows and Programming	3
2.	Creating and Displaying Windows	35
3.	Painting the Client Area with Text	87
	II. Getting Input	
	The Keyboard	125
	The Mouse	157
	The Timer	197
7.	Child Window Controls	225
	III. Using Resources	
8.	Memory Management	281
9.	Icons, Cursors, Bitmaps, and Strings	323
10.	Menus and Accelerators	359
11.	Dialog Boxes	415
	IV. The Graphics Device Inte	erface
12.	An Introduction to GDI	499
13.	[14.27.27.27.27.27.28.27.27.27.27.27.27.27.27.27.27.27.27.27.	541
14.	Bits, Blts, and Metafiles	601
15.	Text and Fonts	641
16.	Using the Printer	699
	V. Data Exchange and Links	
17.	The Clipboard	763
18.	Dynamic Link Libraries	805
	Index	843



PREFACE

This book covers almost everything you'll need to know to write programs for Microsoft Windows 2.0 and Windows/386 using the C programming language. Since its introduction in November 1985, Microsoft Windows has established itself as the standard graphical-based multitasking windowing environment running under MS-DOS on IBM PCs and compatibles. Most major software manufacturers have made clear their intentions of developing applications that run under Windows. My goal in writing this book has been to help aspiring Windows programmers get up to speed and write those applications that the rest of us will use.

The advent of OS/2 and the OS/2 Presentation Manager emphasizes the importance of Windows even more. Windows 2.0 and the OS/2 Presentation Manager have a common user interface and similarly structured application program interfaces. Until the OS/2 Presentation Manager is available, becoming familiar with Windows 2.0 is the best way to prepare yourself for OS/2 and the future of PC software.

Windows has the reputation of being easy for users but tough for programmers. Often the aspiring Windows programmer faces a steep learning curve, where the search for knowledge leads to an avalanche of information. For this reason, I have set a leisurely pace in the early chapters, building up programs from simple beginnings and then adding enhancements.

Beginning Windows programmers usually want to see lots of programming examples. To satisfy that need, this book contains more than 60 complete programs. Many of them are short and stripped down to clearly illustrate various Windows programming techniques. Others are quite long to show how everything fits together. Several of the programs are useful utilities. Others are tools for exploring Windows.

If you already have some Windows programming experience but are still hazy on some topics, this book will help clear away the fog. I think it's particularly important for Windows programmers to understand why they often need to put some strange-looking code in their programs. I have therefore included extensive explanations of several aspects of Windows that nobody else seems willing to discuss. If you've been programming for Windows and have no idea what the <code>MakeProcInstance</code> function does (for example), this is one book that thinks you should know.

Although this book is primarily for programmers, I have also included much information that will interest technically minded nonprogrammers who are curious about the inner workings of Windows. If you can "read but not write" C programs, you can learn a lot about Windows here without taking the plunge into actual programming.

What I'm not going to do in this book is teach you how to use Windows. If you have no experience with Windows, now is the time to install it and play with it for a while. Windows is very easy to learn.

Nor will I teach you how to program in C. Before you even think about programming for Windows, you should have a good working knowledge of programming in C for a more conventional operating system such as MS-DOS. If your C is a little rusty, you may want to spend some time becoming better acquainted with the topics of structures and pointers.

A good familiarity with the segmented architecture of the Intel 8086 family of microprocessors will also help. If you know how 8086 addressing works and the difference between near and far pointers and functions, you're in good shape. For those readers who don't, I've included some brief explanations along the way.

To compile the programs in this book and to write your own programs for Windows, you need the following software packages:

- Microsoft Windows 2.0 or Windows/386
- Microsoft Windows Software Development Kit 2.0
- Microsoft C Compiler 4.0 or 5.0
- Microsoft Macro Assembler 4.0 or 5.0 (for Chapter 18 only)

You can use a C compiler other than Microsoft's if the compiler is suitable for compiling Windows programs. Most other C compilers can't be used for this purpose.

To run Windows and the Windows Software Development Kit, you need the following hardware:

- An IBM personal computer (or compatible) with a fixed disk and 640 KB of memory running MS-DOS version 2.0 or later. A machine based on an 80286 or 80386 microprocessor with a fast fixed disk is best.
- A graphics display and video board, preferably an Enhanced Graphics Adapter (EGA) or a Video Graphics Array (VGA).
- A mouse. (Although a mouse is generally optional for most Windows programs, some of the programs in this book require one.)

Sometimes readers of computer books are curious about the author's own system. Mine is rather straightforward. I did most of my programming and writing on an IBM PC/AT Model 339 (8 MHz) with two 30 megabyte fixed disks, 512 KB of memory on the system board, and a 1.5 megabyte Intel Above Board PS/AT. The system includes a Microsoft bus mouse, an IBM 256 KB Enhanced Graphics Adapter, and a NEC MultiSync monitor. My IBM 5152 Graphics printer—which I had feared was already in its twilight years even before I began the book—successfully printed at least three copies of every chapter without once complaining. Amazing.

The book and programs were written using WordStar 3.3. (Old habits die hard, and very old habits perhaps never die.) The text files were submitted on disk to Microsoft Press, where they were promptly converted to the format of a more modern word processor.

A book such as this could not have come about without help and encouragement from some very special people. I offer my heartfelt thanks with a handshake or hug (as appropriate) to the following people:

- To everyone at Microsoft Press who was involved with the editing and production of Programming Windows, for behind-the-scenes work that makes all the difference in the world.
- To everyone at Microsoft who has contributed to the development of Windows, for creating a system with fascinating depth and seemingly endless things to learn.
- To Jonathan Lazarus, for his faith, support, and enthusiasm over the years, and to Tandy Trower, who was responsible for bringing me and Microsoft Press together to talk about a Windows programming book.
- To my friends and colleagues at PC Magazine who recognized the importance of this book and graciously let me work on it without interruption (except, of course, when something really important came up), and particularly to John Dickinson, Bill Machrone, and Paul Somerson, who helped rescue me from corporate oblivion.
- To all the Windows programmers (and particularly the indefatigable Michael Geary) who contribute to the Windows Developers Roundtable on General Electric's GEnie bulletin board, for their many intelligent and thought-provoking discussions about Windows programming.
- · And most of all to Jan, for being there.

Charles Petzold November 1987

Special Offer COMPANION DISKS TO

COMPANION DISKS TO PROGRAMMING WINDOWS

Microsoft Press has created a set of Companion Disks to PROGRAMMING WINDOWS to save you time typing and proofreading the more than 60 complete Windows programs provided in this book. Available in either 5.25-inch format (four-disk set) or 3.5-inch format (two-disk set), the Companion Disks contain both the source code and executable (.EXE) files for all the book's programs. These include many useful utilities, such as HEXCALC, a hexadecimal calculator; DIGCLOCK, a digital clock display; BLOWUP, a tool for capturing any part of the screen to the clipboard; POPPAD, a handy notepad; WINPRTSC, a screen-printing utility; and other programs that let you explore and understand Windows' use of the keyboard, the mouse, graphics, color, and fonts. These Companion Disks are a valuable ready-to-use resource for Windows programmers.

If you have questions about the files on the disk, you can contact the author through MCI mail (CPETZOLD or 143-6815).

The Companion Disks to PROGRAMMING WINDOWS are available only from Microsoft Press. To order, use the special reply card bound in the back of the book. If the card has already been used, send \$29.95, plus sales tax if applicable (CA residents 5% plus local option tax, CT 7.5%, FL 6%, MA 5%, MN 6%, MO 4.225%, NY 4% plus local option tax, WA State 7.8%) and \$2.50 per disk for domestic postage and handling, \$6.00 per disk for foreign orders, to: Microsoft Press, Attn: Companion Disk Offer, 21919 20th Ave S.E., Box 3011, Bothell, WA 98041-3011. Please specify 5.25-inch or 3.5-inch format. Payment must be in U.S. funds. You may pay by check or money order (payable to Microsoft Press) or by American Express, VISA, or MasterCard; please include both your credit card number and the expiration date. All domestic orders are shipped 2nd day air upon receipt of order by Microsoft.

If any of these disks prove defective, please send the defective disk(s) along with your packing slip to: Microsoft Press, Consumer Sales, 16011 NE 36th Way, Box 97017, Redmond, WA 98073-9717.

SECTION I

BASIC CONCEPTS

Chapter 1

Windows and Programming

Microsoft Windows is an operating environment that runs under MS-DOS version 2.0 or later, generally on IBM personal computers or compatible machines. The installed base of IBM PCs and compatibles running MS-DOS is currently about 10 million.

For the user, Windows provides a multitasking graphical-based windowing environment that runs programs especially written for Windows and some current programs written for MS-DOS. (Many other programs written for MS-DOS can run under Windows but will not be windowed or multitasked.) Programs especially written for Windows have a consistent appearance and command structure and are thus often easier to learn and use than conventional MS-DOS programs. Users can easily switch between different programs running under Windows and exchange data between them.

For the program developer, Windows provides a wealth of built-in routines that allow the easy implementation of menus, dialog boxes, scroll bars, and other components of a friendly user interface. Windows also contains an extensive graphics programming language that includes the use of formatted text in a choice of fonts. Programmers can treat the keyboard, mouse, video display, printer, system timer, and RS-232 communication ports in a device-independent manner. Windows programs run identically on a variety of hardware configurations.

For the future, Windows is also an integral part of the new protected mode operating system developed by Microsoft and IBM, Operating System/2. Under this system, Windows is

called the Presentation Manager. Microsoft expects OS/2 to establish foundations that will carry the PC-compatible microcomputer industry through the next ten years. The OS/2 Presentation Manager is seen as the principal environment for new OS/2 application programs.

A BRIEF HISTORY OF WINDOWS

Windows was originally announced by Microsoft Corporation in November 1983 and released two years later, in November 1985. The first version of Windows was Windows 1.01. Windows 1.02 (May 1986) was the international version with editions in many European languages. Windows 1.03 (August 1986) was a domestic version with minor enhancements to make it consistent with the European version. Windows 1.03 included drivers for European keyboards and additional screen and printer drivers. Windows 1.04 (April 1987) included new drivers primarily for the support of the video modes of IBM's recent PS/2 line of personal computers.

At the time of the first introduction of Windows, several other software manufacturers had also introduced systems that ran programs in a windowed or graphical environment. The success of any such environment depends on the quality and popularity of application programs that are designed to run under it. Although in this respect Windows was well on its way to becoming the standard windowing environment for the PC, the real boost came in April 1987 when Microsoft and IBM announced the introduction of OS/2 and the OS/2 Presentation Manager.

Developed under the IBM/Microsoft Joint Development Agreement, OS/2 is an operating system that uses the protected mode operation of the Intel 80286 and 80386 microprocessors. Although programmers can develop character mode applications that do not require the Presentation Manager component of OS/2, the Presentation Manager provides a much better environment for new applications. The OS/2 Presentation Manager also plays a major role in IBM's Systems Application Architecture (SAA), a long-term plan that includes the establishment of a consistent user interface across IBM's entire line of computers.

Windows 2.0—the subject of this book—is an MS-DOS version of the Presentation Manager released in November 1987. Windows 2.0 incorporates changes to the appearance and user interface of Windows for consistency with the user interface of the OS/2 Presentation Manager. The most significant of these changes involves the use of "overlapped" windows rather than the "tiled" windows found in Windows 1.0. Windows 2.0 also includes enhancements to the keyboard and mouse interface, particularly for menus and dialog boxes.

Although the user interface of Windows 2.0 is the same as that for the OS/2 Presentation Manager, the application program interface (API) is different, particularly for graphics.

The two environments share many conceptual and structural similarities, however, and Microsoft expects to make tools available for the conversion of existing MS-DOS Windows programs to the API of the OS/2 Presentation Manager.

WINDOWS, USERS, AND PROGRAMMERS

Windows provides considerable advantages to both users and programmers over the conventional MS-DOS environment. The benefits to users and the benefits to program developers are really quite similar, because the job of a program developer is to give the users what they need and want. Windows makes this possible.

The "Visual Interface" and Other Jargon

Beneath the obscure jargon used in describing a system such as Windows are some very simple concepts. Windows is said to incorporate a "visual interface." In one sense, what this means is that the Windows user can see something meaningful on the screen.

MS-DOS does not have a visual interface. Just as some of the very early personal computers were sold without keyboards or video displays, MS-DOS is sold without anything to look at. After MS-DOS is loaded into the computer, the video display offers only a prompt, as shown in Figure 1-1. The prompt tells the user exactly one thing: that the default disk drive is drive C. MS-DOS then waits for the user to enter something at the prompt. Like what? Check your MS-DOS manual to find out.

C>

Figure 1-1. The MS-DOS prompt

This is a typical command line interface, and it is beginning to smell a little musty. The personal computer came out of an environment where ease of use was not a practical consideration. At the beginning of the personal computer revolution (the mid-1970s), the people who used small computers very often programmed them and in some cases even built them. Simply getting the machine running at all was the miracle. A better user interface was a luxury.

The command line interface is no longer tolerable. In contrast to the MS-DOS prompt, the initial screen of Windows is elaborate, as shown in Figure 1-2 (on the following page). What you see is a program that comes with Windows called the MS-DOS Executive, and it (very nearly) has all the functionality of the old MS-DOS command line. The menu across the top indicates several categories of commands the user can execute. Triggering one of these menu items with either the keyboard or the mouse invokes a popup menu that lists further commands.




Figure 1-2. The initial screen of Windows

The Consistent User Interface

Users no longer expect to spend long periods of time learning how to use the computer or mastering a new program. Windows helps out because all Windows programs have the same fundamental look and feel. The program is identified by a caption bar, and, as in the MS-DOS Executive program, most functions are initiated through the program's menu. Figure 1-3 shows a typical Windows program.

Some menu items invoke dialog boxes in which the user enters additional information. One dialog box found in almost every large Windows program is used to open a file. (See Figure 1-4.) This dialog box looks the same (or very similar) in many different Windows programs, and it is usually invoked from the same menu option.

Basically, once you know how to use one Windows program, you're in a good position to easily learn another. The menus and dialog boxes allow a user to experiment with a new program and explore its features. Most Windows programs have both a keyboard interface and a mouse interface. Although most functions of Windows programs can be controlled through the keyboard, using the mouse is often easier for many chores.

From the programmer's perspective, the consistent user interface results from using the routines built into Windows for constructing menus and dialog boxes. All menus have the same keyboard and mouse interface because Windows handles this job rather than the application program.




Figure 1-3. The standard elements of a typical Windows program




Figure 1-4. A dialog box invoked by choosing Open from the File menu of Windows' WRITE program

Where Did It Come From?

The concepts behind this type of visual interface date from the mid-1970s with work done at the Xerox Palo Alto Research Center (PARC). The interface was used first in the Xerox Alto and later in the 8010 Star Information System. In particular, the Star (introduced in April 1981, four months before IBM introduced the original PC) has a look and feel that is instantly recognizable to Windows users. Xerox PARC took a revolutionary approach in designing a user interface—they did real research using actual naive users rather than relying on the instincts of programmers.

The visual interface pioneered at Xerox PARC was brought into the mainstream and popularized by Apple Computers, first in the ill-fated Lisa and then a year later in the much more successful Macintosh, introduced in January 1984. The Apple Macintosh remains the only real challenger to IBM's dominance in the business market. It is not the hardware of the Macintosh but the operating environment that makes the machine so appealing to users. The Mac is simply easier to use and learn than an IBM PC running MS-DOS. An IBM PC running Windows, however, meets the Macintosh challenge and provides other benefits over both the MS-DOS environment and the Mac.

Windows Is Multitasking

Although some people continue to question whether multitasking is really necessary on a single-user computer, users definitely are ready for multitasking and can benefit from it. The popularity of MS-DOS RAM-resident popup programs (such as SideKick) proves it. Although popups are not, strictly speaking, multitasking programs, they allow fast context switching, and this involves many of the same concepts as multitasking.

Under Windows, every program becomes a RAM-resident popup. Several Windows programs can be displayed and running at the same time. Each program occupies a rectangular window on the screen, as shown in Figure 1-5. The user can move the windows around on the display, change their size, switch between different programs, and transfer data from one program to another. Because this display looks something like a desk (in the days before the desk became dominated by the computer itself, of course), Windows is said to use a "desktop metaphor" for the organization of programs.

Because Windows runs under the single-tasking MS-DOS, it does not employ the most traditional form of multitasking, which is preemptive multitasking based on the system clock. Instead, Windows uses a "nonpreemptive multitasking" that I'll discuss in the next chapter. This nonpreemptive multitasking still allows programs to run nearly simultaneously but avoids problems that would result from treating MS-DOS as if it were a multitasking system. (Because OS/2 is a real multitasking operating system, the OS/2 Presentation Manager uses preemptive multitasking.)




Figure 1-5. A Windows screen with several programs displayed simultaneously

Although Windows provides a standard mechanism called the clipboard for transferring data between programs, a more sophisticated method of interprocess communication is also available. The Dynamic Data Exchange (DDE) protocol defines how two applications can send messages to each other and exchange blocks of data.

Windows Has Real Memory Management

An operating system cannot implement multitasking without also doing something about memory management. As new programs are started up and old ones terminate, memory can become fragmented. The system must be able to consolidate free memory space, which requires that it must move blocks of code and data in memory. Windows can do this. Under the 8086 family of microprocessors running in real mode, this feat has to be regarded as wonderful magic. I'll devote a whole chapter to memory management to show you how it's done.

Programs running under Windows can overcommit memory. A program can contain more code than can fit into memory at any one time. Windows can discard code from memory and later reload the code from the program's .EXE file. A user can run several copies (called "instances") of the same program. All these instances share the same code in memory. Thus the 640 KB memory limit of the PC's architecture is effectively stretched without requiring any additional memory.

Programs running in Windows can share routines located in other .EXE files. The files that contain these shared routines are called dynamic link libraries. Windows includes the mechanism to link the program with the routines in the dynamic link library at run time. Windows itself is a set of dynamic link libraries.

To support all this, Windows programs use a new format of .EXE file, called the "New Executable" format. This file includes the information Windows needs to manage the code and data segments the program contains and to perform the dynamic linking.

Windows Has a Device-Independent Graphics Interface

Windows is a graphical interface, and Windows programs can make full use of graphics and formatted text. A graphical interface is not only more attractive in appearance, but it can also impart a high level of information to the user, as you can see in Figure 1-6.

Programs written for Windows do not directly access the hardware of display devices such as the video display or the printer. Windows includes a graphics programming language that allows the easy display of graphics and formatted text.

Windows virtualizes display hardware. A program written for Windows will run with any video board or any printer for which a Windows device driver is available. The program does not need to determine what type of video display or printer is attached to the system.




Figure 1-6. An example of Windows' use of graphics and formatted text

Putting a device-independent graphics interface on the IBM PC was not an easy job for the Windows developers. The PC was designed based on the principle of open architecture. Third-party hardware manufacturers were encouraged to develop peripherals for the PC (including video boards, printers, and input devices) and have done so in great number. Although several standards have emerged, conventional MS-DOS application programs for the PC must individually support a mass of different hardware configurations. For example, it is fairly common for an MS-DOS word-processing program to be sold with one or two disks full of small files, each one supporting a particular printer. Windows programs do not require this approach, because the support is part of Windows. That fact benefits users, because most Windows programs require little in the way of installation. Everything a program needs can be included in the program's single EXE file. The user can usually copy the EXE file to the fixed disk, load Windows, and go.

Windows Runs MS-DOS Applications

Although Windows is primarily a system to run new programs specifically designed for the environment, Windows can also run many existing MS-DOS programs. The Windows User's Guide refers to these as "standard applications," but many Windows programmers call them "old applications" or "old apps." These programs can be divided into two broad categories: those that can run in a window and those that cannot. Programs that use the MS-DOS and PC BIOS (basic input/output system) software interrupts to read the keyboard and write to the display can generally run in a window. These are called well-behaved applications or "good old apps."

Existing programs that write directly to the video display, use graphics, or take control of the hardware keyboard interrupt cannot be run in a window. These are often called "bad apps." The term *bad* here refers not to the quality of the program—many of the best programs written for the PC are bad apps when it comes to Windows—but to the way in which the program uses the hardware of the PC. There is simply no way that Windows can allow such a program to be windowed and multitasked. (A forthcoming version of Windows that exploits the "virtual 86" mode of the 80386 microprocessor is expected to provide a partial solution to this problem.)

And, of Course, the Disadvantages

Windows is not a perfect environment on the IBM PC under MS-DOS. First, Windows requires a large amount of disk space and lots of memory. Although Windows can in theory be run from two floppy disks on a machine with only 320 KB of memory, it is almost unusable in that configuration. Windows works much better with a fixed disk and 640 KB of memory. Second, Windows can be intolerably slow when running on 8088-based machines such as the original IBM PC and PC/XT. Almost everyone now acknowledges that Windows requires an

80286-based machine (such as the PC/AT or compatible) or an accelerator board (such as the Microsoft MACH 10 board) to perform adequately. But perhaps the most serious problem is that there are not yet enough programs designed for the Windows environment. Taking care of that problem is what this book is all about.

THE STRUCTURE OF WINDOWS

You start up Windows as if it were a normal application program running under MS-DOS. By the time the MS-DOS Executive program appears on the screen, however, Windows has become almost a full-fledged operating system. It's not quite an operating system, because it runs on top of MS-DOS. While Windows is running, it shares responsibility with MS-DOS for managing the hardware resources of the PC. MS-DOS continues to manage the file system of the PC, while Windows does everything else. Windows commands the video display, keyboard, mouse, printer, and serial ports and is responsible for memory management, program execution, and scheduling.

Windows is strong where MS-DOS is weak, and weak where MS-DOS is adequate. Windows includes almost no support of file I/O, which is the most essential chore of a minimal operating system such as MS-DOS. (This leads to some amusing—or not so amusing—consequences. It is easier in a Windows program to create a disk-based metafile containing a complex series of drawing commands than to create a simple ASCII text file. The former is a Windows job; the latter requires that the program use MS-DOS.)

The application program interface of Windows is very different from that of MS-DOS. Let's review first how application programs written for MS-DOS communicate with the operating system.

MS-DOS and Application Programs: The Theory

Figure 1-7 shows the theoretical relationship between an application program, MS-DOS, the ROM BIOS, and the hardware. An application program makes function calls to MS-DOS mostly through the Interrupt 21H interface. Most of these function calls pertain to file I/O, but others include some support for the video display, keyboard, printer, and RS-232 communication ports. The component of MS-DOS that handles these calls is usually named MSDOS.SYS in a version of MS-DOS configured for non-IBM machines and IBMDOS.COM in the version of MS-DOS sold by IBM.

If MS-DOS must access the hardware of the machine to process a particular function call, MS-DOS makes a call to one of its device drivers. MS-DOS includes device drivers for the standard hardware of the computer in a file called IO.SYS in non-IBM versions of MS-DOS and IBMBIO.COM in the IBM version. Other device drivers can be installed when MS-DOS first

loads. These device drivers generally make function calls to the ROM BIOS of the machine through software interrupts. On IBM-compatible machines, these include Interrupt 13H (disks) and Interrupt 10H (the video display). The ROM BIOS then accesses the hardware.

MS-DOS and Application Programs: The Practice

Of course, Figure 1-7 has no relation to reality, because MS-DOS provides extremely limited support for the video display, keyboard, printer, and serial port. For this reason, most application programs bypass MS-DOS for everything except file I/O. The PC's ROM BIOS provides some additional support for the nondisk hardware, but often the performance is inadequate. The BIOS is particularly a problem for video graphics and interrupt-driven RS-232 communications. Without an adequate operating system or BIOS, application programs have no choice but to access the hardware directly. For most application programs, the real relationship between the program, MS-DOS, the ROM BIOS, and the hardware is as shown in Figure 1-8 (on the following page).




Figure 1-7. The theoretical relationship between an application program, MS-DOS, the ROM BIOS, and the hardware




Figure 1-8. The real relationship between an application program, MS-DOS, the ROM BIOS, and the hardware

Windows and Application Programs

A Windows application is significantly different from an MS-DOS application in several ways. Windows provides application programs with access to about 450 function calls. These function calls are generally handled by three main modules in Windows called the KERNEL, GDI (Graphics Device Interface), and USER modules. The KERNEL module (about 50 KB) is responsible for memory management, loading and executing programs, and scheduling. The GDI module (about 100 KB) is responsible for graphics, and USER (about 150 KB) is responsible for everything else.

The USER and GDI modules call routines in the Windows device drivers. The device drivers directly access the computer's hardware or (in the case of the printer driver) call the ROM BIOS printer-output routine. Under normal circumstances, a Windows program never directly accesses the hardware of the computer or makes calls to the ROM BIOS. It has no need to do so because of the high level of support that Windows provides in using the PC's hardware. The relationship between a Windows program, Windows itself, MS-DOS, and the other system components is shown in Figure 1-9.

The Interrupt 21H calls that a Windows program makes are mostly those for file I/O and (more rarely) the MS-DOS EXEC function call to load another program. All the other calls that a program makes are Windows function calls. The dashed lines in Figure 1-9 indicate that




Figure 1-9. The relationship between an application program, Windows, MS-DOS, the ROM BIOS, and the hardware

Windows intercepts Interrupt 21H calls to MS-DOS. Windows does this partly to provide additional support for some function calls (in particular the EXEC function call) and partly to prevent a program from calling MS-DOS routines that write to the display or read the keyboard. Windows also intercepts many BIOS calls to prevent the BIOS from interfering with Windows' device drivers. Figure 1-10 (on the following page) shows in greater detail the relationship between the Windows modules and device drivers, although this figure still presents a somewhat simplified picture. The GDI module and some of the driver files also call functions in the KERNEL module, and application programs themselves sometimes call functions in the driver modules.

You'll note that the names of the three main modules of Windows are shown as files—GDI.EXE, USER.EXE, and KERNEL.EXE. The various device driver modules also have filenames, each of which has the extension .DRV. If you have a normally installed version of Windows, the only one of these files that you will see is the printer driver that you install.




Figure 1-10. The relationship between the Windows modules and device drivers

Generally, the filename of the printer driver is an abbreviation of the name of the printer. The other modules are merged into two large files named WIN200.BIN and WIN200.OVL. However, many Windows programmers prefer installing a version of Windows called the "slow boot" version. All the modules shown in Figure 1-10 are separate files in the "slow boot" version. This provides an easy way to try various drivers without reinstalling Windows. Directions on installing a "slow boot" version of Windows are included in the Windows Software Development Kit. Don't worry about the "slow boot" version being slow—at most it adds a second or two to the time it takes to load Windows. After that, it runs at normal speed.

Figure 1-10 might look very comforting to you, because it indicates that Windows is not much different from conventional operating systems. An application program makes calls to Windows, Windows makes calls to its device drivers, and the device drivers access the hardware. But don't get too comfortable just yet, because this diagram—although generally accurate—tells you absolutely nothing about what's really going on inside Windows.

More Jargon: "Object-Oriented Programming"

Some say that when you're programming for Windows, you're actually doing "object-oriented programming." The concept of object-oriented programming—like the graphics windowing system itself—originated at Xerox PARC. In object-oriented programming, an "object" is an abstract data type that consists of a data structure and various functions that act on the data structure. Objects receive "messages" that cause them to change (that is, perform operations on) themselves.

Windows has many objects, but one object ranks first in importance. It is the object that is the center of your Windows programs, the object that will soon seem to have a life of its own, the object that might even show up in your dreams—the object called the "window."

What Is a Window?

From the user's perspective, a window is the rectangular area that a particular program occupies on the screen. Although a single program can create many windows, usually the program has a single main, or top-level, window that looks a little like, well, a window. To the user, this is the program's work space on the screen. The window is what Windows uses to divide the screen into separate programs.

From the programmer's perspective, a window is an object that receives and processes messages. If I said instead that a window "receives and processes user input," you might swallow the statement more easily. After all, any interactive program has to process user input in the form of keystrokes or mouse clicks. And certainly, many of the messages that a window receives pertain to user input. But messages go far beyond that. Messages inform the window of all events that affect the window.

When a program creates one or more windows (as we'll be doing in the next chapter), each window has certain characteristics—a style, a size, a position on the screen, a character string in its caption bar, a menu, an icon. But a window is defined by more than merely its appearance. A window is defined also by how it responds to a particular message. This is determined by a function (called the "window function") associated with the window. Every window has a window function.

The messages that a window receives contain information about an event. When we say that a "window receives messages," what we really mean is that the window's window function is called with information about the message. This information is passed as parameters to the function.

Where do these messages come from? Who sends them? That is, who or what calls a window's window function? Most messages come from Windows. But a window can also send itself a message. This action is the equivalent of posting a little note to yourself on the refrigerator door to remind you to do something. Or a window in one program can send a message to a window in another program. You can visualize this as a type of electronic mail system in which windows can communicate with each other.

Let's begin, however, with the messages that are conceptually the easiest—those messages that are caused by user input in the form of keystrokes and mouse clicks. These messages are often the instigators of many more messages that result from the user input. The Alt-F4 combination (which closes a window) is a good example. Closing down a program involves lots of messages. The program's window must be informed that it's being destroyed, for example. But some other program running under Windows must be informed that it can now assume the topmost position on the display. How does the program know this? It doesn't have to ask—it gets told. It obtains the information through a message.

The Messaging System

Figure 1-11 shows one part of the Windows messaging system. This part translates keyboard and mouse events into messages. The keyboard and mouse drivers handle asynchronous interrupts from the keyboard and mouse devices. When a keyboard or mouse event occurs, the appropriate driver calls a function in the USER module that translates this event into a formatted message containing information about the event—the key that was struck or the position of the mouse, for example. This message is stored in a system message queue.

Windows has only one system message queue, but each program currently running under Windows also has its own program message queue, as shown in Figure 1-12. Each message in the system message queue must eventually be transferred by the USER module to a program's message queue. The program's message queue stores all messages for all windows in that program.




Figure 1-11. The translation of keyboard and mouse events into system queue messages




Figure 1-12. The translation of messages in the system queue to the individual programs' message queues

In Windows, the keyboard and mouse are shared resources. One keyboard and one mouse must provide input to all programs running under Windows. A particular keyboard or mouse message can go to only one window. So how does Windows determine which program's message queue gets the keyboard or mouse message? At any one time, only one window has the "input focus." The window with the input focus receives all keyboard messages while it has the focus. The mouse is handled differently. Mouse messages are sent to the window that is physically underneath the mouse.

The keyboard and mouse messages go into a system message queue before being transferred to a program's message queue, because some messages can affect which window must eventually receive the message. If one of the keyboard messages in the queue is for an Alt-Esc combination, for example, which changes the input focus from one program's window to another program's window, then any keyboard messages that follow must go in the second program's message queue. But Windows doesn't know that until the Alt-Esc message has been processed by the window that receives it.

Another type of message that is very much like the keyboard and mouse messages is the timer message. (Not coincidentally, Chapters 4, 5, and 6 of this book cover the keyboard, the mouse, and the timer, respectively.) A program can set a timer so that one of its windows receives a message at periodic intervals. This message goes straight into the program's message queue, as shown in Figure 1-13.

Other messages get into a program's message queue as a result of the program's calling certain functions in Windows. It's a little early to expose you to actual Windows function names, but a few are shown in Figure 1-14. How does a program get these messages out of the message queue? The program calls the Windows *GetMessage* function (an extremely important function that you're going to see a lot of), and Windows returns the next message from the program's message queue in the form of a data structure. This process is shown in Figure 1-15.

A program calls GetMessage in a short piece of code called a "message loop." The message loop obtains messages from the queue with GetMessage and sends them off to the appropriate window function with DispatchMessage. Because a program can create more than one window, a program can have more than one window function. The DispatchMessage logic in Windows must determine which of the program's windows gets




Figure 1-13. The transfer of timer messages into a program's message queue




Figure 1-14. The transfer of other messages into a program's message queue




Figure 1-15. The retrieval of messages from the message queue by a program

this message. Another program can also send a program's window a message using the function *SendMessage*. As shown in Figure 1-16 (on the following page), the Windows USER module takes these messages and passes them to the recipient—which is the window function.

The window function then processes the message. If the window function chooses not to process the message, it can call on Windows to do its own default processing. It does this by calling <code>DefWindowProc</code>. This function often generates more messages, some of which can also go to window functions in other programs. It is through this process that the Alt-F4 key combination, for example, generates numerous messages both to the window with the input focus and to other windows.

If all this seems too abstract right now, don't worry about it. We'll be rehashing this material again in the next chapter—you may find it easier to grasp at that point, because you'll be working with a real program rather than flowcharts.




Figure 1-16. The process of sending messages to various window functions

PROGRAMMING FOR WINDOWS

Programming for Windows is an all-or-nothing proposition. You cannot write an old application—even a well-behaved one—and use Windows only for some graphics, for instance. If you want to use any part of Windows, you have to make the commitment to write a fullfledged Windows program.

This fact should be fairly obvious from the discussion of the structure of Windows. Everything in Windows is interconnected. If you want to draw some graphics on the video display, you need something called a "handle to a device context." To get that, you need a "handle to a window." To get that, you must create a window and be prepared to receive messages to the window. To receive and process messages to the window, you need a window function. And at that point you're writing a Windows program.

In the next chapter we'll write a few Windows programs. Before we do, we need to cover a few preliminaries.

8086 Architecture

Both MS-DOS and Windows run on computers that use microprocessors of the Intel 8086 family. Although you may think that you don't have to worry about the microprocessor when you're programming in a high-level language, an understanding of the segmented memory architecture of the 8086 helps greatly in understanding Windows.

The Intel 8086 family includes the 8086, 8088, 80186, 80188, 80286, and 80386 microprocessors. The 80286 and 80386 microprocessors can run in two different modes called real mode and protected mode. MS-DOS and Windows support only real mode, in which the memory architecture is essentially the same as that used by the earlier microprocessors. (OS/2 and the OS/2 Presentation Manager run in protected mode.) When I speak of the 8086 below, I'm talking about all members of the 8086 family, although the discussion is pertinent to only the real mode operation—not the protected mode—of the 80286 and 80386.

The 8086 can directly address 1 megabyte of memory. This 1 megabyte space address requires a 20-bit address. However, the 8086 is a 16-bit microprocessor, and all the registers within the 8086 are only 16 bits wide. So when the 8086 addresses memory, it must use two 16-bit registers to generate the address. These registers are called the segment register and the offset register. The segment register is shifted 4 bits to the left (effectively multiplying the value by 16) and added to the offset register to create a 20-bit address.

A segment register shifted 4 bits to the left is a physical address in the 8086 address space that marks the beginning of a segment. Offsets are then used to address memory within a segment. An 8086 program is most efficient when it does not change the segment registers very often and when it uses only 16-bit offset registers to address memory. The block of memory addressed by a 16-bit register based on a fixed segment register is called a "segment."

Most books on 8086 assembly-language programming state that a segment is 65,536 bytes (or 64 KB) long. That is the maximum size of a block of memory that can be addressed with a 16-bit register. When working with Windows, however, you'll find it helpful to think of segments as having a specific size ranging in length from 1 byte to 65,536 bytes. Windows' memory management is based somewhat on the protected mode architecture of the 80286, and this concept of specific segment size is more consistent with that architecture.

The 8086 microprocessor has four segment registers called CS (code segment), DS (data segment), SS (stack segment), and ES (extra segment). The CS register always points to the beginning of the segment that contains the currently executing code. The stack is located in the segment referenced by the SS register. Data is generally accessed using the DS register, but a program can override this and access data in any of the four segments addressed by the four segment registers. An 8086 program can also access data using an explicit 16-bit segment address and 16-bit offset address.

When a program calls a subroutine, that subroutine can be either in the same code segment as the code that calls it or in a different code segment. A call to a subroutine within the same code segment is known as an "intrasegment call," a "near call," or, sometimes, a "short call." This call involves changing only the 16-bit instruction pointer (IP) register that references the code. A call to a subroutine in another code segment is known as an "intersegment call," a "far call," or a "long call." Such a call requires that both the 16-bit CS register and the 16-bit IP register be changed. In effect, such a call requires a 32-bit address.

Similarly, a program can access data either in the segment referenced by the DS register or in another segment. When a program accesses data relative to the DS register, it requires only a 16-bit "near pointer" or "short pointer." A program that accesses data in another data segment requires both a 16-bit segment address and a 16-bit offset address. This address is called a "far pointer" or "long pointer."

A C program compiled with the Microsoft C Compiler can have one or more code segments and one or more data segments. The number of code and data segments in a program is indicated by the "memory model." The Microsoft C Compiler supports five memory models:

Memory Model	Code Segments	Data Segments
Small	1	1
Medium	Multiple	1
Compact	1	Multiple
Large	Multiple	Multiple
Huge	Multiple	Multiple

The huge memory model is the same as the large model except that individual data items can be larger than 64 KB—the compiler generates code to skip from one segment to another when accessing data.

In medium-model or large-model programs, all calls to functions in the program are far calls. In compact-model or large-model programs, the compiler must generate code that uses long pointers to access data. One of the data segments, called the "automatic data segment," contains the program's stack. In small-model or medium-model programs, the DS and SS registers normally reference the same data segment.

You can use any of the four memory models when programming for Windows. However, for reasons that we'll explore in Chapter 8, it is recommended that you use only the small and medium models. (Most of the programs in this book use the small model.) A Windows program thus normally contains only one data segment. If a Windows program requires access to more than 64 KB of data, it can use methods described in Chapters 8 and 9.

Windows programs are often characterized as "mixed model." Although the C compiler treats a Windows program as small model or medium model, the program can contain calls to functions outside its own code segment, and it can reference data outside its own data segment. The Microsoft C Compiler recognizes the two keywords near and far to accommodate mixed-model programming. These two keywords are very important in Windows programs. Let's see why.

Calling the 450 Windows Functions

Windows gives a program access to about 450 functions. Each of these functions has a name (such as *DispatchMessage* and *SendMessage*, which you saw in Figure 1-16). The interface to these functions is not a software interrupt, as an MS-DOS programmer might first suspect; rather, in assembly-language terms, the interface is a far intersegment call.

The compiler treats the Windows function as if it were a function located in a code segment other than the code segment that the program occupies. The function itself is located in one of the various modules that make up Windows. Parameters to the function are passed on the stack, which is the same mechanism used in passing parameters to functions within a program. This interface between an application program and Windows is sometimes known as the CALL-based API (application program interface).

One or more of the parameters to a Windows function can be a pointer to a data item located in the program's data segment or an address in the program's code segment. Because the Windows module that carries out the function request uses its own code and data segments, the parameter must be passed as a 32-bit far address consisting of a 16-bit segment address and a 16-bit offset address. With only one oddball exception, all pointers passed as parameters to Windows functions are far pointers.

The Pascal Calling Sequence

When a function is called from a C program (whether it is a function within the program or a Windows function), the compiler generates machine code that first pushes the function parameters on the stack and then calls the function using the assembly-language CALL instruction. Normally, implementations of C on 8086 microprocessors generate code that pushes the parameters on the stack from right to left—that is, beginning with the last parameter to the function. After the function returns, the code that called the function adjusts the stack pointer by adding to it a number equal to the number of bytes the code originally pushed on the stack.

An alternative calling sequence is called the Pascal calling sequence. Parameters are pushed on the stack from left to right, and the function itself adjusts the stack before returning to the caller. On the 8086, the Pascal calling sequence is somewhat more space-efficient. This is one reason that all Windows functions are implemented using the Pascal calling sequence. The Microsoft C Compiler recognizes the keyword *pascal* in a function definition or declaration and generates the appropriate code.

The Pascal calling sequence has some disadvantages. First, functions with a variable number of parameters are more difficult to implement. However, all Windows functions have a fixed number of parameters. Second, if your program calls a Windows function with an incorrect number of parameters, the program will probably crash.

Dynamic Linking

When a program makes a Windows function call, the compiler must generate machine code for a far intersegment call to the function located in a code segment in one of the Windows modules. This is a problem, because at the time your program is compiled and linked, the address of the Windows function is unknown, and it remains unknown until the program is actually running inside Windows.

Normally when you use LINK to link object (.OBJ) files produced by a compiler into one executable (.EXE) file, all the functions that the program calls must be resolved. The .EXE file must contain these functions. If LINK cannot find a particular function in one of the .OBJ files that it is linking, then it searches in library (.LIB) files specified on the LINK command line. If the function is not in the .LIB file, then LINK displays an error message indicating an "unresolved external" reference, which means that the program is calling a function but that LINK cannot find the function to include in the .EXE file.

When you link a Windows program, however, you don't use the normal LINK program. Instead you use a linker called LINK4.EXE that is provided with the Windows Software Development Kit. This linker allows a program to have calls to functions that cannot be fully resolved at link time. Only when the program is loaded into memory to be run are the far calls resolved. Windows resolves the calls by inserting the addresses of these functions into the code of your program. This process is known as "delayed binding" or "dynamic linking."

To properly prepare a Windows program for this process, the Windows program must be linked with special "import libraries" that are included in the Windows Software Development Kit. For a small-model Windows program, the import library is the file SLIBW.LIB, which contains a record for every Windows function that your program can call. The record indicates the Windows module that contains this function and, often, an "ordinal number," which is simply a positive number that corresponds to the function in the module.

For example, let's say your Windows program makes a call to the Windows GetMessage function. When you use LINK4 to link the program, LINK4 finds the GetMessage function listed in SLIBW.LIB. LINK4 can then determine from information in SLIBW.LIB that the GetMessage function is located in the Windows USER module and has an ordinal number of 108. LINK4 embeds this information in the program's .EXE file. When the program is run, Windows can link the call your program makes with the actual GetMessage function in the USER module.

The New Executable Format

The format of the MS-DOS executable file has no place to embed this dynamic link information. Windows programs instead use a format of .EXE file called the New Executable format, which is documented in the Windows Software Development Kit. Most files that are associated with Windows are either program modules or dynamic link library modules (often called simply "library modules" or "libraries"). Program files and library files both use the New Executable format.

Programs are tasks that run under Windows and can receive messages. Library modules contain routines that assist the programs in carrying out various chores. These library modules include the KERNEL, USER, and GDI modules and all the Windows device drivers.

Library modules provide functions that can be called from other library modules or from programs. To the module that contains the functions, the functions are known as "exports." These exported functions are identified in the New Executable format with a name and an ordinal number. The Entry Table section of the New Executable format indicates the address of each exported function within the module.

From the perspective of a Windows program, the library functions that a program calls are known as "imports." The far calls that a program makes to an imported function are identified in the various relocation tables. When Windows loads a program into memory, it must reconcile all references to imported functions in the program with the actual functions exported from the library modules.

A Windows program also usually contains at least one exported function—a function that is called from outside the program, generally from one of the library modules. This is the window function that receives messages to a window. The program must flag this function as exported so that Windows properly allows the function to be called from an external module. This process is covered in Chapter 8.

The EXEHDR program included with the Windows Software Development Kit is an MS-DOS program that displays much of the information available in the header section and relocation tables of the New Executable format file. You can run EXEHDR on the KERNELEXE, USER.EXE, and GDLEXE files to see the list of exported functions (with their ordinal numbers) contained in these modules. You can also run EXEHDR on Windows programs to determine what Windows functions they call. The imported functions are indicated by the library module name and an ordinal number. The EXEHDR output of the library module lets you reconcile those numbers with the function names.

Memory Management

The New Executable format used for Windows programs and libraries also contains information on each of the code and data segments in a program or library. In most cases, data segments of Windows programs and libraries are flagged as moveable, and code segments are flagged as moveable and discardable. As these flags indicate, Windows can move code and data segments in memory. Windows can also discard code segments from memory if additional memory space is required. If Windows discards a code segment from memory and later needs it again, it must reload the code segment from the original EXE file. Windows libraries and programs can also contain code segments that are flagged as "load on call," which means that the code segment will not be loaded into memory at all unless a function in the code segment is called from another code segment. Because of such sophisticated memory management, Windows can simultaneously run several programs in a memory space that might otherwise be inadequate for even one of the programs.

Although this approach to memory management is a natural when the 80286 or 80386 microprocessor is run in protected mode, normally it would be impossible in real mode. A stored segment address that references a code or data segment would become invalid if that segment were moved.

The implementation of this memory management scheme in real mode is probably the most spectacular accomplishment of the developers of Windows. It is sometimes also—as you might expect—a little tricky in actual practice. You must take certain precautions to ensure that your programs do not directly reference a moveable code or data segment. For example, when Windows dynamically links the far calls in one code segment to functions in another code segment, the calls actually reference a fixed area of memory called a "thunk." This thunk then references the moveable code segment. When Windows moves the moveable code segment referenced by this thunk, it must change the referenced address.

Windows programs must be compiled using a compiler that specifically accommodates certain requirements of Windows; one of these requirements is Windows' memory management. Again, we'll examine this process in more detail in Chapter 8. The HEAPWALK program included with the Windows Software Development Kit displays a segment-by-segment memory map within Windows. Although often used for debugging, HEAPWALK also functions as a tool for exploring memory organization in Windows.

Getting a Handle on Handles

The word *handle* will come up a lot as we begin to program for Windows. In the next chapter you'll encounter an "instance handle" and a "handle to a window." You'll also eventually encounter handles to resources such as icons, cursors, menus, and strings; handles to graphics tools such as bitmaps, pens, brushes, and fonts; and even handles to allocated memory.

A handle is a 16-bit unsigned number. In many cases the handle references an object (in the form of a data structure) located in a moveable section of memory. Although the memory can be moved, the handle remains constant. A program always obtains a handle from Windows (most often when calling a Windows function) and then uses the handle in subsequent calls to Windows functions. The actual value of the handle is unimportant to your program, but the Windows module that gives your program this handle knows how to use it to reference memory.

The Big Header File

At the top of every Windows program is the preprocessor directive:

#include <windows.h>

WINDOWS.H is a large (87 KB) header file supplied with the Windows Software Development Kit. If your Windows programs seem to take longer to compile than normal C programs, you can justifiably blame it on the size of WINDOWS.H. This header file is not only large but is also extremely important. You should treat WINDOWS.H as a part of the Windows documentation. You'll probably want to print out a copy or keep the file within easy access of a text editor or file browser.

WINDOWS.H contains more than 1250 #define statements. Most of these simply define a text identifier as a constant. The C compiler replaces occurrences of this identifier with the constant during preprocessing. For example, in the next chapter you'll encounter the identifier WM_QUIT, which WINDOWS.H defines as:

#define WM_QUIT 0x0012

Almost every constant used in Windows is identified by name in WINDOWS.H. When programming for Windows, you almost never have to use numbers for predefined codes.

Some #define statements in WINDOWS.H seem a little strange, for instance:

#define PASCAL pascal

and:

#define FAR far

The lowercase *pascal* and *far* are keywords in Microsoft C. Although *pascal* may show up in some other implementations of C, it is certainly not part of the standard language. The *far* keyword is a necessary addition to C compilers on the PC and compatibles because of the segmented architecture of the 8086-family microprocessors. It's best to use the uppercase PASCAL and FAR in your programs rather than the lowercase keywords themselves. If you ever need to adapt your program for another C compiler or even—however unlikely this may seem at the present—for a version of Windows that runs on another microprocessor, you'll find that it's much easier to change one WINDOWS.H file than lots of C source code files.

WINDOWS.H also contains more than 100 typedef declarations, of which more than 20 are declarations of data structures used for passing information between a Windows program and Windows. This is one simple typedef declaration from WINDOWS.H:

typedef int BOOL

This declares the data type called BOOL as a synonym for an *int* (an integer). Here are some other *typedef* declarations:

WINDOWS.H Type	СТуре	
BYTE	unsigned char	
WORD	unsigned short	
LONG	signed long	
DWORD	unsigned long	
PSTR	char •	
NPSTR	char near •	
LPSTR	char far •	

Because handles are so common in Windows programs, each type of handle has its own typedef definition. Here are some of them:

WINDOWS.H Type	Handle Type	
HANDLE	Generic (WORD)	
HWND	To a window	
HDC	To a device context	
HMENU	To a menu	
HICON	To an icon	
HCURSOR	To a cursor	
HBRUSH	To a brush	
HPEN	To a pen	
HFONT	To a font	

The *typedef* statements for structures usually include both a name that you can use as a synonym for the structure and a tag name. The *typedef* statement for the Windows message structure is:

```
typedef tagMSG
(

HWND hWnd;
WORD message;
WORD wParam;
LONG lParam;
DWORD time;
POINT pt;
}
MSG;
```

(The POINT data type is another structure.) If you want to define a variable within your program (named msg, for example) as a structure of type MSG, you use the definition:

```
MSG msg ;
```

WINDOWS.H also includes type declarations for near pointers and far pointers to the structures. For example:

```
typedef MSG FAR *LPMSG
```

This declares the data type LPMSG as a far (or long) pointer to the data type MSG.

WINDOWS.H also contains declarations of all the approximately 450 Windows functions. This is one of them:

```
BOOL FAR PASCAL GetMessage (LPMSG, HWND, unsigned, unsigned) ;
```

With what you've learned so far, this declaration should look almost comprehensible. The function GetMessage returns a value of type BOOL. Like all Windows functions, GetMessage is declared as a FAR PASCAL function, which is really a far pascal function. Based on this

function declaration in WINDOWS.H, the Microsoft C Compiler will generate the correct code for a *far pascal* function.

The compiler checks to see that the number of parameters you pass to the function and their data types are the same as those in the WINDOWS.H declaration of the function. For example, if you attempt to call <code>GetMessage</code> with only three parameters, you'll get a message from the compiler. The first parameter to <code>GetMessage</code> has a data type of LPMSG, which is a far pointer to a MSG structure. If you tried to use an integer instead, you'd get another message from the compiler. These warning messages are important when you're using functions that are implemented with the Pascal calling sequence. Unless the correct number of words are pushed on the stack, the program will probably crash. It's a good idea to compile Windows programs with a warning level of 2. If you get a warning message from the C compiler regarding parameters to a Windows program, it usually indicates a problem.

In keeping with C programming tradition, most of the constants and *typedef* names in WINDOWS.H are uppercase. The 450 Windows function names mix uppercase and lowercase in a way that breaks each function name into separate words. Some function names are quite long, but the use of mixed case makes them easily readable and almost self-explanatory. The Windows function with the longest name (26 letters) is *IsClipboardFormatAvailable*. If this sounds to you like a Windows function that determines if the clipboard is holding data of a particular data format, you're absolutely correct.

To Cast or Not to Cast

The function declaration of GetMessage in WINDOWS.H is:

```
BOOL FAR PASCAL GetMessage (LPMSG, HWND, unsigned, unsigned) ;
```

We'll use this function in the next chapter. We'll first define a structure variable of type MSG like this:

```
MSG msg ;
```

and then call the function using the address of msg as the first parameter and 0 (or NULL) for each of the other three parameters:

```
GetMessage (&msg, NULL, 0, 0)
```

Normally, the expression *Emsg* in a small-model or medium-model program would generate a near 16-bit pointer to the structure. However, based on the function declaration in WINDOWS.H, the C compiler will generate code that pushes a far 32-bit pointer on the stack when preparing to call *GetMessage*. The *GetMessage* function declaration in WINDOWS.H indicates that the first parameter is a far pointer, so that's what the C compiler uses.

In some Windows programs, you will see near pointers explicitly cast into far pointers, like this:

```
GetMessage ((LPMSG) &msg, NULL, 0, 0)
```

The cast of the address of msg to a far pointer of type MSG is unnecessary, and you should probably avoid the practice. Unnecessary casting can be dangerous. For example, suppose a function was declared like this:

```
SomeFunction (DWORD far *) ;
```

and you defined a variable of type DWORD (unsigned long integer):

```
DWORD dw ;
```

You want to pass the address of this variable to the function. But you might forget the \mathcal{E} :

```
SomeFunction (dw) ;
```

If you compile with warning level 1 or higher, you'll get a message from the compiler about the problem here. But if you use a cast and forget the \mathcal{E} , the function call will look like this:

```
SomeFunction ((DWORD far *) dw) ;
```

This will never cause a warning message, even though it's wrong.

Debugging Windows programs is no great joy. You'll be in better shape if you let the compiler find some of the errors beforehand. Don't explicitly cast unless you need to.

Hungarian Notation

Windows programmers often use a notation for variable names that at first looks peculiar. The variable name is given an initial lowercase letter or letters that denote the data type of the variable, followed by a descriptive name in mixed uppercase and lowercase—for example:

```
WORD wBufferSize ;
DWORD dwFileSize ;
```

The idea here is that the variable name itself reminds you of the data type of the variable. This is often called Hungarian notation in honor of the legendary Microsoft programmer Charles Simonyi.

Although it is very simple, Hungarian notation is enormously helpful in avoiding dumb errors. If you happen to code the assignment statement:

```
wBufferSize = dwFileSize ;
```

the error is much more evident than if you had used normal C variable names like buffersize and filesize:

```
buffersize = filesize;
```

Hungarian notation helps you avoid errors before they reach the compiler. You'll probably like Hungarian notation so much that you'll start using it in your MS-DOS C programs as well.

	The notation	in this	book's sampl	e programs	uses these	prefixes:
--	--------------	---------	--------------	------------	------------	-----------

Prefix	Data Type
c	char
by	BYTE (unsigned char)
n	short or int
x	short (when used as x coordinate or dimension)
y	short (when used as y coordinate or dimension)
i	int
b	BOOL (int)
w	WORD (unsigned int)
h	HANDLE (unsigned int)
1	LONG (long)
dw	DWORD (unsigned long)
fn	function
s	string
SZ	string terminated by NULL (0)

These can also be prefaced by another letter or letters indicating a pointer:

Prefix	Pointer Type	
p	pointer	
lp	long (or far) pointer	
np	near (or short) pointer	

For example, the variable *lpszCmdLine* is a far pointer to a NULL-terminated string. The variable might be defined as:

```
char far *lpszCmdLine ;
```

LPSTR lpszCmdLine ;

Although some programmers use the prefix rec (record) to indicate a structure variable, I have tended to use an abbreviation of the structure type—for example, msg for a structure of type MSG, or pt for a structure of type POINT. If the program has several POINT structures, the names can be prefixed with pt, such as ptUpperLeft and ptCurrent.

The Learning Curve

OF:

Although Windows is an easy system for users, it has the reputation of being a difficult system for programmers. I won't claim that learning to program for Windows is easy. No system that contains 450 function calls can be easy, even for a Windows programmer with years of

experience. There may never come a time when you'll be able to do Windows programming without consulting the Programmer's Reference. My copy permanently rests on the top ledge of my keyboard, leaning against the PC right under the display.

If you have a background in a system such as MS-DOS where programs are generally linear and organized in a top-down fashion, Windows programming will at first seem bizarrely convoluted. The structure of a Windows program is turned inside out. It's the messaging that makes the difference. Where once your program inquired, now it is informed. Where once you wrote to the screen, now you invalidate your client area.

When I first started learning Windows programming, I decided to do what I had always done when learning a new operating system or a new language—to write a simple "hex dump" program to display the contents of a file. In a normal environment, such a program involves rudimentary file I/O and screen output formatting. However, my Windows hex dump program turned into a monster. It required that I learn about menus, dialog boxes, scroll bars, and the like. As a first Windows program, it was definitely a mistake, demanding that I absorb too much all at once.

Yet when this program was finished, it was quite unlike any hex dump program I had written before. Rather than obtain the filename from a command line, WINDUMP (as I called it) presented a list box showing all the files in the current directory. Rather than write its output to the screen in a simple teletype fashion, WINDUMP had scroll bars so I could move to any part of the file. As an extra bonus, I could even run two copies of WINDUMP to compare two files side by side. In short, WINDUMP was the first hex dump program I wrote that I was actually proud of.

What you have to ask yourself is this: Do I want my programs to use a more modern and productive user interface, one that includes menus, dialog boxes, scroll bars, and graphics? If you answer yes, then the question becomes: Do I want to write all this menu, dialog box, scroll bar, and graphics code myself? Or would I rather take advantage of all the code already inside Windows for creating these elements? In other words, is it easier to learn how to use 450 function calls or to write them yourself?

If you're going to write your own user interface logic, you had better close this book and get to work right away. Meanwhile, the rest of us are going to learn how to make a window.

Chapter 2

Creating and Displaying Windows

Perhaps the scariest aspect of beginning Windows programming is the overhead required to create a simple window on the display. But creating a window is a prerequisite for nearly everything else you do in Windows.

This chapter is restricted to the creation and display of various types of windows. We'll begin with a program that does nothing at all and slowly build it up over the course of the chapter. As we build on this program, I'll also compare it with a normal C program that does something roughly equivalent. We'll abandon this normal C program when it becomes apparent that it's not in the same league and, in fact, really not even playing the same game.

FROM SOURCE CODE TO EXECUTABLE

The simplest normal C program (let's call it NOTHING.C) looks like this:

Using the Microsoft C Compiler, you compile and link this little program with the following command line:

cl nothing.c

The CLEXE compiler creates a NOTHING.OBJ object module file and then loads LINK.EXE, which links the object module with the SLIBC.LIB small-model C library to create

NOTHING.EXE, ready to execute. When you run NOTHING.EXE under MS-DOS, you'll immediately return to the MS-DOS command line prompt.

The simplest Windows program in C (also called NOTHING.C) is a few lines longer and is shown in Figure 2-1. After we create the NOTHING.EXE file (not a one-step process), we can run it under Windows. The program will end almost as soon as it begins.

Figure 2-1. The simplest Windows program: NOTHING.C

The first line in the Windows version of our NOTHING.C program is a **include* statement for WINDOWS.H, the header file required for every Windows program. Even a program of this size needs WINDOWS.H for the definitions of PASCAL, HANDLE, LPSTR, and FALSE.

Just as every C program has a function called *main* that is the entry point to the program, every Windows program coded in C has a function called *WinMain*. Aside from some start-up code inserted in your program during linking, *WinMain* is the entry point to the Windows program. From the definition of *WinMain*, you can tell that it's called from the start-up code with a Pascal calling sequence and that it returns an integer on exit. It is not declared FAR because it is called from the start-up code, which for a small-model program is in the same segment as *WinMain*.

WinMain receives four parameters from Windows. (More precisely, the C start-up code obtains these items from Windows and passes them to WinMain.) Although this small program doesn't use these parameters, the Pascal calling sequence requires that they be explicitly listed. You can use whatever names you like for these four parameters, but the ones shown here have become fairly standard.

The h that begins the parameter names hInstance and hPrevInstance stands for "handle." (I warned you in Chapter 1 that you'll be encountering lots of handles.) The data type HANDLE is defined in WINDOWS.H as a WORD, which in turn is defined as a 16-bit unsigned short integer.

The hInstance parameter is an "instance handle." This is a number that uniquely identifies the program when it is running under Windows. As you know, you can run multiple

copies of the same program under Windows. Each copy is called an "instance," and each has a different *hInstance* value. This *hInstance* value is equivalent to a "task ID" or "process ID" common in multitasking operating systems.

The hPrevInstance parameter is the instance handle of the most recent previous instance of the same program that is still active. If hPrevInstance is NULL (or 0) on entry to WinMain, then no other copies of the program are currently executing under Windows.

The *lpsz* prefix that begins *lpszCmdLine* indicates that this parameter is a "long pointer to a string terminated with a zero." (In normal MS-DOS programming, this is often called an ASCIIZ string.) The variable is declared with a data type of LPSTR. LPSTR is defined with a *typedef* statement in WINDOWS.H as a *char far* *, or a far pointer to a character string. This character string is a command line argument to NOTHING.

For example, if you run NOTHING from the Windows MS-DOS Executive program by choosing either Run or Load from the File menu, you can type the name of the program in a dialog box. If you enter the program name with the following command line:

NOTHING will happen

then *lpszCmdLine* will point to a string containing "will happen" terminated with a 0. If you simply run or load this program from the MS-DOS Executive file list without using the dialog box, then *lpszCmdLine* will point to a 0 byte.

The nCmdShow parameter is an integer indicating how the program is initially to be displayed in Windows. This number is assigned by the program that makes the MS-DOS EXEC function call to execute your program. Programs do not often need to examine this number, but they can if they want. In most cases the number is either a 1 or a 7. But it's best not to think of the value as a 1 or a 7. Rather, think of the value as SW_SHOWNORMAL (which is defined in WINDOWS.H as 1) or SW_SHOWMINNOACTIVE (defined as 7).

If you run the program from the MS-DOS Executive by pressing Enter, double-clicking the filename with the mouse, or selecting Run from the File menu; or if the program is included in the run section of WIN.INI; or if you run the program by entering the name as a parameter to WIN.COM like this:

WIN NOTHING

then *nCmdShow* is set to SW_SHOWNORMAL. However, if you "load" the program as an icon from the MS-DOS Executive by pressing Shift-Enter or by choosing Load from the Load menu, or if the program is loaded because it is listed in the *load* section of WIN.INI, then *nCmdShow* is set to SW_SHOWMINNOACTIVE.

In NOTHING.C, WinMain returns the value FALSE, which is defined in WINDOWS.H as 0. This is normal for Windows programs that terminate prematurely.

Compiling NOTHING.C

We compiled our normal C program with the command:

```
cl nothing.c
```

We'll compile most of our Windows programs with a more extensive command line that looks like this:

```
cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp nothing.c
```

The number of command line switches may seem a little disturbing. Let's examine each of them and see why we want it.

The -c switch causes CLEXE to compile the NOTHING.C program and create NOTHING.OBJ but not to link it. Without this switch, CLEXE runs LINK.EXE to link the program as well. You can't use LINK.EXE with Windows programs. You must use LINK4, the Windows linker, instead.

The -D switch defines the identifier LINT_ARGS. The definition of this identifier enables parameter type checking on standard C library functions when you include the header file with the function declarations. This allows the C compiler to flag problems in your code before they become bugs.

The -Gsw switch is a combination of two switches, -Gs and -Gw. The -Gs switch removes a call to a function that checks for stack overflow. The C compiler normally inserts this call on entry to each internal function. A stack overflow generates a Windows FatalExit call. You will generally not know that this call has been generated unless you have the debugging version of Windows installed with an external terminal connected to COM1. It's best simply to be sure that you are using a sufficient stack.

The -Gw switch is the Windows switch that inserts special prolog and epilog code in each function defined as *far* in your program. This prolog and epilog code (discussed in depth in Chapter 8) aids Windows in moving code and data segments in memory.

The -Os switch optimizes for smaller code size. (The default is optimization for faster execution speed.) In a multitasking environment with limited memory, optimizing for smaller code size is a matter of politeness. (For easier source-level debugging, often the -Od switch is used instead to disable all optimization.)

The -W2 switch gives additional compiler warning messages beyond the default -W1 level. You should make every effort to write programs that show no warning messages when you compile with -W2. (Every program in this book meets this criterion.) Windows will not tolerate sloppy C programming. You can get away with careless code when programming in C for MS-DOS, but similarly careless code will lead to nasty bugs in Windows programs. This switch also saves time in other ways. If you use the -W2 switch and misspell the name of a Windows function, the compiler displays a warning message. If you use the -W1 switch, you won't know about the misspelling until later, when LINK4 can't find the function.

The -Zp switch packs structures. Normally, the fields of C structures are aligned on integer boundaries. A structure that looks like this:

```
struct
{
    char a ;
    int b ;
}
sample ;
```

normally defines 4 bytes of storage for the structure *sample* because the compiler inserts an extra byte after the variable *a*. When compiled with the -Zp switch, the structure takes up only 3 bytes. All structures used in Windows are packed, so the -Zp switch is required.

You may also have seen the switch -Asnw in the CL command line for compilations of other sample Windows programs. The -As and -An switches indicate small code and near data, which together define a small-model program, the default. The -Aw switch causes the compiler to assume that DS (the data segment) is not equal to SS (the stack segment). The -Asnw switch is *not* required for compiling Windows programs. It is required for compiling Windows dynamic link libraries, a subject we won't encounter until Chapter 18.

The switches absolutely required for a small-model compilation of a Windows program are:

```
-c -Gw -Zp
```

In addition, whenever floating-point math is used within a Windows program, the -FPa switch is required. This switch causes the "alternate" floating-point library (rather than the floating-point libraries that use the 8087 math coprocessor and 8087 emulation) to be linked with the program. The 8087 and emulation libraries cannot be used in Windows programs.

The Definition File and Linking

In addition to the C source code, another file is required for Windows programs. It is called a "module definition file" and has the extension .DEF. The definition file aids the LINK4 linker in creating the .EXE file by telling it the characteristics of the program's code and data segments, the size of the program's local data heap (from which the program can allocate memory), and the size of the program's stack. This information becomes part of the header section of the New Executable file format. The NOTHING.DEF file is shown in Figure 2-2.

```
NAME NOTHING
DESCRIPTION 'Do-Nothing Program for Windows (C) Charles Petzold, 1987'
STUB 'WINSTUB.EXE'
CODE MOVEABLE
DATA MOVEABLE MULTIPLE
HEAPSIZE 1024
STACKSIZE 4096
```

Figure 2-2. The NOTHING.DEF file

The NAME line defines NOTHING as a Windows program (rather than a Windows dynamic link library) and gives it a module name, which should be the name of the program's .EXE file.

The DESCRIPTION line simply inserts some text into the .EXE file. This is an excellent place for a copyright notice or version information.

The STUB is a program that is inserted into the .EXE file to be executed when anyone attempts to run NOTHING.EXE from the MS-DOS command level. The WINSTUB.EXE program included with the Windows Software Development Kit simply displays the message "This program requires Microsoft Windows" and terminates.

The CODE statement indicates that the program's code segment is MOVEABLE, which means that Windows can move the code segment to another location in memory if it needs to consolidate blocks of free memory. The MOVEABLE option also makes the code "discardable," which means that Windows can discard the code segment from memory and later reload it from the .EXE file. This is the normal option for Windows programs. If you follow proper Windows programming practice, you will not (in theory) encounter any problems when Windows moves your code.

The DATA statement indicates that we want the data segment to be MOVEABLE and MULTIPLE. Again, we are giving Windows permission to move the data segment in memory if necessary. We use MULTIPLE to request that each instance of the program get its own separate data segment. This is necessary because the data segment contains the program's stack and other data items that must be separate for each instance. The code segment, on the other hand, is shared by all instances of the program.

The HEAPSIZE line specifies the amount of extra local memory (memory in the program's own data segment) that will be available for allocation. The value depends on what the program needs. NOTHING doesn't need to allocate any local memory, but we threw in a small value nonetheless. Windows can expand a program's local heap if necessary.

The STACKSIZE line specifies the size of the stack. The value of 40% bytes is a minimum recommended value. You'll want a bigger stack size if your program has recursive functions or large nonstatic variables.

The Windows linker is called LINK4 and reads the NOTHING.OBJ and NOTHING.DEF files to create the NOTHING.EXE file that you can run under Windows. The command line to link NOTHING is:

link4 nothing, /align:16, /map, slibw, nothing

LINK4 has five parameters separated by commas. The first (NOTHING) is the name of the object module file created by the CL compiler. The .OBJ extension is assumed.

The second parameter is the name of the .EXE file, which by default is the same as the first .OBJ file but with a .EXE extension, so LINK4 will name it NOTHING.EXE. We also include a LINK4 switch /align:16 here, which aligns code and data segments in the .EXE file on 16-byte boundaries for space efficiency.

The third parameter is the name of the map file, which by default takes the same name as the .EXE file with a .MAP extension. The /map switch tells LINK4 to create the map file.

The fourth parameter is the name of the Windows SLIBW.LIB import library, which allows LINK4 to resolve all references to Windows functions within the program. (We haven't used any yet, but the start-up code has a few.) LINK4 builds a relocation table in the .EXE file that specifies the name of the module and the function name (or ordinal number) for each Windows function call within the program. Windows uses this relocation table for dynamic linking. This SLIBW.LIB library also contains the start-up code for Windows C programs. (If a small-model Windows program uses regular C library functions, floating-point math, or long integer manipulation, LINK4 also accesses the SLIBC.LIB, SLIBFA.LIB, and LIBH.LIB libraries. The compiler inserts the names of these libraries into the .OBJ file so you don't have to list them when running LINK4.)

Finally, the fifth parameter to LINK4 contains the name of the module definition file, NOTHING.DEF. The .DEF extension is assumed.

Making the Program

Because the combination of compiling and linking a Windows program is somewhat complex, Windows programmers usually take advantage of MAKE. A "make file" is constructed that shows a "target file" on the left, a colon, and "dependent files." If the file date and time of the dependent files is later than that of the target file, then MAKE executes the indented command lines that follow. A make file by convention has no extension. The NOTHING make file is shown in Figure 2-3.

```
nothing.obj : nothing.c
cl -c -D LINT-ARGS -Gsw -Os -W2 -Zp nothing.c
nothing.exe : nothing.obj nothing.def
link4 nothing, /align:16, /map, slibw, nothing
```

Figure 2-3. The NOTHING make file

Executing:

MAKE NOTHING

on the MS-DOS command line runs CLEXE and LINK4.EXE, to create the executable NOTHING.EXE file. Now you can go into Windows and execute NOTHING.EXE from the MS-DOS Executive. The mouse cursor briefly changes to an hourglass as Windows loads the program, but nothing happens. The program terminates soon after *WinMain* begins execution.

A PROGRAM WITH A WINDOW

In regular C programming, to step up from a program that does nothing to a program that displays a message, you simply add a single line to the program.

This program prints the text "Hello, world" on some teletype device (like the video display under MS-DOS) and then terminates. However, the Windows environment is obviously much more complex than the simple teletype device involved with the simple "Hello, world" program. A Windows program cannot simply display something on the screen. The Windows program must first build a window for itself.

Let's write a Windows program somewhat equivalent to the simple C program shown above and call it WELCOME1. This program will display a normal overlapped window with the title "Welcome to Windows" in its caption bar. The program will then terminate, just like the "Hello, world" program. All the source code (C file, module definition file, and make file) for WELCOME1.C is shown in Figure 2-4.

```
welcomel.obj : welcomel.c
   cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp welcomel.c

welcomel.exe : welcomel.obj welcomel.def
   link4 welcomel, /align:16, /map, slibw, welcomel
```

Figure 2-4. The WELCOME1 program

(continued)

Figure 2-4. Continued

```
if (!hPrevInstance)
           wndclass.style
                                     = CS HREDRAW | CS VREDRAW ;
           wndclass.lpfnWndProc = WndProc ;
           wndclass.cbClsExtra = 0;
           wndclass.cbWndExtra
                                     = 0 ;
           wndclass.hInstance = hInstance;
wndclass.hIcon = LoadIcon (NULL, IDI_APPLICATION);
wndclass.hCursor = LoadCursor (NULL, IDC_ARROW);
           wndclass.hbrBackground = GetStockObject (WHITE BRUSH) ;
           wndclass.lpszMenuName = NULL;
wndclass.lpszClassName = szAppName;
           if (!RegisterClass (&wndclass))
                 return FALSE :
     hWnd = CreateWindow (szAppName,
                                                 /* window class name
                                                  /* window caption
                       "Welcome to Windows",
                       WS OVERLAPPEDWINDOW,
                                                   /* window style
                       CW USEDEFAULT,
                                                   /* initial x position
                       0,
                                                   /* initial y position
                       CW USEDEFAULT,
                                                   /* initial x size
                       0,
                                                   /* initial y size
                       NULL,
                                                  /* parent window handle */
/* window menu handle */
/* program instance handle */
                       NULL,
                       hInstance,
                       NULL) ;
                                                  /* create parameters
     ShowWindow (hWnd, nCmdShow) ;
     UpdateWindow (hWnd) :
     return FALSE ;
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
             hWnd ;
     unsigned iMessage ;
     WORD
               wParam ;
     LONG
               1Param ;
     return DefWindowProc (hWnd, iMessage, wParam, lParam) ;
```

```
NAME
               WELCOME1
DESCRIPTION
               'Welcome to Windows -- Program No. 1 (C) Charles Petzold, 1987'
STUB
               'WINSTUB.EXE'
CODE
               MOVEABLE
DATA
               MOVEABLE MULTIPLE
HEAPSIZE
               1024
STACKSIZE
               4096
EXPORTS
               WndProc
```

This program is a big jump up from NOTHING.C. WinMain has grown substantially, and a second function, called WndProc, is now present.

WELCOME1's WinMain function shows the code necessary to create and display a window on the screen. This job can be divided into five steps:

- 1. Set up a window class structure.
- 2. Call the RegisterClass function to register that window class.
- Call the CreateWindow function to create a window based on the registered window class.
- 4. Call the ShowWindow function to display that window on the screen.
- 5. Call the UpdateWindow function to paint the client area of the window.

The WinMain function in WELCOME1 then returns FALSE to end the program. Conceptually, the most difficult part of this code comes right at the beginning with this thing called a "window class." So let's tackle that.

The Window Class

The windows that you create in a Windows program can take on a variety of different characteristics. The windows can be different sizes, be placed in different areas on the display, have different text in their caption bars, have different background colors, use different mouse cursors, and so forth.

Every window that you create in a Windows program using *CreateWindow* must be based on a window class. Some of the characteristics of a window are specified as parameters in the *CreateWindow* function call, and others are specified in the window class structure. The characteristics of a window are divided like this so that multiple windows can be created based on the same window class.

Every window class has a name. If you register only one window class in your program, you can use the name of the program as the name of the window class. The WELCOME1 program uses the variable <code>szAppName</code> (which contains the text string "Welcome1") to provide this name. You'll note that the first parameter to <code>CreateWindow</code> is the name of the window class on which the window being created is based.

When you register a window class, the class becomes available to all programs running under Windows. You must avoid conflicts between the names of the window classes that your program registers and those that other programs may use. For this reason, if you register multiple window classes, the name of each window class should begin with the name of your program.

The window class is a data structure. WINDOWS.H contains a *typedef* statement that defines the name WNDCLASS as the window class structure. You define a structure variable (called *wndclass*, for example) of type WNDCLASS using the line:

WNDCLASS wndclass ;

You then set the fields of this structure and give Windows a far pointer to the structure by calling:

```
RegisterClass (&wndclass) ;
```

Windows then makes a copy of the structure. As I mentioned, this window class becomes available to all programs running under Windows, which means that only the first instance of a program needs to register the class. Later instances can simply refer to the existing window class when calling *CreateWindow* to create a window based on that class.

For this reason, WELCOME1 registers the "Welcome1" window class only if it is the first instance of WELCOME1 to be running under Windows. WELCOME1 can determine its "instance status" by checking the value of hPrevInstance, which it does with the first statement in WinMain:

```
if (!hPrevInstance)
```

If hPrevInstance is NULL, then no other copies of WELCOME1 are currently running, so the program proceeds to set up the window class structure and register the window class.

The WNDCLASS structure has 10 fields. The first field is the window class style:

```
wndclass.style = CS_HREDRAW | CS_VREDRAW ;
```

CS_HREDRAW and CS_VREDRAW are identifiers defined in WINDOWS.H along with several other identifiers that begin with the letters CS ("class style"). Each of these CS identifiers functions as a bit flag. That is, the various CS identifiers are defined as 0x0001, 0x0002, 0x0004, 0x0008, 0x0010, and so forth. When you use two or more of these identifiers, they must be combined with the C bitwise OR operator. Many of the identifiers in WINDOWS.H work in this fashion.

The CS_HREDRAW and CS_VREDRAW flags tell Windows that the entire client area of the window must be redrawn if either the horizontal size (CS_HREDRAW) or vertical size (CS_VREDRAW) of the window changes. You may be able to eliminate one or both of these identifiers in some programs you write. We'll also write some programs in later chapters that use other class style flags. These two are the most common.

The second field is the most important field of the window class structure. This specifies the "window function" that processes messages to all windows that are created based on this window class. The window function determines how the window responds to input and what the window does. In WELCOME1, this field is set to the function named *WndProc*:

```
wndclass.lpfnWndProc = WndProc ;
```

The *lpfn* prefix of the field name means "long pointer to a function." It is set to the address of the *WndProc* function, which is located near the end of WELCOMELC. It doesn't appear to be a particularly complex function at the moment, I'll discuss window functions more in this chapter and much much more in chapters to come.

The next field is cbClsExtra. (The cb prefix stands for "a count of bytes.") This field reserves some extra space at the end of the copy of the window class structure that Windows stores. For most purposes it can be set to 0:

```
wndclass.cbClsExtra = 0 ;
```

Windows also stores a data structure for every window. The next field reserves some extra space at the end of all data structures for windows based on this class:

```
wndclass.cbWndExtra = 0;
```

Zero is normal.

The next field is the instance handle of the program. This is passed to the program as a parameter to WinMain:

```
wndclass.hInstance = hInstance;
```

The next two fields are named *hIcon* and *hCursor*. The *h* prefix indicates these are handles. A program's icon is the small bitmapped picture that appears when the program is minimized. Later in this book we'll create customized icons for programs. Right now, we'll take an easy approach and use a predefined icon:

```
wndclass.hlcon = LoadIcon (NULL, IDI_APPLICATION) ;
```

IDI_APPLICATION is an identifier from WINDOWS.H. The standard icon it refers to is simply a black frame on a white background. The icon itself is stored in Windows, and the *LoadIcon* function returns a handle to it. We don't really care about the value of this handle. We simply use it to set the value of this field. Windows can properly access the icon specified here by using the handle.

Similarly, the next field is a handle to a mouse cursor:

```
wndclass.hCursor = LoadCursor (NULL, IDC_ARROW) ;
```

This specifies the shape the mouse cursor will take when it is positioned over the client area of all windows created based on this class. The IDC_ARROW cursor is the standard tilted arrow cursor.

The next field specifies the background color of the client area of windows created based on this class. The prefix *hbr* means "handle to a brush." *Brush* is a graphics term that refers to a colored pattern of pixels used to fill an area. Windows has several standard, or "stock," brushes. The *GetStockObject* call shown here returns a handle to a white brush:

```
wndclass.hbrBackground = GetStockObject (WHITE_BRUSH) ;
```

This means the background of the client area of the window will be solid white, which is a common choice.

The next field specifies the window class menu:

```
wndclass.lpszMenuName = NULL ;
```

WELCOME1 doesn't have a menu. If it did, the menu would have a name, and the name would appear in quotation marks. The NULL (or 0) indicates no menu.

Finally, the window class structure contains the name of the window class. This is the name stored in the variable szAppName.

```
wndclass.lpszClassName = szAppName ;
```

Now that the window class structure is filled with numbers, we can register it:

```
if (!RegisterClass (&wndclass))
    return FALSE;
```

The parameter to RegisterClass is a far pointer to the address of the window class structure. The compiler will translate the near address of the window class structure (Gwndclass) to a far address because the RegisterClass declaration in WINDOWS. Hindicates that the parameter is a far pointer. RegisterClass returns a 0 if Windows cannot register the class (perhaps because of insufficient memory). To account for this possibility, the program terminates if RegisterClass fails.

Creating the Window

The window class defines general characteristics of a window, thus allowing the same window class to be used for many different windows. When you actually create the window by calling *CreateWindow*, you specify more detailed information about the window. Rather than use a data structure like *RegisterClass*, the *CreateWindow* call requires all the information to be passed as parameters to the function. Here's the *CreateWindow* call in WELCOME1:

```
hWnd = CreateWindow (szAppName,
                                     /* window class name
              "Welcome to Windows",
                                     /* window caption
                                                                */
              WS_OVERLAPPEDWINDOW,
                                      /* window style
                                                                */
              CW_USEDEFAULT.
                                      /* initial x position
                                                                */
                                      /* initial y position
                                                                */
              CW_USEDEFAULT,
                                      /* initial x size
                                      /* initial y size
                                                                ./
              NULL,
                                     /* parent window handle
              NULL,
                                     /* window menu handle
                                                                */
              hInstance,
                                      /* program instance handle */
              NULL) ;
                                      /* create parameters
                                                                */
```

Although we need to register a window class only for the first instance of a program, we create a window separately for each instance. Each instance has its own window, and all the windows are based on the same window class. Later in this chapter we'll create multiple windows within the same program, again all based on the same window class.

The parameter marked "window class name" is szAppName, which contains the string "Welcome1"—the name of the window class we just registered. This is how the window is associated with the window class.

For this first program, we are creating a normal overlapped window with a caption bar, a system menu box to the left of the caption bar, minimize and maximize icons to the right of the caption bar, and a thick window frame. That's a standard style of windows, and it has the WINDOWS.H name WS_OVERLAPPEDWINDOW, which appears as the "window style" parameter. The "window caption" is the text that will appear in the caption bar.

The parameters marked "initial x position" and "initial y position" specify the initial position of the upper left corner of the window relative to the upper left corner of the screen. By using the identifier CW_USEDEFAULT as the "initial x position," we're indicating we want Windows to use the default position for an overlapped window. Windows positions successive overlapped windows at stepped horizontal and vertical offsets from the upper left corner of the display. Specifying 0 for the initial y position here indicates to Windows to use the default positioning logic for the y coordinate also. Similarly, the "initial x size" and "initial y size" parameters specify the width and height of the window. The CW_USEDEFAULT and 0 parameters indicate we want Windows to use a default size for the window, which extends to the right side of the display and above the icon area at the bottom of the screen.

The parameter marked "parent window handle" is set to NULL because this window has no parent window. The "window menu handle" is also set to NULL because the window has no menu. The "program instance handle" is set to the instance handle passed to the program as a parameter of WinMain. Finally, a "create parameters" pointer is set to NULL. You could use this pointer to access some data that you might later want to reference in the program.

The *CreateWindow* call returns a handle to the created window. This handle is saved in the variable *hWnd*. Every window in Windows has a handle. Your program uses the handle to refer to the window. Many Windows functions require *hWnd* as a parameter so that Windows knows to which window the function applies. If a program creates many windows, each has a different handle. The handle to a window is one of the most important handles a Windows program will (pardon the expression) handle.

After the *CreateWindow* call returns, the window has been created internally in Windows. However, the window will not yet appear on the display. Two more calls are needed. The first is:

```
ShowWindow (hWnd, nCmdShow) ;
```

This uses both the handle to the window just created and the *nCmdShow* parameter passed to *WinMain*, which determines how the window is to be initially displayed on the screen. If *nCmdShow* is SW_SHOWNORMAL, the window is displayed normally. If *nCmdShow* is SW_SHOWNINNOACTIVE, then the window is initially displayed as an icon.

The ShowWindow call puts the window (or icon) up on the display. If the parameter is SW_SHOWNORMAL, the client area of the window is erased with the background brush specified in the window class. The Windows function call:

```
UpdateWindow (hWnd) ;
```

then causes the client area to be painted. Because nothing appears in the client area of WELCOME1, this call has no visual effect on the window. The WinMain function in WELCOME1 then returns FALSE and causes the program to terminate.

And What About WndProc?

We seem to have described a complete working program without discussing the purpose of that second function in WELCOMELC, called WndProc. It certainly looks simple enough:

```
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
   HWND   hWnd;
   unsigned iMessage;
   WORD   wParam;
   LONG   1Param;
   {
    return DefWindowProc (hWnd, iMessage, wParam, 1Param);
}
```

This function does nothing but call the Windows function <code>DefWindowProc</code>, passing to it the same four parameters passed to <code>WndProc</code>. After <code>DefWindowProc</code> returns to <code>WndProc</code>, <code>WndProc</code> returns also, with the value obtained from the <code>DefWindowProc</code> call.

If you look over WELCOME1.C, however, you'll see that this function is actually used only once—when setting up the window class structure:

```
wndclass.lpfnWndProc = WndProc ;
```

The function is also declared near the top of the program:

```
long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG) ;
```

But that's only because the function name is used in *WinMain*. That's it. WELCOME1 never calls *WndProc*. Why do we need a function in the program that we don't use? What's it doing there besides taking up space?

It is true that WELCOME1 itself never calls WndProc.

But something else calls WndProc.

That something else is Windows.

Don't Call Me, I'll Call You

On the way to our mastery of Windows programming, we will encounter some conceptual hurdles. This is one of the big ones.

Programmers are familiar with the idea of calling on the operating system to do something. For instance, C programmers use the *open* or *fopen* function to open a file. The library functions provided with the compiler have code that eventually calls the operating system to open the file. No problem.

But Windows is different. Although Windows has more than 450 functions that your program can call, Windows also makes calls to *your* program, specifically to the window function we have called *WndProc*. (Watch out for terminology here—I'll be talking about "Windows functions," which are routines within Windows that your program calls, and the "window function," which is a function within your program that Windows calls.) The window function can have any name. (We've chosen the standard *WndProc*.) You must reference the function in the *lpfnWndProc* field of the window class structure. *WndProc* is the window function for all windows that are created based on this window class.

Windows calls WndProc when a window is first being created. Windows calls WndProc when the window is later destroyed. Windows calls WndProc when the window has been resized or moved or made into an icon. Windows calls WndProc when an item has been selected from a menu. Windows calls WndProc when a scroll bar is being moved or clicked with the mouse. Windows calls WndProc to tell it when it must repaint its client area. The calls to WndProc tell the program what is happening to the window. Windows sends the program information through these calls.

Windows delivers all this information to WndProc in the form of formatted "messages." In most Windows programs, the bulk of the program is dedicated to handling these messages. The 175 or so different messages that Windows can send to a window function are all identified with names that begin with the letters WM and an underscore. The names are defined in WINDOWS.H and refer to numbered codes.

Actually, the idea of a routine within a program that is called from outside the program is not unheard of in normal programming. The *signal* function in C can trap a Ctrl-Break. You may have experience with intercepting hardware interrupts in assembly language or using one of the ON constructions in Microsoft BASIC. The Microsoft Mouse driver has a method that non-Windows programs can use to be notified of mouse activity.

In Windows, this concept is extended to cover everything. You'll often encounter the expression "Windows sends a message to a window." What this means is that Windows calls the window function of the window.

A Closer Look at WndProc

Right now, the WndProc function looks like this:

```
long FAR PASCAL WndProc (hWnd, iMessage, wParam, lParam)
   HWND   hWnd;
   unsigned iMessage;
   WORD   wParam;
   LONG   lParam;
   {
    return DefWindowProc (hWnd, iMessage, wParam, lParam);
}
```

Note that—like the Windows functions you call from your program—*WndProc* is defined as FAR PASCAL. Your program's code and Windows' code are in different code segments. Windows calls *WndProc* from outside the program's code segment.

The first parameter to *WndProc* is the handle to the window to which Windows is sending the message. Because multiple windows can be created based on the same window class, a single window function could process messages for more than one window within a single program. *WndProc* would use this parameter to determine which window is receiving the message. Because WELCOME1 has only one window, this window handle is the same value returned from the *CreateWindow* call.

The second parameter to *WndProc* specifies the message itself, which is one of the identifiers from WINDOWS.H that begin with WM_. For example, WM_KEYDOWN identifies a keystroke message that results when a key is depressed.

The parameters wParam (a WORD, or 16-bit unsigned integer) and lParam (a LONG, or 32-bit signed integer) contain information that depends on the particular message. Sometimes wParam contains two byte values stuck together. Sometimes lParam contains two word values stuck together. Sometimes lParam contains a far pointer to something. Sometimes wParam and lParam are both 0 and can be ignored. It all depends on the message.

Let's look at an example. Whenever the client area of a window changes in size, Windows calls that window's window function. The hWnd parameter to the window function is the handle of the window changing in size. The iMessage parameter is WM_SIZE. The wParam parameter for a WM_SIZE message is the value SIZENORMAL, SIZEICONIC, SIZEFULLSCREEN, SIZEZOOMSHOW, or SIZEZOOMHIDE (defined in WINDOWS.H as the numbers 0 through 4). The wParam parameter indicates whether the window has been minimized, maximized, or hidden as a result of another window being maximized. The IParam parameter contains the new size of the window. The new width (a (16-bit value) and the new height (a 16-bit value) have been stuck together in the 32-byte IParam. WINDOWS.H includes macros to help you extract these two values from IParam. We'll do this in the next chapter.

Default Message Processing

In WELCOME1, WndProc is forgoing the opportunity to process messages from Windows. Any messages that a window function does not process must be passed to a Windows function called DefWindowProc. The value returned from this function must also be returned from WndProc. WndProc does this with the line:

return DefWindowProc (hWnd, iMessage, wParam, lParam);

Let's take another look at WinMain to get a better view of the whole process. The RegisterClass call tells Windows that WndProc is the window function to use for messages to windows created using the "Welcomel" window class. The CreateWindow tells Windows to create a window based on the "Welcome1" class. CreateWindow causes Windows to send several messages to the window. That is, Windows calls WndProc with several messages named WM_GETMINMAXINFO, WM_NCCREATE, WM_NCCALCSIZE, and WM_CREATE. WndProc calls DefWindowProc within Windows for each message. The DefWindowProc routine processes the messages and returns control to WndProc. WndProc then returns control to Windows, which completes the CreateWindow call by returning control to WinMain.

The ShowWindow call tells Windows to put the window on the screen. Windows calls WndProc with several messages, including WM_SHOWWINDOW, WM_SIZE, WM_MOVE, and WM_ACTIVATE.

The *UpdateWindow* call generates a WM_PAINT message. If WELCOME1 did something normal (like display something in the client area of the window), this WM_PAINT message would tell *WndProc* that it was time to paint the window.

In all cases, WndProc turns the messages over to DefWindowProc and lets Windows worry about them. WndProc is being lazy at the moment. We'll put it to work shortly.

Creating WELCOME1.EXE

Because WndProc is called from Windows, you must specify that it is an "exported function" in the WELCOMELDEF file:

NAME DESCRIPTION STUB	WELCOME1 'Welcome to WindowsProgram No. 1 (c) Charles Petzold, 1987' 'WINSTUB.EXE'
CODE	MOVEABLE
DATA	MOVEABLE MULTIPLE
HEAPSIZE	1024
STACKSIZE	4096
EXPORTS	WndProc

The EXPORTS statement identifies *WndProc* as a function that can be called from outside the program. This statement is extremely important, and it's easy to forget it. (We'll explore what the EXPORTS statement really does in Chapter 8.)

The WELCOME1 make file is similar to that for the NOTHING program:

When you execute:

MAKE WELCOME1

on the MS-DOS command line, the WELCOMELEXE executable file is created. When you execute WELCOMELEXE in Windows, the window appears on the display with the caption "Welcome to Windows," and then it disappears.

I can tell already that you're not quite satisfied with this program. We put a lot of work into it, and it's still not quite normal. The window goes up smoothly, but then it just comes down again. If I were a carpenter who installed such a window in your living room, you'd have me by the neck.

A Program That Stays Around Awhile

I said initially that WELCOME1 would be similar to the normal C "Hello, world" program, which displays "Hello, world" and then terminates. That the words "Hello, world" continue to appear on your screen even after the program has terminated is merely one of the many quirks of a primitive teletype interface.

To create a normal C program that continues to run until the user specifically quits the program (say by pressing Q), you would write code that looked something like this:

```
#include <stdio.h>
    main ()
    {
        puts ("Hello, world (Enter Q to quit).\n") ;
        while ('Q' != getchar ()) ;
    }
}
```

The program sits in the little while loop waiting for Q to be entered and only then terminates.

Let's add a few lines to to WELCOME1 to do something similar. This new version of the program is called WELCOME2 and is shown in Figure 2-5.

```
welcome2.obj : welcome2.c
    cl -c -D LINT_ARGS -Gsw -Os -W2 -2p welcome2.c

welcome2.exe : welcome2.obj welcome2.def
    link4 welcome2, /align:16, /map, slibw, welcome2
```

Figure 2-5. The WELCOME2 program

(continued)

Figure 2-5. Continued

```
static char szAppName [] = "Welcome2" ;
            hWnd ;
    HWND
    MSG
                 msq ;
    WNDCLASS
                wndclass ;
    if (!hPrevInstance)
         wndclass.style = CS_HREDRAW | CS_VREDRAW ;
wndclass.lpfnWndProc = WndProc ;
wndclass.cbClsExtra = 0 ;
wndclass.cbWndExtra = 0 ;
          wndclass.hInstance = hInstance;
wndclass.hIcon = LoadIcon (NULL, IDI_APPLICATION);
wndclass.hCursor = LoadCursor (NULL, IDC_ARROW);
          wndclass.hbrBackground = GetStockObject (WHITE BRUSH) ;
          wndclass.lpszMenuName = NULL ;
          wndclass.lpszClassName = szAppName ;
          if (!RegisterClass (&wndclass))
               return FALSE :
                                                  /* window class
    hWnd = CreateWindow (szAppName,
                                                 /* window caption
                      "Welcome to Windows",
                                                  /* window style
                      WS OVERLAPPEDWINDOW,
                                                  /* initial x position
                      CW USEDEFAULT,
                                                  /* initial y position
                      0.
                                                  /* initial x size
                      CW USEDEFAULT,
                                                  /* initial y size
                      0,
                                                  /* parent window handle
/* window menu handle
                      NULL,
                      NULL,
                                                  /* program instance handle */
                      hInstance,
                                                  /* create parameters
                      NULL) ;
     ShowWindow (hWnd, nCmdShow) ;
     UpdateWindow (hWnd) ;
     while (GetMessage (&msg, NULL, 0, 0))
           TranslateMessage (&msg) ;
           DispatchMessage (&msg) ;
     return msg.wParam ;
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
     HWND
           hWnd ;
     unsigned iMessage ;
            wParam ;
     WORD
     LONG
               1Param ;
     switch (iMessage)
           case WM DESTROY:
                 PostQuitMessage (0) ;
                 break :
           default:
                 return DefWindowProc (hWnd, iMessage, wParam, 1Param) ;
      return OL ;
```

Figure 2-5. Continued

```
NAME
              WELCOME2
DESCRIPTION
               'Welcome to Windows -- Program No. 2 (C) Charles Petzold, 1987'
STUB
               'WINSTUB.EXE'
CODE
              MOVEABLE
DATA
              MOVEABLE MULTIPLE
HEAPSIZE
              1024
STACKSIZE
               4096
EXPORTS
               WndProc
```

You can now create WELCOME2.EXE and run the program in Windows. You will see that it comes up as a normal overlapped window, as shown in Figure 2-6. Using either the keyboard or mouse, you can move the window around the display, maximize it, minimize it, and close it to end the program. It's a real Windows program!




Figure 2-6. The WELCOME2 window

Let's look at what had to be added.

The Message Loop

WinMain now has a new variable called msg that is defined to be of type MSG:

MSG msg ;

MSG is a structure defined in (where else?) WINDOWS.H. It is the Windows message structure. At the bottom of WinMain is some new code:

This is a standard Windows message loop.

Earlier, we looked at the messages that Windows sends to the *WndProc* function as a result of the *CreateWindow*, *ShowWindow*, and *UpdateWindow* calls. These are not the only messages that *WndProc* will receive.

Windows maintains a message queue for each currently running application. The Get-Message call that begins the message loop retrieves a message from this message queue:

```
GetMessage (&msg, NULL, 0, 0)
```

This call passes to Windows a far pointer to the message structure called *msg*. The second, third, and fourth parameters are set to NULL (or 0) to indicate that we want all messages for all windows in our program. Windows fills in the fields of the message structure with the next message from the message queue. The fields of this structure are:

- msg.hwnd—the handle to the window to which the message is directed. In the WELCOME2 program, this is the same as the hWnd value returned from CreateWindow, because that's the only window this program has.
- msg.message—the message identifier.
- msg.wParam—a 16-bit parameter dependent on the message.
- msg.lParam—a 32-bit parameter dependent on the message.
- msg.time—the time the message was placed in the queue.
- msg.pt—the mouse coordinates at the time the message was placed in the queue.

If the *message* value is anything except a WM_QUIT message, *GetMessage* returns a nonzero value. (A WM_QUIT message causes the program to fall out of the loop. The program then terminates, returning the *wParam* member of the *msg* structure.)

The line:

```
TranslateMessage (&msg) ;
```

passes this structure back to Windows. If the message happens to be a keystroke message (a WM_KEYDOWN or a WM_SYSKEYDOWN message), Windows places a character code message (WM_CHAR or WM_SYSCHAR) in the message queue. Even for a program as simple as WELCOME2, TranslateMessage has an important role to play. Without this line, you would

have no keyboard control over WELCOME2's system menu. You might try removing this line and recreating WELCOME2.EXE to see what happens.

The line:

```
DispatchMessage (&msg) ;
```

again passes this message structure back to Windows. Windows then sends the message to the appropriate window procedure for processing. That's *WndProc*. After *WndProc* processes the message (which most of the time involves passing the message to *DefWindow-Proc*), it then returns to Windows, which is still servicing the *DispatchMessage* call. When Windows returns to WELCOME2 from the *DispatchMessage* call, the loop continues with the next *GetMessage* call.

The new WndProc is also slightly expanded:

You'll notice now that the four parameters to WndProc are the same as the first four fields of the msg structure retrieved by GetMessage and sent to WndProc via DispatchMessage. Windows pulls the structure apart into separate variables to make the data somewhat easier to use within WndProc. (If you ever need the time and pt fields of the msg structure within WndProc, you can obtain the values using the GetMessagePos and Get-MessageTime calls.)

And notice that *WndProc* is now processing a message! It's only one message for the moment (WM_DESTROY), but it's a start. The C switch and case construction is the most common method that Windows programmers use to process specific messages. For something this simple, an *if-then-else* construction would be just as suitable. Whenever *WndProc* processes a message, it returns a 0 back to Windows.

WndProc calls PostQuitMessage when it receives a WM_DESTROY message. The WM_DESTROY message indicates that the window is being destroyed. This is the last message that WndProc receives. The PostQuitMessage call causes a WM_QUIT message to be placed

in the program's message queue. When *GetMessage* retrieves this message, the *GetMessage* call returns 0, which causes the program to drop out of the loop. *WinMain* ends, and the program terminates.

Where did the WM_DESTROY message come from? Generally, it is sent to the window function by a *DestroyWindow* call that *DefWindowProc* makes in response to a WM_CLOSE message. The WM_CLOSE message is sent to the window function to signal that the user chose Close from the program's system menu. The WM_CLOSE message is generated by the WM_SYSCOMMAND message, which could be the result of a keyboard message or a mouse message.

Messages beget messages beget messages. All the messages to the window go through WndProc. If you'd like an audible demonstration of the number of messages that WndProc receives, insert the line:

MessageBeep (0);

right above the switch statement in WndProc, remake the program, and run it.

Another Hurdle

In one sense, the message loop at the bottom of WinMain looks a little more traditional. The loop is polling for messages, just like a normal program polls for keyboard data.

Earlier I introduced the concept of Windows sending messages to a window, which means that Windows calls the window function. But now it's obvious that this message loop is actually retrieving the messages and getting them to *WindProc* in a roundabout manner. So does a Windows program poll for messages and route them like a normal program? Or does it receive messages directly from outside the program? Well, both.

Messages can be either "queued" or "nonqueued." The queued messages are those that are placed in a program's message queue by Windows and retrieved by a program using Get-Message. The messages are dispatched to the window function using DispatchMessage. The nonqueued messages are sent to the window directly when Windows calls the window function. The result is that the window function gets all the messages—both queued and non-queued—for the window. Structurally, Windows programs are very clean, because they have one central point of message processing.

The queued messages are primarily those that result from user input in the form of keystrokes (such as WM_KEYDOWN and WM_KEYUP), characters that result from keystrokes (WM_CHAR), mouse movement (WM_MOUSEMOVE), and mouse button clicks (WM_LBUTTONDOWN). Queued messages also include the timer message (WM_TIMER), the repaint message (WM_PAINT), and the quit message (WM_QUIT). The nonqueued messages are everything else. In many cases the nonqueued messages result from queued messages. When you pass a message to <code>DefWindowProc</code> within the window function, Windows often processes the message by sending the window function other messages.

For example, when the user presses and releases the Alt-F10 key combination, Windows places a WM_SYSKEYDOWN message and a WM_SYSKEYUP message in the program's message queue. The program retrieves these messages—one at a time—from the queue with GetMessage and dispatches them to the window function with DispatchMessage. The window function ignores the messages and calls DefWindowProc.

For the WM_SYSKEYDOWN message, *DefWindowProc* calls the window function directly with a WM_SYSCOMMAND message with *wParam* equal to SC_MAXIMIZE. Again the message is passed to *DefWindowProc*, which then sends the window function many messages, including a WM_SIZE message to indicate the new size. Windows also sends other window functions in other programs messages to indicate that they are being covered with a maximized window. Only when all these messages are completed does Windows return from the *DispatchMessage* call that originally dispatched the Alt-F10 key combination to the window function.

This process is obviously complex, but fortunately most of the complexity is Windows' problem rather than our program's. From the perspective of the window function, these messages come through in an orderly, synchronized manner. The window function can do something with these messages or ignore them. For this reason, the window function has been called the "ultimate hook." Messages notify the window function of almost everything that affects the window.

Notice also that the window function must be reentrant. That is, Windows often calls WndProc with a new message as a result of WndProc calling DefWindowProc with a previous message. This is one reason that a Windows program requires a 4 KB stack, as indicated in the module definition (.DEF) file. In most cases the reentrancy of the window function presents no problem, but you should be aware of it.

The structure of WELCOME2 shows the structure of virtually all Windows programs. WinMain does most program initialization and then sits in a small message loop. WndProc processes all messages from Windows, including all the nonqueued messages generated by the initialization in WinMain, all the queued messages retrieved by GetMessage from the message queue, and all the nonqueued messages that are sent to WndProc directly.

Nonpreemptive Multitasking

The GetMessage call within the message loop is important for another reason. Except for some device drivers that must process hardware interrupts (such as the timer, keyboard, mouse, and serial port), Windows usually treats WELCOME2 as if it were the only program running under the system. Windows will not arbitrarily switch away from WELCOME2 and run some other program. The one exception is during the GetMessage call. If WELCOME2's message queue has no waiting messages, and another program has some messages in its message queue, then Windows switches from WELCOME2 to the other program. That makes sense, does it not?

You can think of it this way: In most cases, when your program calls a function in Windows, you can expect that the function will be processed and return control to your program within a reasonable period of time. When you call *GetMessage*, however, it may be some time before Windows returns with a message if the program's message queue does not contain any messages and another program's message queue does. Windows can take advantage of the delay caused by an empty message queue during a *GetMessage* call to switch to another program that has messages waiting. As a result, Windows has a "jumpy" type of multitasking. Sometimes a program has a long job to do, and all other programs running under Windows seem to stop running during this time.

Rather than "jumpy multitasking," this characteristic is usually called "nonpreemptive multitasking." Windows is multitasking between programs by switching between them. But Windows is not doing this as in a traditional multitasking system, based on the tick of a hardware clock and allocating each program a tiny time-slice to do its stuff. It's multitasking at the point where programs check the message queue for messages.

The process is actually a little more complex than that: Windows also switches between programs during <code>PeekMessage</code> and <code>WaitMessage</code> calls, but these are less common than <code>GetMessage</code>. Furthermore, the WM_PAINT and WM_TIMER messages are treated as low-priority messages, so Windows can switch away from a program if only WM_PAINT and WM_TIMER messages are present in the queue.

Variations on a Theme

Before proceeding to another version of the WELCOME program, let's explore some variations on the WELCOME2 program and see how they affect the appearance and functionality of the window. If you want to try out some of these changes, remember to run MAKE on WELCOME2 each time to make a new .EXE file.

The ShowWindow call

In WINDOWS2, the ShowWindow call uses the nCmdShow value passed as a parameter to WinMain:

```
ShowWindow (hWnd, nCmdShow);
```

This value determines whether the window is initially displayed as a normal window (if nCmdShow equals SW_SHOWNORMAL) or as an icon (SW_SHOWMINNOACTIVE).

You don't have to use nCmdShow, however. You can instead use a constant defined in WINDOWS.H to force the window to be displayed a particular way. For example:

```
ShowWindow (hWnd, SW_SHOWMAXIMIZED) ;
```

displays the window maximized to use the full screen. If you use:

```
ShowWindow (hWnd, SW_SHOWMINIMIZED) ;
```

the window is displayed as an icon. The difference between SW_SHOWMINIMIZED and SW_SHOWMINNOACTIVE is that the former makes the window the active window, and the latter does not.

The window style

The third parameter to the *CreateWindow* call is the "window style." This is a 32-bit unsigned long integer. The parameter is interpreted as a series of bit flags. You can use identifiers defined in WINDOWS.H combined with the C bitwise OR operator to specify the window style. Figure 2-7 shows the upper 16 bits of the 32-bit window style and the various identifiers that set these bits.




Figure 2-7. The upper 16 bits of the 32-bit window style and the identifiers that set the bits

The window style that is used in the *CreateWindow* call of the WELCOME2 program is WS_OVERLAPPEDWINDOW, which is a combination of several identifiers. Rather than use WS_OVERLAPPEDWINDOW, you can instead specify the flags individually:

```
WS_OVERLAPPED | WS_CAPTION | WS_SYSMENU | WS_THICKFRAME | WS_MINIMIZEBOX | WS_MAXIMIZEBOX
```

The WS_OVERLAPPED identifier means that the window is an overlapped window. This is one of three general styles of window. The other two are WS_POPUP (a popup window) and

WS_CHILD (a child window). (In some old Windows programs written for versions earlier than 2.0, you'll see the identifiers WS_TILED and WS_TILEDWINDOW. These are essentially the same as WS_OVERLAPPED and WS_OVERLAPPEDWINDOW, but the names refer to the use of tiled windows in Windows 1.0x. The former WS_SIZE identifier is the same as WS_THICKFRAME. The WS_MINIMIZEBOX and WS_MAXIMIZEBOX identifiers were introduced with version 2.0.)

Most Windows programs create at least one overlapped window that often functions as the program's main, or top-level, application window. Popup windows are often used as temporary subsidiary windows. A dialog box is a popup window, for example. Child windows can take many forms and have many functions. Child windows can divide an overlapped window or popup window into various regions. Windows includes several predefined window classes that programs use to create "child window controls." These take the form of buttons, scroll bars, list boxes, and edit fields that you'll often see within a dialog box. We'll look at popup windows and child windows before concluding this chapter, but right now let's concentrate on the different styles possible with overlapped windows.

You might initially want to replace the WS_OVERLAPPEDWINDOW identifier in WELCOME2.C with the separate flags shown above and see for yourself how these flags affect the window that WELCOME2 displays. If you remove WS_MAXIMIZEBOX, the maximize icon at the right of the caption bar is not displayed. Likewise, the Maximize option on WELCOME2's system menu is disabled. You cannot maximize the window. If you remove WS_MINIMIZEBOX, the minimize icon at the right of the caption is not displayed, and the Minimize option on the system menu is disabled. Now the window cannot be minimized to an icon.

If you remove WS_THICKFRAME, the thick frame surrounding the window is replaced with a thin black borderline. The Size option on WELCOME2's system menu is disabled, and you cannot resize the window. If you remove WS_SYSMENU, the system menu box is not displayed. This makes it impossible for the user to terminate the program except by terminating Windows.

The WS_CAPTION window style is superfluous for an overlapped window, which always has a caption bar across the top. You can try replacing WS_CAPTION with WS_DLGFRAME (a frame around the window often used for dialog boxes) or WS_BORDER (a thin border around the window without a caption), or you can simply remove WS_CAPTION. Regardless, the caption bar continues to be displayed.

You can put scroll bars in WELCOME2's window by including the identifier WS_VSCROLL (a vertical scroll bar on the right on the window) or WS_HSCROLL (a horizontal scroll bar on the bottom of the window) or both. The resultant window style (assuming you want to keep all the original identifiers) is:

WS_OVERLAPPED | WS_CAPTION | WS_SYSMENU | WS_THICKFRAME | WS_MINIMIZEBOX | WS_MAXIMIZEBOX | WS_VSCROLL | WS_HSCROLL

If you experiment with these scroll bars, you'll find that Windows displays a reverse video flash when you click the arrows of the scroll bar with the mouse and a dotted box when you drag the scroll bar. At the same time, Windows is also informing WELCOME2 (by sending messages to *WndProc*) how the scroll bar is being manipulated. We'll use scroll bars in the next chapter.

The WS_MINIMIZE, WS_MAXIMIZE, WS_VISIBLE, and WS_DISABLED bits are used to set the initial state of the window and don't play much of a role in overlapped windows. We'll use the WS_CLIPCHILDREN and WS_CLIPSIBLINGS bits later in this chapter.

The background color

Just as we were able to change the look and functionality of a window by changing the window style parameter in the *CreateWindow* call, we can also change certain characteristics of the window by tampering with some of the fields of the window class structure. Let's start with the *hbrBackground* field, which determines the background color of the window. WELCOME2 uses a white background:

```
wndclass.hbrBackground = GetStockObject (WHITE_BRUSH) ;
```

Besides WHITE_BRUSH, you can use other stock brushes: GRAY_BRUSH, LTGRAY_BRUSH, DKGRAY_BRUSH, BLACK_BRUSH, and the rather strange-sounding HOLLOW_BRUSH and NULL_BRUSH. These last two are identical (as you can determine from their definitions in WINDOWS.H) and cause the background of the client area to be left alone and not erased. Whatever was there before will still appear.

Well, these are fine for a monochrome world, but what about color? Rather than getting a monochrome brush from the Windows stock room, we can create our own colored brush:

```
wndclass.hbrBackground = CreateSolidBrush (RGB (255, 0, 255));
```

This creates a magenta background. The *CreateSolidBrush* call takes a 32-bit DWORD (unsigned long integer) parameter that specifies a color value. The lowest byte of this color value is a value of red ranging from 0 (minimum) to 255 (maximum). The next highest byte is green, the next is blue, and the highest byte is 0. Rather than sticking these three bytes together yourself, you can use a macro from WINDOWS.H called RGB. This lets you specify the red, green, and blue color values separately. RGB defines the operations that stick the bytes together in a 32-bit integer:

```
#define RGB(r,g,b) (((DWORD) ((b) << 8 | (g)) << 8) | (r))
```

You might also want to create a hatched brush:

```
wndclass.hbrBackground = CreateHatchBrush (HS_VERTICAL,
RGB (255, 0, 255));
```

This is similar to the solid brush except that it has vertical hatch marks. Other styles of hatches you can use here are HS_HORIZONTAL, HS_FDIAGONAL, HS_BDIAGONAL,

HS_CROSS, and HS_DIAGCROSS. (Although it won't cause any problems to experiment with CreateSolidBrush or CreateHatchBrush in WELCOME2, any brushes created with these two functions should be explicitly deleted by the program that creates them. We'll do this in future chapters.)

You may also want to use a background color corresponding to one of the system colors you've set in the Windows CONTROL panel. In this case, you must add 1 to an identifier and cast it into a type HBRUSH, like so:

```
wndclass.hbrBackground = (HBRUSH) (COLOR_WINDOW + 1) ;
```

Specifying COLOR_WINDOW makes the color that you defined in the CONTROL application the color of the client area of your window. Most likely, this is white. If you have WELCOME2 active and go into CONTROL to change this color, WELCOME2's background changes as soon as you save your changes. You can also use COLOR_ACTIVECAPTION, COLOR_SCROLLBAR, or any of several others for the background of your window.

The icon and the cursor

To define the icon and cursor in WELCOME2's window class, we used the statements:

```
wndclass.hicon = LoadIcon (NULL, IDI_APPLICATION) ;
and:
```

```
wndclass.hCursor = LoadCursor (NULL, IDC_ARROW) ;
```

For the icon, you may want to try some of Windows' other predefined icons, such as IDI_HAND, IDI_QUESTION, IDI_ASTERISK, and IDI_EXCLAMATION. You've probably seen some of them in message boxes in various Windows applications. This is their usual function. You can also set *wndclass.hIcon* equal to NULL, in which case the program is responsible for drawing the icon. The Windows CLOCK application uses this technique to display a clock even when the program is in the icon area.

Windows uses the cursor defined in the window class to display the mouse cursor whenever it enters the window's client area. The IDC_ARROW cursor is standard in many applications. Other predefined cursors are IDC_CROSS, IDC_IBEAM, IDC_UPARROW, and IDC_WAIT (the hourglass cursor). If you set windclass.hCursor equal to NULL, the mouse cursor disappears when it enters WELCOME2's client area.

A Fixed-size Window

The WELCOME2 program uses CW_USEDEFAULT as the "initial x position" and "initial x size" parameters of *CreateWindow*, causing Windows to position and size the window according to its standard rules. You can also specify a particular position and size for the window. You might want to do this for a window that should always be a fixed size (such as the Windows CALC program).

The WELCOME3 program, shown in Figure 2-8, demonstrates how to create such a fixed-size window. WELCOME3 creates an overlapped window that is one-half the height and width of the screen and is positioned in the center.

```
welcome3.obj : welcome3.c
    c1 -c -D LINT_ARGS -Gsw -Os -W2 -Zp welcome3.c

welcome3.exe : welcome3.obj welcome3.def
    link4 welcome3, /align:16, /map, slibw, welcome3
    echo /* no resources */ >welcome3.rc
    rc welcome3
```

```
/* WELCOME3.C -- Welcome to Windows Program No. 3 */
#include <windows.h>
long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG) ;
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
     HANDLE hInstance, hPrevInstance;
     LPSTR
                 lpszCmdLine ;
     int
                nCmdShow :
     static char szAppName [] = "Welcome3" ;
     HWND hWnd;
     MSG
                msg ;
     MSG msg;
short xScreen, yScreen;
WNDCLASS wndclass;
     if (!hPrevInstance)
                                 = CS HREDRAW | CS VREDRAW ;
          wndclass.style
          wndclass.lpfnWndProc = WndProc;
wndclass.cbClsExtra = 0;
wndclass.cbWndExtra = 0;
          wndclass.hbrBackground = GetStockObject (WHITE BRUSH) ;
          wndclass.lpszMenuName = NULL ;
          wndclass.lpszClassName = szAppName ;
          if (!RegisterClass (&wndclass))
               return FALSE ;
     xScreen = GetSystemMetrics (SM CXSCREEN) ;
     yScreen = GetSystemMetrics (SM CYSCREEN) ;
                    ndow (szAppName, /* window class name "Welcome to Windows", /* window caption
     hWnd = CreateWindow (szAppName,
                    WS OVERLAPPED |
                                              /* window style
                                                                          */
                          WS CAPTION | WS SYSMENU | WS MINIMIZEBOX,
```

Figure 2-8. The WELCOME3 program

Figure 2-8. Continued

```
xScreen / 4,
                                                 /* initial x position
                                                 /* initial y position
/* initial x size
                     yScreen / 4,
xScreen / 2,
                      yScreen / 2,
                                                 /* initial y size
                                                 /* parent window handle
                      NULL,
                                                 /* window menu handle
                      NULL,
                                                 /* program instance handle
/* create parameters
                      hInstance,
                      NULL) ;
     ShowWindow (hWnd, nCmdShow);
     UpdateWindow (hWnd) ;
     while (GetMessage (&msg, NULL, 0, 0))
           TranslateMessage (&msg) ;
           DispatchMessage (&msg) ;
     return msg.wParam ;
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
     HWND
              hWnd ;
     unsigned iMessage ;
             wParam ;
     WORD
     LONG
               lParam :
     switch (iMessage)
           case WM DESTROY:
                PostQuitMessage (0) ;
                break ;
           default:
                return DefWindowProc (hWnd, iMessage, wParam, 1Param) ;
     return OL ;
```

```
NAME WELCOMES
DESCRIPTION 'Welcome to Windows -- Program No. 3 (C) Charles Petzold, 1987'
STUB 'WINSTUB.EXE'
CODE MOVEABLE
DATA MOVEABLE MULTIPLE
HEAPSIZE 1024
STACKSIZE 4096
EXPORTS WINDPROC
```

To obtain the dimensions of the screen, WELCOME3 calls the Windows function GetSystemMetrics:

```
xScreen = GetSystemMetrics (SM_CXSCREEN) ;
yScreen = GetSystemMetrics (SM_CYSCREEN) ;
```

The single parameter to GetSystemMetrics is an identifier defined in WINDOWS.H. (In the next chapter we'll write a program that displays all the information available from the Get-SystemMetrics function.) The values returned from GetSystemMetrics are in units of pixels. For an IBM Enhanced Graphics Adapter connected to an Enhanced Color Display, for instance, xScreen is set to 640 and yScreen to 350.

CreateWindow expects the position and size parameters to be in units of pixels. The CreateWindow call in WELCOME3 looks like this:

```
hWnd = CreateWindow (szAppName,
                                      /* window class name
              "Welcome to Windows",
                                      /* window caption
              WS_OVERLAPPED
                                      /* window style
                   WS_CAPTION | WS_SYSMENU | WS_MINIMIZEBOX,
              xScreen / 4,
                                     /* initial x position
              yScreen / 4,
                                     /* initial y position
              xScreen / 2,
                                     /* initial x size
              yScreen / 2,
                                     /* initial y size
              NULL,
                                     /* parent window handle
                                      /* window menu handle
                                                                +/
              NULL,
              hInstance,
                                     /* program instance handle */
              NULL) ;
                                      /* create parameters
```

The upper left corner of the WELCOME3 window is positioned one-fourth the screen width from the left of the screen and one-fourth the screen height from the top of the screen, as shown in Figure 2-9.




Figure 2-9. The WELCOME3 window

The window style excludes the WS_THICKFRAME and WS_MAXIMIZEBOX flags. Thus the user is unable to change the size of WELCOME3's window except to minimize it. You don't have to exclude these flags, of course. The Windows CLOCK program is initially displayed in a nondefault size, but it includes a thick frame and maximize box to allow the user to make it larger or smaller.

Even if you want the window to be a fixed size, you can let Windows give it a default position. To do this with WELCOME3, you set the parameters like so:

```
CW_USEDEFAULT, /* initial x position */
0, /* initial y position */
xScreen / 2, /* initial x size */
yScreen / 2, /* initial y size */
```

If you look at the WELCOME3 make file, you will notice two strange-looking lines near the bottom:

```
echo /* no resources */ >welcome3.rc
rc welcome3
```

ECHO, of course, is an internal MS-DOS command. The ECHO statement here creates a file named WELCOME3.RC and stores the string /* no resources */ in it. The RC.EXE program run in the next statement is the Windows resource compiler, which we'll study in depth beginning in Chapter 9. The resource compiler uses the WELCOME3.RC file to create a WELCOME3.RES file (which will be 0 bytes long because WELCOME3.RC contains only a comment) and then adds the non-existent resources to WELCOME3.EXE.

But why? Well, RC.EXE also modifies the WELCOME3.EXE file to indicate a Windows version number. Without running the resource compiler on WELCOME3, Windows 2.0 would assume that WELCOME3.EXE is a Windows 1.0 program and interpret the *CreateWindow* parameters accordingly. Because Windows 1.0 ignored the position and size parameters for tiled windows (as they were called then), Windows 2.0 would do the same and thus would not use the specified position and size in displaying the window. Until we start routinely including resources in our Windows programs, we may occasionally have to use this trick to take advantage of Windows 2.0 capabilities.

One Class, Many Windows

Because creating a window requires both registering a window class and making a *CreateWindow* call, you may wonder why these two jobs are not combined into a single big function to define all the characteristics of a window in one shot. One answer is that you can create many different windows from the same window class. That happens normally if you load multiple instances of the same program in Windows. Each window uses the same window class, which has to be registered only when the first instance runs. Windows also has some predefined window classes that you can use for child windows. Your program itself can create several windows based on the same window class. The WELCOME4 program, shown in Figure 2-10, creates 10 overlapped windows based on one window class.

```
welcome4.obj : welcome4.c
    cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp welcome4.c

welcome4.exe : welcome4.obj welcome4.def
    link4 welcome4, /align:16, /map, slibw, welcome4
```

```
/* WELCOME4.C -- Welcome to Windows Program No. 4 */
#include <windows.h>
#include <stdio.h>
long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG) ;
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
     HANDLE hInstance, hPrevInstance;
     LPSTR
                  lpszCmdLine ;
     int
                  nCmdShow ;
     static char szAppName [] = "Welcome4" ;
     char
                 szCaption [60] ;
     HWND
                  hWnd ;
     MSG
                  msg ;
     short
                  i :
     WNDCLASS wndclass;
     if (!hPrevInstance)
          wndclass.style
                                   = CS HREDRAW | CS VREDRAW ;
          wndclass.lpfnWndProc = WndProc ;
          wndclass.cbClsExtra = 0;
wndclass.cbWndExtra = 0;
          wndclass.hInstance
                                  = hInstance ;
          wndclass.hlcon = LoadIcon (NULL, IDI_APPLICATION);
wndclass.hCursor = LoadCursor (NULL, IDC_ARROW);
          wndclass.hbrBackground = GetStockObject (WHITE_BRUSH) ;
          wndclass.lpszMenuName = NULL ;
          wndclass.lpszClassName = szAppName ;
          if (!RegisterClass (&wndclass))
                return FALSE ;
     for (i = 0 ; i < 10 ; i++)
                                                      /* window class name
          hWnd = CreateWindow (szAppName,
                           NULL,
                                                      /* window caption
                           WS OVERLAPPEDWINDOW,
                                                      /* window style
                           CW USEDEFAULT,
                                                      /* initial x position
                           0.
                                                      /* initial y position
                           CW USEDEFAULT,
                                                     /* initial x size
                          0,
                                                     /* initial y size
                                                     /* parent window handle
/* window menu handle
/* program instance handle
                           NULL,
                           NULL,
                           hInstance,
                           NULL) ;
                                                      /* create parameters
```

Figure 2-10. The WELCOME4 program

Figure 2-10. Continued

```
sprintf (szCaption, "Instance Handle = %X, Window Handle = %X",
                         hInstance, hWnd) ;
          SetWindowText (hWnd, szCaption) ;
          ShowWindow (hWnd, SW SHOWNORMAL) ;
          UpdateWindow (hWnd) ;
     while (GetMessage (&msg, NULL, 0, 0))
          TranslateMessage (&msg) ;
          DispatchMessage (&msg) ;
     return msg.wParam ;
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
             hWnd :
     unsigned iMessage :
     WORD
             wParam ;
     LONG
             1Param :
     switch (iMessage)
          case WM DESTROY:
              PostQuitMessage (0) ;
              break :
          default:
               return DefWindowProc (hWnd, iMessage, wParam, 1Param) ;
     return OL ;
```

```
NAME
               WELCOME4
               'Welcome to Windows -- Program No. 4 (C) Charles Petzold, 1987'
DESCRIPTION
               'WINSTUB. EXE'
STUB
               MOVEABLE
CODE
               MOVEABLE MULTIPLE
DATA
HEAPSIZE
               1024
STACKSIZE
               4096
               WndProc
EXPORTS
```

The CreateWindow call in WELCOME4 uses NULL for the window caption, indicating to Windows that the window will initially have no caption. Following the CreateWindow call, WELCOME4 sets the caption to the window using these statements:

The normal C sprintf function (declared in the header file STDIO.H) uses a formatting string to format numeric or string variables. The result is stored in the character array indicated by the first parameter to sprintf, in this case szCaption. The SetWindowText function uses this string to set the caption for each window. The caption indicates the instance handle (which is the same for all windows created from the same instance of the program) and the window handle (different for every window). The ShowWindow call uses SW_SHOWNORMAL for all 10 windows to display them as normal overlapped windows.

The WndProc window function processes messages for all the windows because they all use the same window class, which is where the window function is specified. If you had actual processing in WndProc that was different for each of the 10 windows, you might want to store the window handles returned from CreateWindow in a global array and use that array within WndProc to determine the window to which a particular message is directed.

Notice that the various windows seem to behave independently. If you click with the mouse on any of the 10 windows, that window becomes the active window (indicated by a different color in the caption bar) and moves to the foreground. Each of the windows created in WELCOME4 can be individually minimized or maximized.

If you choose Close from the system menu of any of the 10 windows, the other 9 are destroyed also, and the program terminates. This is a result of using the same window function for all 10 windows. Whenever one window gets a WM_DESTROY message, the *PostQuit-Message* function is called to place a WM_QUIT message in the message queue. The program terminates after retrieving this message, and Windows cleans up after the program by getting rid of the program's other windows.

If you want to allow the program to be terminated only from the first window created by the program, you first define a global variable near the top of your program, like this:

```
HWND hWndFirstWindow ;
```

Following the CreateWindow call, you set this variable equal to the first window created in the loop:

```
if (i == 0)
    hWndFirstWindow = hWnd;
```

You then alter the WM_DESTROY logic in WndProc:

```
case WM_DESTROY:
    if (hWnd == hWndFirstWindow)
        PostQuitMessage (0) ;
    break ;
```

Now you can close each of the windows individually. Only when you close the first window that was created will *WndProc* put the WM_QUIT message in the program's message queue.

The creation of 10 overlapped windows in one program is highly unusual. Almost all Windows programs create only one overlapped top-level window and then use popup windows and child windows for all other purposes. One problem with multiple overlapped windows is that each window can be independently minimized and displayed as an icon. A Windows program should really have only one icon that identifies the program, and this should be the icon of the main overlapped window.

CREATING POPUP AND CHILD WINDOWS

Having established that WELCOME4 does not provide the best way to add multiple windows to a program, we are now ready to examine popup windows and child windows. It is sometimes easy and sometimes difficult to tell by the appearance of a window whether it is an overlapped window, a popup window, or a child window. As we'll see, child windows in particular can assume many different looks and functions.

The Popup Window

Programmers generally use popup windows to display information that needs to be on the screen for only a short period of time. Popup windows are usually invoked by an option on the program's menu. Although dialog boxes are popup windows, they are generally created using the Windows *CreateDialog* and *DialogBox* functions rather than the *CreateWindow* function. We'll examine dialog boxes in Chapter 11.

Message boxes are popup windows that are created within Windows when a program calls the Windows MessageBox function. The window invoked by the Get Info option on the File menu in the Windows MS-DOS Executive program is another popup window. Popup windows also appear in the HEAPWALK program (supplied with the Windows Software Development Kit) when you choose Show or LocalWalk from the Object menu.

A program generally uses a separate window function (and hence a separate window class) for the popup window. This allows the window function for the overlapped window and the window function for the popup window to be more easily structured, because each window function obtains messages only for one window.

You can create a popup window by using the WS_POPUP identifier in the "window style" parameter in the *CreateWindow* call. Popup windows can sometimes look and act very much like overlapped windows. Here are some identifying characteristics of popup windows:

 Popup windows do not require a caption bar. You can use the WS_BORDER or WS_DLGFRAME window styles instead of WS_CAPTION. WS_BORDER displays a thin black frame around the popup window. WS_DLGFRAME displays a thicker frame most commonly used in dialog boxes.

- Popup windows are often fixed in size (although they don't have to be). To create
 a fixed-size popup window, exclude the WS_THICKFRAME window style. To
 create a popup window of variable size, include WS_THICKFRAME and
 WS_MAXIMIZEBOX.
- If a popup window has a system menu box, the Minimize option is always disabled. Do not include the WS_MINIMIZEBOX identifier in the window style for a popup window.
- For popup windows, the "parent window handle" parameter in the CreateWindow
 call can be either NULL, as it is with overlapped windows, or it can be set to the
 handle of another window, most often the main overlapped window of the
 program. This makes the overlapped window the "parent" of the popup window.

The WELCOME5 program, shown in Figure 2-11, creates one overlapped window and two popup windows.

```
welcome5.obj : welcome5.c
    cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp welcome5.c

welcome5.exe : welcome5.obj welcome5.def
    link4 welcome5, /align:16, /map, slibw, welcome5
    echo /* no resources */ >welcome5.rc
    rc welcome5
```

```
/* WELCOMES.C -- Welcome to Windows Program No. 5 */
#include <windows.h>
long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG);
long FAR PASCAL PopupWndProc (HWND, unsigned, WORD, LONG);
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
    HANDLE hInstance, hPrevInstance;
    LPSTR lpszCmdLine;
    int nCmdShow;
    (
    static char szAppName [] = "Welcome5";
    static char szPopupClass [] = "Welcome5";
    static char szPopupClass [] = "Welcome5";
    static char szPopupClass [] = "Welcome5";
    wNDCLASS wndclass;
```

Figure 2-11. The WELCOME5 program

Figure 2-11. Continued

```
if (!hPrevInstance)
                             = CS HREDRAW | CS VREDRAW ;
     wndclass.style
     wndclass.lpfnWndProc = WndProc;
     wndclass.cbClsExtra = 0;
wndclass.cbWndExtra = 0;
     wndclass.hInstance = hInstance;
wndclass.hIcon = LoadIcon (NULL, IDI_APPLICATION);
undclass.hCursor = LoadCursor (NULL, IDC_ARROW);
     wndclass.hCursor = LoadCursor (NULL, IDC ARROW) ;
wndclass.hbrBackground = GetStockObject (WHITE_BRUSH) ;
     wndclass.lpszMenuName = NULL ;
     wndclass.lpszClassName = szAppName ;
     if (!RegisterClass (&wndclass))
           return FALSE ;
     wndclass.style
                              = CS HREDRAW | CS VREDRAW ;
     wndclass.lpfnWndProc = PopupWndProc;
     wndclass.cbClsExtra = 0 ;
     wndclass.cbWndExtra = 0;
     wndclass.hInstance
                               = hInstance ;
     wndclass.hCon = NULL;
wndclass.hCursor = LoadCursor (NULL, IDC_CROSS);
     wndclass.hbrBackground = GetStockObject (LTGRAY_BRUSH) ;
     wndclass.lpszMenuName = NULL ;
     wndclass.lpszClassName = szPopupClass ;
     if (!RegisterClass (&wndclass))
           return FALSE ;
xScreen = GetSystemMetrics (SM CXSCREEN) ;
vScreen = GetSystemMetrics (SM CYSCREEN) ;
                                         /* window class name
hWnd = CreateWindow (szAppName,
                                          /* window caption
                 "Welcome to Windows",
                 WS OVERLAPPEDWINDOW,
                                            /* window style
                 0,
                                             /* initial x position
                                            /* initial y position
                 0,
                                            /* initial x size
                 CW USEDEFAULT,
                                            /* initial y size
                 0,
                                            /* parent window handle
                 NULL,
                                            /* window menu handle
                 NULL,
                                            /* program instance handle
/* create parameters
                 hInstance,
                 NULL) ;
ShowWindow (hWnd, nCmdShow);
UpdateWindow (hWnd) ;
hWndMain = hWnd ;
hWnd = CreateWindow (szPopupClass, /* window class name "Popup with Parent", /* window caption
                 WS_POPUP | WS_CAPTION | /* window style
                       WS SYSMENU | WS THICKFRAME | WS MAXIMIZEBOX,
```

Figure 2-11. Continued

```
xScreen / 9,
                                                   /* initial x position
                      yScreen / 8,
yScreen / 3,
yScreen / 2,
                                                  /* initial y position
                                                   /* initial x size
                                                   /* initial y size
                                                  /* parent window handle
/* window menu handle
/* program instance handle
                       hWndMain,
                       NULL,
                       hInstance,
                                                   /* create parameters
                       NULL) ;
      ShowWindow (hWnd, SW SHOWNORMAL) ;
     UpdateWindow (hWnd) ;
     hWnd = CreateWindow (szPopupClass, /* window class "Popup without Parent", /* window caption
                       WS POPUP | WS CAPTION | /* window style
                             WS SYSMENU | WS THICKFRAME | WS MAXIMIZEBOX,
                       5 * xScreen / 9,
                                                   /* initial x position
                      5 * XSCreen / 8,
yScreen / 8,
xScreen / 3,
yScreen / 2,
NULL,
NULL,
                                                   /* initial y position
                                                   /* initial x size
                                                   /* initial y size
                                                   /* parent window handle */
/* window menu handle */
/* program instance handle */
                       hInstance,
                                                   /* create parameters
                       NULL) ;
     ShowWindow (hWnd, SW SHOWNORMAL) ;
     UpdateWindow (hWnd) ;
     while (GetMessage (&msg, NULL, 0, 0))
           TranslateMessage (&msg) ;
           DispatchMessage (&msg) ;
     return msg.wParam ;
long FAR PASCAL WndProc (hWnd, iMessage, wParam, lParam)
     HWND hWnd;
     unsigned iMessage :
     WORD
            wParam ;
     LONG
               lParam ;
     switch (iMessage)
           case WM DESTROY:
                 PostQuitMessage (0) ;
                 break ;
           default:
                 return DefWindowProc (hWnd, iMessage, wParam, 1Param) ;
     return OL ;
```

Figure 2-11. Continued

```
long FAR PASCAL PopupWndProc (hWnd, iMessage, wParam, lParam)
   HWND   hWnd;
   unsigned iMessage;
   WORD   wParam;
   LONG   lParam;
   {
    return DefWindowProc (hWnd, iMessage, wParam, lParam);
   }
}
```

```
NAME
              WELCOME5
               'Welcome to Windows -- Program No. 5 (C) Charles Petzold, 1987'
DESCRIPTION
              'WINSTUB.EXE'
STUB
              MOVEABLE
CODE
              MOVEABLE MULTIPLE
DATA
HEAPSIZE
              1024
STACKSIZE
               4096
               WndProc
EXPORTS
              PopupWndProc
```

WELCOME5 registers two window classes named "Welcome5" and "Welcome5_Popup"; these window classes correspond to the two window functions called *WndProc* for the main overlapped window and *PopupWndProc* for the two popup windows. WELCOME5.DEF lists both window functions in the EXPORTS section:

```
EXPORTS WndProc
PopupWndProc
```

Each window function receives messages only for windows created based on that window class. Queued messages for all three windows come through the program's single message queue, but during the *DispatchMessage* call, Windows routes the message to the correct window function for the window.

The window class structure for the popups has a NULL icon because popup windows cannot be minimized. The background of the popup windows is the stock LTGRAY_BRUSH, and the cursor is the cross-hair cursor, IDC_CROSS. The *PopupWndProc* window function does not process WM_DESTROY messages. Although you can close the popup windows (which will destroy them), you can terminate the program only by closing the main overlapped window.

The initial position and size parameters of the *CreateWindow* call for the overlapped window cause it to be displayed across the full width of the screen. The initial position parameters for popup windows are (like those for overlapped windows) relative to the upper left corner of the display. The *CreateWindow* calls for the two popups use formulas based on the width and height of the screen for the position and size. The three windows are shown in Figure 2-12.




Figure 2-12. The WELCOME5 display

The only real difference between the two popup windows in WELCOME5 is the "parent window handle" parameter to *CreateWindow*. For the popup on the left, this parameter is set to the window handle of the overlapped window. For the popup on the right, this parameter is set to NULL. The captions of the two popup windows identify which is which.

Popups and Parents

When a popup window has a parent, it is affected by actions involving the parent. If you experiment in Windows with WELCOME5, you'll see some significant differences between the two popup windows:

- When you minimize the main overlapped window, the popup window with a
 parent is hidden, but the popup window without a parent is not.
- When you maximize the main overlapped window, all other windows are hidden except the popup window with a parent.
- When the overlapped window is the active window (indicated by the color of the
 caption bar), the overlapped window is displayed on top of the popup window
 without a parent. However, the overlapped window is never displayed on top of
 the popup window with a parent.

The popup window without a parent is essentially independent of the main overlapped window. In fact, these two windows are reminiscent of the multiple overlapped windows in WELCOME4. The only real difference is that the popup cannot be minimized.

When we say that a popup window has a parent, we are *not* saying that the popup window is a child window. Child windows are something else entirely. Child windows are even more attached to their parents than popup windows are. Here are the basic rules regarding parents for the three types of windows:

- An overlapped window never has a parent.
- A child window always has a parent.
- A popup window may or may not have a parent. If the popup window has a
 parent, however, it is still not a child window. It's a popup window.

Child Windows

If you counted and categorized all the windows created during a typical Windows session, your results would probably look something like this:

- · One overlapped window for each program you ran.
- One popup window for each dialog box and each message box displayed, plus perhaps a couple more. (Windows also creates a popup window whenever it displays a popup menu, but let's ignore that.)
- · Hundreds of child windows.

Child windows are so prevalent partly because they can assume many forms and functions. In a dialog box, every push button, check box, radio button, edit field, text field, list box, and scroll bar is a child window. These so-called child window controls are the most common form of child windows. They are based on window classes that are registered by Windows itself with window functions contained within Windows.

The MS-DOS Executive uses child windows to divide its client area into three sections—the disk drive section, the current pathname section, and the file and directory section. Microsoft Excel uses child windows for the windows within its work space that contain sheets, macro sheets, and charts. The scroll bars are child windows, and so are those little black bars at the top and to the left of the scroll bars that split a work sheet into two or four sections.

In experimenting with WELCOME5, you may have noticed that when you move the overlapped window, the popup windows stay put. This is not true of child windows, which follow their parent around the display. Moreover, child windows are never displayed outside the client area of their parent.

You can create a child window using the CreateWindow call with a window style parameter of WS_CHILD, and you can include the same window style identifiers used for overlapped windows and popup windows. In addition, if you create a child window control

based on a predefined window class, you can include identifiers beginning with the letters ES (edit style), BS (button style), SS (static style), LBS (list box style), and SBS (scroll bar style). We'll explore child window controls in depth in Chapter 7.

But right now, let's party.

The PARTY Program

The PARTY program, shown in Figure 2-13, invites all the windows we've met so far, encouraging them to bring their children and anybody else who might pop up.

```
party.obj : party.c
    cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp party.c

party.exe : party.obj party.def
    link4 party, /align:16, /map, slibw, party
    echo /* no resources */ >party.rc
    rc party
```

```
/* PARTY.C -- Overlapped, Popup, and Child Windows */
#include <windows.h>
long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG) ;
long FAR PASCAL PopupWndProc (HWND, unsigned, WORD, LONG);
long FAR PASCAL ChildWndProc (HWND, unsigned, WORD, LONG);
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
      HANDLE hInstance, hPrevInstance;
      LPSTR
                    lpszCmdLine ;
               nCmdShow ;
      int
      static char szAppName [] = "Party" ;
      static char szPopupClass [] = "Party Popup";
static char szChildClass [] = "Party Child";
      HWND hWnd, hWndMain, hWndPopup1, hWndPopup2;
      short
                   msg ;
                    xScreen, yScreen ;
      WNDCLASS
                    wndclass ;
      if (!hPrevInstance)
            wndclass.style = CS_HREDRAW | CS_VREDRAW ; wndclass.lpfnWndProc = WndProc ;
            wndclass.cbClsExtra = 0;
wndclass.cbWndExtra = 0;
            wndclass.hInstance = hInstance;
wndclass.hIcon = LoadIcon (NULL, IDI_APPLICATION);
wndclass.hCursor = LoadCursor (NULL, IDC_ARROW);
            wndclass.hbrBackground = GetStockObject (WHITE_BRUSH) ;
            wndclass.lpszMenuName = NULL ;
            wndclass.lpszClassName = szAppName :
            if (!RegisterClass (&wndclass))
                  return FALSE ;
```

Figure 2-13. The PARTY program

Figure 2-13. Continued

```
= CS HREDRAW | CS VREDRAW ;
    wndclass.style
    wndclass.lpfnWndProc = PopupWndProc ;
     wndclass.cbClsExtra = 0;
    wndclass.cbWndExtra
                            = 0 ;
     wndclass.hInstance
                            = hInstance ;
    wndclass.hIcon = NULL;
wndclass.hCursor = LoadCursor (NULL, IDC_CROSS)
     wndclass.hbrBackground = COLOR WINDOW + 1 ;
    wndclass.lpszMenuName = NULL;
wndclass.lpszClassName = szPopupClass;
    if (!RegisterClass (&wndclass))
         return FALSE ;
                            = CS HREDRAW | CS VREDRAW ;
     wndclass.stvle
     wndclass.lpfnWndProc = ChildWndProc;
     wndclass.cbClsExtra
                            = 0 ;
     wndclass.cbWndExtra
                            = 0 ;
     wndclass.hInstance
                            = hInstance ;
     wndclass.hCon = NULL;
wndclass.hCursor = LoadCursor (NULL, IDC_UPARROW);
     wndclass.hbrBackground = GetStockObject (LTGRAY BRUSH) ;
     wndclass.lpszMenuName = NULL ;
     wndclass.lpszClassName = szChildClass ;
     if (!RegisterClass (&wndclass))
          return FALSE ;
xScreen = GetSystemMetrics (SM_CXSCREEN) ;
yScreen = GetSystemMetrics (SM CYSCREEN) ;
                                          /* window class name
hWnd = CreateWindow (szAppName,
                                          /* window caption
                "Party Program",
                WS OVERLAPPEDWINDOW,
                                          /* window style
                                          /* initial x position
                0,
                                          /* initial y position
                0.
                                          /* initial x size
                CW USEDEFAULT,
                                          /* initial y size
                0,
                                          /* parent window handle
                NULL,
                                          /* window menu handle
                NULL,
                                         /* program instance handle */
/* create parameters */
                hInstance,
                NULL) ;
ShowWindow (hWnd, nCmdShow) ;
UpdateWindow (hWnd) ;
hWndMain = hWnd ;
                                         /* window class name
hWnd = CreateWindow (szPopupClass,
                "Popup with Parent",
                                          /* window caption
                WS POPUP | WS CAPTION | /* window style
                     WS SYSMENU | WS THICKFRAME | WS MAXIMIZEBOX,
                                          /* initial x position
                xScreen / 9,
                                          /* initial y position
/* initial x size
                yScreen / 8,
xScreen / 3,
yScreen / 4,
                                          /* initial y size
```

Figure 2-13. Continued

```
hWndMain,
                                                                    /* parent window handle
                           NULL,
                                                                    /* window menu handle */
/* program instance handle */
                           hInstance,
                           NULL) ;
                                                                      /* create parameters
ShowWindow (hWnd, SW SHOWNORMAL) ;
UpdateWindow (hWnd) ?
hWndPopup1 = hWnd ;
hWnd = CreateWindow (szPopupClass,
                          indow (szPopupClass, /* window class name
"Popup without Parent", /* window caption
WS_POPUP | WS_CAPTION | /* window style
                                   WS_SYSMENU | WS_THICKFRAME | WS_MAXIMIZEBOX,
                          5 * xScreen / 9, /* initial x position */
yScreen / 8, /* initial y position */
xScreen / 3, /* initial x size */
yScreen / 4, /* initial x size */
NULL, /* initial y size */
NULL, /* parent window handle */
NULL, /* window menu handle */
hInstance, /* program instance handle */
NULL); /* create parameters */
ShowWindow (hWnd, SW_SHOWNORMAL) ;
UpdateWindow (hWnd) ;
hWndPopup2 = hWnd ;
hWnd = CreateWindow (szChildClass, /* window class name "Child Window 1", /* window caption
                          WS_CHILD | WS_CAPTION | /* window style
WS_CLIPSIBLINGS | WS_SYSMENU |
WS_THICKFRAME | WS_MAXIMIZEBOX,
                                                                    /* initial x position
/* initial y position
/* initial x size
/* initial y size
                          xScreen / 9,
yScreen / 2,
xScreen / 3,
yScreen / 4,
hWndMain,
                                                                   /* parent window handle */
/* window menu handle */
/* program instance handle */
/* create parameters */
                          hInstance,
                          NULL) ;
ShowWindow (hWnd, SW SHOWNORMAL) ;
UpdateWindow (hWnd) ;
hWnd = CreateWindow (szChildClass, /* window class name "Child Window 2", /* window caption
                          WS_CHILD | WS_CAPTION | /* window style
WS_CLIPSIBLINGS | WS_SYSMENU |
WS_THICKFRAME | WS_MAXIMIZEBOX,
                          5 * xScreen / 9,
yScreen / 2,
xScreen / 3,
vScreen / 4.
                                                                     /* initial x position
                                                                    /* initial y position
                                                                   /* initial x size
/* initial y size
                          yScreen / 4,
```

Figure 2-13. Continued

```
/* parent window handle
                     hWndMain,
                                              /* window menu handle
                     2,
                                              /* program instance handle */
                     hInstance,
                     NULL) ;
                                              /* create parameters
    ShowWindow (hWnd, SW SHOWNORMAL) ;
     UpdateWindow (hWnd) :
                    indow ("Edit", /* window class name
"Edit Box Text", /* window caption
    hWnd = CreateWindow ("Edit",
                     WS_CHILD | WS_BORDER | /* window style
                         WS VSCROLL | WS HSCROLL | ES_MULTILINE | ES_AUTOVSCROLL | ES_AUTOHSCROLL,
                     10,
                                               /* initial x position
                                              /* initial y position
/* initial x size
                    10,
                    xScreen / 4,
yScreen / 8,
hWndPopupl,
                                              /* initial y size
                                             /* parent window handle
/* window menu handle
                     3,
                     hInstance,
                                              /* program instance handle */
/* create parameters */
                     NULL) ;
     ShowWindow (hWnd, SW SHOWNORMAL) ;
     UpdateWindow (hWnd) 7
    /* initial x position
                     10,
                                               /* initial y position
                     10,
                     xScreen / 4,
yScreen / 8,
bWndPopun2
                                              /* initial x size
                                           /* initial y size
/* parent window handle
/* window menu handle
                     hWndPopup2,
                                              /* program instance handle */
                     hInstance,
                                              /* create parameters
                     NULL) ;
     ShowWindow (hWnd, SW_SHOWNORMAL) ;
     UpdateWindow (hWnd) ;
     while (GetMessage (&msg, NULL, 0, 0))
          TranslateMessage (&msg) ;
          DispatchMessage (&msg) ;
     return msg.wParam ;
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
     HWND hWnd ;
     unsigned iMessage ;
     WORD wParam;
     LONG
             1Param :
     switch (iMessage)
          case WM DESTROY:
               PostQuitMessage (0) ;
                break ;
```

Figure 2-13. Continued

```
default:
              return DefWindowProc (hWnd, iMessage, wParam, 1Param) ;
     return OL ;
long FAR PASCAL PopupWndProc (hWnd, iMessage, wParam, 1Param)
             hWnd :
     unsigned iMessage ;
     WORD
            wParam :
     LONG
             lParam ;
     return DefWindowProc (hWnd, iMessage, wParam, 1Param) ;
long FAR PASCAL ChildWndProc (hWnd, iMessage, wParam, 1Param)
     HWND
             hWnd ;
    unsigned iMessage ;
            wParam ;
     WORD
     LONG
             1Param ;
    return DefWindowProc (hWnd, iMessage, wParam, 1Param) ;
```

```
NAME
              PARTY
DESCRIPTION
               'Overlapped, Popup, and Child Windows (C) Charles Petzold, 1987
STUB
              'WINSTUB. EXE'
CODE
               MOVEABLE
DATA
              MOVEABLE MULTIPLE
HEAPSIZE
               1024
STACKSIZE
               4096
EXPORTS
               WndProc
               PopupWndProc
               ChildWndProc
```

PARTY registers three window classes, "Party," "Party_Popup," and "Party_Child," corresponding to the window functions *WndProc*, *PopupWndProc*, and *ChildWndProc*. The "Party" window class is used for a single overlapped window, "Party_Popup" for two popup windows (just as in WELCOME5), and "Party_Child" for two child windows displayed near the bottom of the overlapped window. These are child windows of the overlapped window. Each of the two popup windows also has a child window. All seven windows in PARTY are shown in Figure 2-14 (on the following page).

If you look at the *CreateWindow* calls for the child windows of the popups, you'll see that one of the child windows uses a window class named "Edit" and the other a window class named "Button." These two window classes (as well as "Static," "Listbox," and "Scrollbar") are predefined by Windows, and their window functions are contained within Windows. The queued messages for child windows you create based on these window




Figure 2-14. The PARTY display

classes still come through your program's message queue, but the messages are dispatched and processed in the appropriate window function contained in Windows.

The child window contained in the popup window on the left is an edit box with scroll bars. If you click on that child window with the mouse, you can type in text, scroll the text, and even copy it to the clipboard. The window function for the "Edit" window class is apparently doing more than simply calling <code>DefWindowProc</code>. The child window contained in the other popup is a push button. When you click the push button with the mouse, it flashes.

Here are some basic facts about child windows that PARTY demonstrates:

- The initial position of the child window given in the CreateWindow call is relative
 to the upper left corner of its parent window—not the upper left corner of the
 screen, which is the case for overlapped windows and popup windows. The
 window menu handle in the CreateWindow call is set to a "child window ID."
 We'll examine the reason for this in Chapter 7.
- As noted earlier, child windows always follow their parent around the screen. If you move the overlapped window or the popup windows, the child windows stay in the same position relative to their parent. This is not the case for a popup window with a parent.
- The two windows that are children of the overlapped window were created with WS_SYSMENU style. However, the system menu box looks a little different from the system menu of overlapped and popup windows. Although you can maximize,

move, and size these two child windows, the primary function of a child window's system menu is to close the window; for this reason, a system menu box on a child window is sometimes called a "close box."

- If you move one of these child windows beyond the overlapped window's client
 area, it is clipped. Child windows cannot appear outside the client area of their
 parent. If you maximize either of these child windows, it does not fill up the entire
 screen but only the client area of its parent.
- The caption bars of child windows do not indicate that the child window is active, even if you click the child window with the mouse. Child windows are never active windows.

OK, party's over. Let's send the popups and children away for a while and concentrate on the overlapped window. So far, it has only other windows in its client area. We're ready to give it something more.

Chapter 3

Painting the Client Area with Text

In the previous chapter we constructed a simple window, but we didn't use it to display anything except other windows. All we did was build a frame surrounding a nice white canvas. Now it's time to paint.

The part of the window that your program is free to paint is called the "client area." The client area occupies all the space of the window that is not taken up by the caption bar, the window border or frame, the menu bar (if any), and scroll bars (if any). You can do almost anything you want with that client area—anything, that is, except assume that it will be a particular size or that the size will remain constant while your program is running. If you are accustomed to writing programs for the IBM PC, this exception may come as a bit of a shock. You can no longer think in terms of 25 lines and 80 columns of text. Your program shares the video display with other Windows programs. The user controls how the programs are arranged on the screen. Your program must accept the size it's given and do something reasonable with it.

This works both ways. Just as your program may find itself with a client area barely large enough in which to say "Hello," it may also someday be run on a big-screen high-resolution video system and discover a client area big enough for two entire pages of text and plenty of closet space besides. Dealing intelligently with both these eventualities is an important part of Windows programming.

Although Windows has extensive Graphics Device Interface (GDI) functions for displaying graphics, in this chapter we stick to displaying simple lines of text. We also ignore the various fonts (typefaces) and font sizes that Windows makes available and use only Windows' default "system font." This may seem limiting, but it's really not. The problems we encounter—and solve—in this chapter apply to all Windows programming. When you display a combination of text and graphics (as, for instance, the Windows CALENDAR, CARDFILE, and CALC programs do), the character dimensions of Windows' default system font often determine the dimensions of the graphics.

This chapter is ostensibly about learning how to paint, but it's really about learning the basics of device-independent programming. Windows programs can assume little about their environment. Instead, they must use the facilities that Windows provides to obtain information about the environment.

If you're impatient to display some text in the client area of a window, you can replace the WndProc function in WELCOME2.C in Chapter 2 with the function shown here:

```
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
    HWND
                hWnd ;
               iMessage ;
    unsigned
                wParam ;
    WORD
    LONG
                lParam ;
    static char szText [] = "Hello" ;
     static short xChar, yChar;
                 hDC :
     PAINTSTRUCT ps ;
    TEXTMETRIC tm ;
     switch (iMessage)
          case WM_CREATE:
              hDC = GetDC (hWnd) ;
              GetTextMetrics (hDC, &tm);
              xChar = tm.tmAveCharWidth ;
              yChar = tm.tmHeight ;
              ReleaseDC (hWnd, hDC);
              break ;
          case WM_PAINT:
              hDC = BeginPaint (hWnd, &ps);
               TextOut (hDC, xChar, yChar, szText, sizeof szText - 1) ;
               EndPaint (hWnd, &ps) ;
              break ;
          case WM_DESTROY:
              PostQuitMessage (0) ;
              break ;
              return DefWindowProc (hWnd, iMessage, wParam, lParam) ;
     return OL ;
```

This version of WndProc displays the word Hello in the upper left corner of the client area. The text begins one character to the right of the left window border and one character below the bottom of the caption bar.

I don't expect this code example to make much sense at this point. There's a lot to cover here, including the processing of WM_PAINT messages, getting device context handles, determining the size of a character, and actually displaying the text. You may want to look back at this example as we tackle these subjects below.

PAINTING AND REPAINTING

Under MS-DOS, a program using the display in a full-screen mode can write to any part of the display. What the program puts on the display will stay there and will not mysteriously disappear. The program can then discard information needed to recreate the screen display. If another program (such as a RAM-resident popup) overlays part of the display, then the popup is responsible for restoring the display when it leaves.

In Windows, you can write only to the client area of your window, and you cannot be assured that what you write to the client area will remain there until your program specifically writes over it. For instance, the dialog box from another application may overlay part of your client area. Although Windows will attempt to save and restore the area of the display underneath the dialog box, it sometimes cannot do so. When the dialog box is removed from the screen, Windows will request that your program repaint this portion of your client area.

Windows is a message-driven system. Windows informs applications of various events by posting messages in the application's message queue or sending messages to the appropriate window function. Windows informs a window function that part of the window's client area needs updating by posting a WM_PAINT message.

The WM_PAINT Message

Most Windows programs call the function *UpdateWindow* during initialization in *WinMain* shortly before entering the message loop. Windows takes this opportunity to send the window function its first WM_PAINT message. That message informs your window function that the client area is ready to be painted. Thereafter, that window function should be ready at any time to process additional WM_PAINT messages and even repaint the entire client area of the window if necessary. A window function receives a WM_PAINT message whenever one of the following occurs:

- A previously hidden area of the window is brought into view when a user moves a window or uncovers a window.
- The user resizes the window (if the window class style has the CS_HREDRAW and CS_VREDRAW bits set).

- The program uses the ScrollWindow function to scroll part of its client area.
- The program uses the InvalidateRect or InvalidateRgn function to explicitly generate a WM_PAINT message.

In some other cases when part of the client area is temporarily written over, Windows attempts to save an area of the display and restore it later. In some cases, this is not successful. Windows may sometimes post a WM_PAINT message when:

- Windows removes a dialog box or message box that has overlaid part of the window.
- A menu is pulled down and then released.

In a few cases, Windows always saves the area of the display it overwrites and then restores it. This is the case whenever:

- The cursor is moved across the client area.
- · An icon is dragged across the client area.

Dealing with WM_PAINT messages requires that you alter your thinking about how you write to the display. Your program should be structured so that it accumulates all the information necessary to paint the client area but paints only "on demand"—when Windows sends the window function a WM_PAINT message. If your program needs to update its client area, it can force Windows to generate this WM_PAINT message. This may seem a round-about method to display something on the screen, but the structure of your programs benefits from it.

Valid and Invalid Rectangles

Although a window function should be prepared to update the entire client area whenever it receives a WM_PAINT message, it often needs to update only a smaller rectangular area. This is most obvious when part of the client area is overlaid by a dialog box. Repainting is required only for the rectangular area uncovered when the dialog box is removed.

That rectangular area is known as an "invalid rectangle." The presence of an invalid rectangle in a client area is what prompts Windows to place a WM_PAINT message in the application's message queue. Your window function receives a WM_PAINT message only if part of your client area is invalid.

Windows internally maintains a "paint information structure" for each window. This structure contains (among other information) the coordinates of the invalid rectangle. If another rectangular area of the client area becomes invalid before the window function processes the WM_PAINT message, Windows calculates a new invalid rectangle that encompasses both areas and stores this updated information in the paint information structure. Windows does not place multiple WM_PAINT messages in the message queue.

A window function can invalidate a rectangle in its own client area by calling *InvalidateRect*. If the message queue already contains a WM_PAINT message, Windows calculates a new invalid rectangle. Otherwise, it places a WM_PAINT message in the message queue. A window function can obtain the coordinates of the invalid rectangle when it receives a WM_PAINT message (as we'll see shortly). It can also obtain these coordinates at any other time by calling *GetUpdateRect*.

After the window function processes the WM_PAINT message, the entire client area is validated. A program can also validate any rectangular region in the client area by calling the *ValidateRect* function. If this call has the effect of validating the entire invalid area, then any WM_PAINT messages pending in the queue are removed.

AN INTRODUCTION TO GDI

To paint the client area of your window, you use Windows' Graphics Device Interface (GDI) functions. (A full discussion of GDI is in Chapters 12–16.) Windows has four different GDI functions for writing text strings to the client area of the window, but the function used most often is *TextOut*. This function has the following format:

TextOut (hDC, x, y, lpsString, nLength)

TextOut writes a character string to the display. The *lpsString* parameter is a long (or far) pointer to the character string, and *nLength* is the length of the string. The x and y parameters define the starting position, in "logical coordinates," of the character string in the client area. The *hDC* parameter is a "handle to a device context," and it is an important part of GDI. Virtually every GDI function requires this handle as the first parameter to the function.

The Device Context

A handle, you'll recall, is simply a number that Windows uses for internal reference. You obtain the handle from Windows and then use the handle in other functions. The device context handle is your window's passport to the GDI functions. With that device context handle you are free to paint your client area and make it as beautiful or as ugly as you like.

The device context (also called the "DC") is really a data structure maintained by GDI. A device context is always associated with a particular display device, such as a printer, plotter, or video display. For a video display, a device context is usually associated with a particular window on the display.

Windows uses the values in the device context structure (also called "attributes" of the device context) in conjunction with the GDI functions. For *TextOut*, for instance, the attributes of the device context determine the color of the text, the color of the background behind the text, how the x and y coordinates are mapped to the client area of the window, and what font Windows uses when displaying the text.

When a program needs to paint, it must first obtain a handle to a device context. After it has finished painting, the program should release the handle. When a program releases the handle, the handle is no longer valid and must not be used. The program should obtain the handle and release the handle during processing of a single message. Device contexts are considered "expensive" in terms of memory, and you should not keep an active device context handle around from one message to another.

Windows applications generally use two different methods for getting the handle to the device context in preparation for painting the screen.

Getting a Device Context Handle: Method One

You use this method when you process WM_PAINT messages. Two functions are involved: BeginPaint and EndPaint. These two functions require the handle to the window (passed to the window function as a parameter) and the address of a structure variable of type PAINTSTRUCT. Windows programmers usually name this structure variable ps and define it within the window function, like so:

```
PAINTSTRUCT ps ;
```

While processing a WM_PAINT message, a Windows function first calls *BeginPaint* to fill in the fields of the *ps* structure. The value returned from *BeginPaint* is the device context handle. This is commonly saved in a variable named *hDC*. You define this variable in your window function like this:

```
HDC hDC ;
```

The HDC data type is defined in WINDOWS.H as a HANDLE. The program may then use GDI functions such as *TextOut*. A call to *EndPaint* releases the device context handle and validates the window.

Typically, processing of the WM_PAINT message looks like this:

The window function must call <code>BeginPaint</code> and <code>EndPaint</code> as a pair while processing the <code>WM_PAINT</code> message. If a window function does not process <code>WM_PAINT</code> messages, then it must pass the <code>WM_PAINT</code> message to <code>DefWindowProc</code> (the default window function) located in Windows. The <code>WELCOME</code> programs did this in the previous chapter.

DefWindowProc processes WM_PAINT messages with the following code:

```
case WM_PAINT:
    BeginPaint (hWnd, &ps) ;
    EndPaint (hWnd, &ps) ;
    break ;
```

This sequence of *BeginPaint* and *EndPaint* with nothing in between simply validates the previously invalid rectangle. But don't do this:

```
case WM_PAINT:
break; /* WRONG !!! */
```

Windows places a WM_PAINT message in the message queue because part of the client area is invalid. Unless you call *BeginPaint* and *EndPaint*, Windows will not validate that area. Instead, Windows will send you another WM_PAINT message. And another, and another, and another...

The Paint Information Structure

Earlier I mentioned a "paint information structure" that Windows maintains for each window. That's what PAINTSTRUCT is. The fields of this structure that your program may use are the following:

hdc Device context handle

fErase Background has been redrawn if nonzero

rcPaint.left Invalid rectangle: left
rcPaint.top Invalid rectangle: top
rcPaint.right Invalid rectangle: right
rcPaint.bottom Invalid rectangle: bottom

Windows uses several other fields internally.

The hdc field is the handle to the device context. In a redundancy typical of Windows, the value returned from BeginPaint is also this device context handle.

In most cases, fErase will be flagged TRUE (nonzero), meaning that Windows has erased the background of the invalid rectangle. Windows erases the background using the brush specified in the hbrBackground field of the WNDCLASS structure that you use when registering the window class during WinMain initialization. Many Windows programs use a white brush:

```
wndclass.hbrBackground = GetStockObject (WHITE_BRUSH) ;
```

However, if your program invalidates a rectangle of the client area by calling the Windows function *InvalidateRect*, one of the parameters to this function specifies whether you want the background erased. If this parameter is FALSE (or 0), then Windows will not erase the background, and the *fErase* field will also be FALSE.

The rcPaint field of the PAINTSTRUCT structure is a structure of type RECT, which stands for "rectangle." The RECT structure is defined in WINDOWS.H and has four fields—left, top, right, and bottom. These four fields define the boundaries of the invalid rectangle, as shown in Figure 3-1. The values are in units of pixels relative to the upper left corner of the client area. The invalid rectangle is the area that you should repaint. Although a Windows program can simply repaint the entire client area of the window whenever it receives a WM_PAINT message, repainting only the area of the window defined by that rectangle saves time.




Figure 3-1. The boundaries of the invalid rectangle

The rcPaint rectangle in PAINTSTRUCT is not only the invalid rectangle, it is also a "clipping" rectangle. This means that Windows restricts painting to within the clipping rectangle. When you use the device context handle from the PAINTSTRUCT structure, Windows will not paint outside the rcPaint rectangle.

To paint outside this *rcPaint* rectangle while processing WM_PAINT messages, you can make this call:

```
InvalidateRect (hWnd, NULL, TRUE) ;
```

before calling *BeginPaint*. This invalidates the entire client area and erases the background. A FALSE value in the last parameter will not erase the background, however. Whatever was there will stay.

In the code fragment shown earlier that displayed "Hello" in the client area, we didn't care about invalid rectangles or clipping rectangles when processing the WM_PAINT message. If the area where the text was displayed happened to be within the invalid rectangle, then TextOut restored it. If not, then at some point during processing of the TextOut call, Windows determined it didn't have to write anything to the display. But this determination takes time. A programmer concerned about performance and speed will want to use the invalid rectangle dimensions during processing of WM_PAINT to avoid unnecessary GDI calls.

Getting a Device Context Handle: Method Two

You can also obtain a handle to a device context if you want to paint the client area when processing messages other then WM_PAINT or if you need the device context handle for other purposes, such as obtaining information about the device context. Call GetDC to obtain the handle to the device context, and ReleaseDC after you're done with it:

```
hDC = GetDC (hWnd) ;

/use GDI functions/
ReleaseDC (hWnd, hDC) ;
```

Like BeginPaint and EndPaint, the GetDC and ReleaseDC functions should be called in pairs. When you call GetDC while processing a message, you should call ReleaseDC before you exit the window function. Do not call GetDC in response to one message and ReleaseDC in response to another.

Unlike the device context handle obtained from the PAINTSTRUCT structure, the device context handle returned from *GetDC* has a clipping rectangle equal to the entire client area. You can paint on any part of the client area, not merely on the invalid rectangle (if indeed there is an invalid rectangle). Unlike *EndPaint*, *ReleaseDC* does not validate any invalid rectangles.

TextOut: The Details

When you obtain the handle to the device context, Windows fills the device context structure with default values. As you'll see in later chapters, you can change these defaults with GDI functions. The GDI function we're interested in right now is TextOut:

TextOut (hDC, x, y, lpsString, nLength)

Let's examine this function in more detail.

The first parameter is the handle to the device context—either the hDC value returned from GetDC or the hDC value returned from BeginPaint during processing of a WM_PAINT message.

The attributes of the device context control the characteristics of this displayed text. For instance, one attribute of the device context specifies the text color. The default color is black. The default device context also defines a background color of white. When a program writes text to the display, Windows uses this background color to fill in the spaces between the characters.

This text background color is not the same background you set when defining the window class. The background in the window class is a brush—which is a pattern that may or may not be a pure color—that Windows uses to erase the client area. It is not part of the device context structure. When defining the window class structure, most Windows applications use WHITE_BRUSH so that the background color in the default device context is the same color as the brush Windows uses to erase the background of the client area.

The *lpsString* parameter is a long pointer to a character string, and *nLength* is the length of the string. The string should not contain any ASCII control characters such as carriage returns, linefeeds, tabs, or backspaces. Windows displays these control characters as solid blocks. *TextOut* does not recognize a 0 as denoting the end of the string and requires the *nLength* parameter for the length.

(The Windows *DrawText* function is another text output function that works on a higher level than *TextOut. DrawText* recognizes null-terminated character strings, embedded carriage returns, linefeeds, and tabs and can even wordwrap. But *DrawText* is a little clumsy for displaying single lines of text.)

The x and y values in *TextOut* define the starting point of the character string within the client area. The x value is the horizontal position; the y value is the vertical position. The upper left corner of the first character in the string is positioned at x and y. In the default device context, the origin (the point where x and y both equal 0) is the upper left corner of the client area. If you use 0 values for x and y in *TextOut*, the character string starts flush against the upper left corner of the client area.

GDI coordinates are "logical coordinates." Windows has a variety of "mapping modes" that govern how the logical coordinates specified in GDI functions are translated to the physical pixel coordinates of the display. The mapping mode is defined in the device context. The default mapping mode is called MM_TEXT (using the WINDOWS.H identifier). Under the MM_TEXT mapping mode, logical units are the same as physical units, which are pixels. Values of x increase as you move to the right of the client area and of y increase as you move down the client area. (See Figure 3-2.) The MM_TEXT coordinate system is identical to the coordinate system Windows uses to define the invalid rectangle in the PAINTSTRUCT structure. Very convenient. (This is not the case with other mapping modes, however.)

The device context also defines a clipping region. As you've seen, the default clipping region is the entire client area for a device context handle obtained from <code>GetDC</code> and the invalid rectangle for the device context handle obtained from <code>BeginPaint</code>. Windows will not display any part of the character string that lies outside the clipping rectangle. If a character is partly within the clipping rectangle, Windows displays only the portion of the character inside the rectangle. Writing outside the client area of your window isn't easy, so don't worry about doing it inadvertently.




Figure 3-2. The x and y coordinates in the MM_TEXT mapping mode

The System Font

The device context also defines the font that Windows uses when writing text to the client area. The default is a font called the "system font" or (using the WINDOWS.H identifier) SYSTEM_FONT. This is a fixed-pitch nonproportional font—every character has the same width. Windows uses the system font for much of the normal text displayed in Windows, such as the text in caption bars, menus, and message boxes.

The system font is a "raster font," which means that the characters of the font are defined as blocks of pixels. The Windows installation disks include various files that contain system fonts and "terminal fonts" for the common video display boards. (The terminal font—also called an OEM font or OEM_FIXED_FONT in WINDOWS.H—is similar to the system font but uses a different character set. This is discussed further in Chapter 4.) During installation of Windows, the SETUP program merges the appropriate system and terminal font files into WIN200.BIN. If you run a "slow boot" version of Windows, the system and terminal fonts are in files called FONTS.FON and OEMFONTS.FON in your Windows directory. The other font files that appear in your Windows directory are discussed in detail in Chapter 15.

When manufacturers of a new video board develop a new Windows display driver, they are also responsible for developing a new system font appropriate for the resolution of the display. Alternatively, the manufacturer might specify that one of the system font files supplied with the retail version of Windows be used. The system font must be designed so that at least 25 lines of 80-character text can fit on the display. That is the only guarantee you have about the relationship between screen size and font size in Windows.

The Size of a Character

To display multiple lines of text using the *TextOut* function, you need to determine the dimensions of the font characters. You can space successive lines of text based on the height of a character, and you can space columns of text across the client area based on the width of a character.

You can obtain character dimensions with the GetTextMetrics call. GetTextMetrics requires a handle to the device context because it returns information about the font currently selected in the device context. Windows copies the various values of text metrics into a structure of type TEXTMETRIC. The values are in units that depend on the mapping mode selected in the device context. In the default device context, this mapping mode is MM_TEXT, so the dimensions are in units of pixels.

To use the GetTextMetrics function, you first need to define a structure variable (commonly called tm):

```
TEXTMETRIC tm ;
```

Next, get a handle to the device context and call GetTextMetrics:

```
hDC = GetDC (hWnd) ;
GetTextMetrics (hDC, &tm) ;
```

After you examine the values in the text metric structure (and probably save a few of them for future reference), you release the device context:

```
ReleaseDC (hWnd, hDC) ;
```

Text Metrics Details

The TEXTMETRIC structure provides a wealth of information about the current font selected in the device context. However, the basic character size for a simple fixed-pitch font (such as the system font) is defined by only six values, as shown in Figure 3-3.




Figure 3-3. The six values defining character size in a fixed-pitch font

The *tmAveCharWidth* includes intercharacter spacing. This value refers to an "average" character width because some fonts have different widths for each character. The text metrics structure also includes a *tmMaxCharWidth* value. For a fixed-pitch font such as SYSTEM_FONT, the two values are the same.

The *tmInternalLeading* value is the space allowed for accent marks above the character. If it is set to 0, accented capital letters are made a little shorter so that the accent fits within the ascent of the character.

The *tmExternalLeading* value is an amount of space that the designer of the font is suggesting be added between character rows. You can accept or reject the font designer's suggestion for including external leading when spacing lines of text.

To give you an idea of the variability of font dimensions, this table shows text metrics values for four system font files distributed with Windows and for three high-resolution video adapters. (Video adapter A is the Moniterm Viking 1; B, the Vermont Microsystems Image Manager 1024; and C, the Sigma Designs LaserView.)

					Video Adapter		
	FONTLO	FONTHI	FONT40	FONTSQ	A	В	C
Resolution							
(H x V):	640 x 200	640 x 350	640 x 400	640 x 480	1280 x 960	1024 x 800	1664 x 1200
tmHeight:	8	10	13	15	16	18	24
tmAscent:	7	9	10	12	13	10	20
tmDescent:	1	1	3	3	3	8	4
tmInternalLeading:	0	2	0	3	0	0	0
tmExternalLeading	: 1	0	2	0	0	0	4
tmAveCharWidth:	8	8	8	8	12	12	16

The purpose of this table is to scare you into thinking about device independence. Windows provides a device-independent graphics interface, but you have to help. Don't write your Windows program so that it guesses at character dimensions. Don't hard code any values. Use the Windows tools to obtain this information.

Formatting Text

Because the dimensions of the system font do not change during a Windows session, you need to call GetTextMetrics only once when your program executes. A good place to make this call is while processing the WM_CREATE message in the window function. Windows calls your window function with a WM_CREATE message when you call CreateWindow in WinMain.

Within the window function you define two variables to save the character width (xChar) and height (yChar):

```
static short xChar, yChar;
```

These variables are defined as *static* because they must be valid when the window function processes other messages (such as WM_PAINT). If the variables are defined outside any functions, they need not be defined as *static*.

Here's the WM_CREATE code:

```
WM_CREATE:
   hDC = GetDC (hWnd) ;
   GetTextMetrics (hDC, &tm) ;
   xChar = tm.tmAveCharWidth ;
   yChar = tm.tmHeight + tmExternalLeading ;
   ReleaseDC (hWnd, hDC) ;
   break ;
```

If you do not wish to include external leading to space lines of text, you can use:

```
yChar = tm.tmHeight;
```

How you use this character size to calculate display coordinates is up to you. A simple method is to leave a *yChar* margin at the top of the client area and an *xChar* margin at the left. To display several lines of left-justified text, the *x* coordinate values when calling the *TextOut* function are:

```
xChar
```

The y coordinate values in TextOut are:

```
yChar * (1 + i)
```

where i is the line number starting at 0.

You may prefer basing coordinates on something finer than the entire size of a single character. When we start to design dialog boxes (a subject covered in Chapter 11), we'll work with horizontal coordinates in units of ½ the character width and vertical coordinates based on ½ the character height. You may also find these units convenient for painting your client area.

You'll often find it necessary to display formatted numbers as well as simple character strings. If you were programming in MS-DOS using normal C functions, you would probably use *printf* for this formatting. You cannot use *printf* in Windows, because it writes to the standard output device. Windows intercepts normal DOS and BIOS display output and throws such output away.

Instead, you can use *sprintf*. The *sprintf* function works just like *printf* except that it puts the formatted string into a character array. You can then use *TextOut* to write the string to the display. Very conveniently, the value returned from *sprintf* is the length of the string—you can pass this value to *TextOut* as the *nLength* parameter. This code shows a typical *sprintf* and *TextOut* combination:

For something as simple as this you could dispense with the *nLength* definition and combine the two statements into one:

It's not pretty, but it works.

Putting It All Together

Now we seem to have everything we need to write a simple program that displays multiple lines of text on the screen. We know how to get a handle to a device context, how to use the *TextOut* function, and how to space text based on the size of a single character. The only thing left is something interesting to display.

The information available in the Windows GetSystemMetrics call looks interesting enough. This function returns information about the size of various graphical items in Windows, such as icons, cursors, caption bars, and scroll bars. These sizes vary with the display adapter and driver. GetSystemMetrics requires a single parameter called an "index." This index is 1 of 37 integer identifiers defined in WINDOWS.H. GetSystemMetrics returns an integer, usually the size of the item specified in the parameter.

Let's write a program that displays all the information available from the GetSystem-Metrics call in a simple one-line-per-item format. Working with this information is easier if we create a header file that defines an array of structures containing both the WINDOWS.H identifiers for the GetSystemMetrics index and the text we want to display for each value returned from the call. This header file is called SYSMETS.H and is shown in Figure 3-4.

```
/* SYSMETS.H -- System Metrics display structure */
#define NUMLINES (sizeof sysmetrics / sizeof sysmetrics [0])
struct
      int nIndex ;
      char *szLabel ;
      char *szDesc ;
      sysmetrics [] =
                            "SM CXSCREEN",
      SM CXSCREEN,
                                                     "Screen width in pixels",
                                                    "Screen height in pixels"
      SM CYSCREEN,
                           "SM CYSCREEN"
      SM CXVSCROLL,
                           "SM CXVSCROLL",
                                                     "Vertical scroll arrow width",
                           "SM CYHSCROLL",
      SM CYHSCROLL,
                                                    "Horizontal scroll arrow height",
                          "SM CYCAPTION",
     SM_CYCAPTION,
SM_CXBORDER,
                                                     "Caption bar height",
                          "SM_CXBORDER",
                                                    "Border width"
     SM CYBORDER,
                           "SM CYBORDER"
                                                     "Border height"
      SM_CXDLGFRAME,
                            "SM_CXDLGFRAME",
                                                     "Dialog window frame width",
                            "SM CYDLGFRAME",
      SM_CYDLGFRAME,
                                                     "Dialog window frame height"
                           "SM_CYVTHUMB",
"SM_CXHTHUMB",
      SM CYVTHUMB,
                                                    "Vertical scroll thumb height"
      SM CXHTHUMB,
                                                    "Horizontal scroll thumb width",
                            "SM CXICON",
      SM CXICON,
                                                     "Icon width"
      SM_CYICON,
                            "SM CYICON",
                                                     "Icon height"
     SM_CXCURSOR, "SM_CXCURSOR", "Cursor width", SM_CYCURSOR, "SM_CYCURSOR", "Cursor height", SM_CYMENU. "SM_CYMENU. "SM_CYMENU."
                           "SM CYMENU",
      SM CYMENU,
                                                    "Menu bar height",
     SM_CXFULLSCREEN, "SM_CXFULLSCREEN", "Full screen client wi
SM_CYFULLSCREEN, "SM_CYFULLSCREEN", "Full screen client wi
SM_CYKANJIWINDOW, "SM_CYKANJIWINDOW", "Kanji window height",
                                                    "Full screen client window width",
                                                    "Full screen client window height",
     SM MOUSEPRESENT, "SM MOUSEPRESENT", "Mouse present flag", SM_CYVSCROLL, "SM CYVSCROLL", "Vertical scroll are CXHSCROLL, "SM_CXHSCROLL", "Horizontal scroll are
                                                    "Vertical scroll arrow height",
     SM_CXHSCROLL,
SM_DEBUG,
                                                    "Horizontal scroll arrow width",
                          "SM SWAPBUTTON",
"SM RESERVED1",
"SM RESERVED2",
                          "SM DEBUG",
                                                    "Debug version flag",
     SM_SWAPBUTTON,
                                                     "Mouse buttons swapped flag",
     SM RESERVEDI,
                                                    "Reserved",
     SM_RESERVED2,
                       "SM_RESERVEDS",
"SM_RESERVED4",
"SM_RESERVED4",
"SM_CXMIN",
"SM_CYMIN",
                                                     "Reserved",
     SM RESERVED3,
                                                     "Reserved"
     SM RESERVED4,
                                                     "Reserved"
                       "SM_CXMIN",
     SM CXMIN,
                                                     "Minimum window width"
     SM CYMIN,
                                                    "Minimum window height",
                                            "Minimize/Maximize icon height",
     SM_CXSIZE,
                           "SM CXSIZE",
                     "SM_CYSIZE", "Minimize/Maximize 1:
"SM_CXFRAME", "Window frame width"
"SM_CYFRAME", "Window frame height
"Minimum tracking wi
     SM CYSIZE,
     SM CXFRAME,
     SM CYFRAME,
                                                    "Window frame height"
                            "SM CXMINTRACK",
     SM_CXMINTRACK,
                                                     "Minimum tracking width of window",
     SM CYMINTRACK,
                            "SM_CYMINTRACK",
                                                     "Maximum tracking width of window",
     SM CMETRICS,
                            "SM CMETRICS",
                                                     "Number of system metrics"
```

Figure 3-4. SYSMETS.H

The program that displays this information is called SYSMETS1. The files required to create SYSMETS1.EXE (make file, C source code, and module definition file) are shown in Figure 3-5 (on the following page). Most of the code should look familiar by now. With the exception of the program name, the DEF and make files are identical to those for WELCOME2. In SYSMETS1.C, WinMain is virtually identical to WELCOME2, and much of the new code in WndProc has been described above.

```
sysmetsl.obj : sysmetsl.c sysmets.h
cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp sysmetsl.c
sysmetsl.exe : sysmetsl.obj sysmetsl.def
link4 sysmetsl, /align:16, /map, slibw, sysmetsl
```

```
/* SYSMETS1.C -- System Metrics Display Program No. 1 */
#include <windows.h>
#include <stdio.h>
#include "sysmets.h"
long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG) ;
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
     HANDLE hInstance, hPrevInstance;
     LPSTR
              lpszCmdLine ;
     int
              nCmdShow ;
     static char szAppName [] = "SysMetsl" ;
              hwnd ;
     HWND
     MSG
              msq ;
     WNDCLASS wndclass :
     if (!hPrevInstance)
                                = CS HREDRAW | CS VREDRAW ;
          wndclass.style
          wndclass.lpfnWndProc = WndProc ;
          wndclass.cbClsExtra = 0;
          wndclass.cbWndExtra
                                 = 0 ;
          wndclass.hInstance
                                 = hInstance ;
          wndclass.hCon = LoadIcon (NULL, IDI APPLICATION)
wndclass.hCursor = LoadCursor (NULL, IDC_ARROW);
          wndclass.hbrBackground = GetStockObject (WHITE BRUSH) ;
          wndclass.lpszMenuName = NULL
          wndclass.lpszClassName = szAppName ;
          if (!RegisterClass (&wndclass))
               return FALSE ;
     hWnd = CreateWindow (szAppName, "Get System Metrics",
                          WS OVERLAPPEDWINDOW,
                          CW USEDEFAULT, 0,
                          CW USEDEFAULT, 0,
                          NULL, NULL, hinstance, NULL) ;
     ShowWindow (hWnd, nCmdShow) ;
     UpdateWindow (hWnd) ;
     while (GetMessage (&msg, NULL, 0, 0))
          TranslateMessage (&msg) :
          DispatchMessage (&msg) ;
     return msg.wParam ;
```

Figure 3-5. The SYSMETS1 program

Figure 3-5. Continued

```
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
               hWnd ;
    HWND
                iMessage ;
    unsigned
    WORD
                 wParam ;
    LONG
                1Param ;
    static short xChar, yChar ;
    char
                 szBuffer [80] ;
                hDC ;
    HDC
    int
                 i ;
    PAINTSTRUCT ps ;
    TEXTMETRIC
                 tm :
    switch (iMessage)
         case WM CREATE:
              hDC = GetDC (hWnd) ;
              GetTextMetrics (hDC, &tm) ;
              xChar = tm.tmAveCharWidth ;
              yChar = tm.tmHeight + tm.tmExternalLeading ;
              ReleaseDC (hWnd, hDC) ;
              break ;
         case WM PAINT:
              BeginPaint (hWnd, &ps) ;
              for (i = 0 ; i < NUMLINES ; i++)
                   sysmetrics[i].szDesc,
                            GetSystemMetrics (sysmetrics[i].nIndex)));
              EndPaint (hWnd, &ps) ;
              break :
         case WM DESTROY:
              PostQuitMessage (0) ;
              break ;
         default:
              return DefWindowProc (hWnd, iMessage, wParam, 1Param) ;
     return OL ;
```

```
NAME
               SYSMETS1
DESCRIPTION
               'System Metrics Display No. 1 (C) Charles Petzold, 1987'
STUB
               'WINSTUB.EXE'
CODE
               MOVEABLE
               MOVEABLE MULTIPLE
DATA
HEAPSIZE
               1024
STACKSIZE
               4096
EXPORTS
               WndProc
```

Not Enough Room

For a first try, SYSMETS1 is not too bad. Figure 3-6 shows how it looks on an EGA in 640 by 350 resolution. You'll notice that you can resize the window and move it around the screen, and SYSMETS1 will always repaint the client area. That's the result of processing the WM_PAINT message. But SYSMETS1 has a really nasty problem: Unless you have a big-screen high-resolution video adapter, you can't see the last few lines of the system metrics list. If you make the window narrower, you can't see the numbers displayed at the ends of the lines.

	Get System Hetrics		0 0
SM_CXSCREEN	Screen width in pixels	640	
SM_CYSCREEN	Screen height in pixels	350	
SM_CXUSCROLL	Vertical scroll arrow width	15	
SM_CYHSCROLL	Horizontal scroll arrow height	13	
SM_CYCAPTION	Caption bar height	16	
SM_CXBORDER	Border width	1	
SM_CYBORDER	Border height	1	
SM_CXDLGFRAME	Dialog window frame width	6	
SM_CYDLGFRAME	Dialog window frame height	6	
SM_CYUTHUMB	Vertical scroll thumb height	18	
SM_CXHTHUMB	Horizontal scroll thumb width	20	
SM_CXICON	Icon width	32	
SM_CYICON	Icon height	32	
SM CXCURSOR	Cursor width	32	
SM_CYCURSOR	Cursor height	32	
SM CYMENU	Menu bar height	12	
SM_CXFULLSCREEN	Full screen client window width	640	
SM_CYFULLSCREEN	Full screen client window height	334	
SM_CYKANJIWINDOW	Kanji window height	0	
SM_HOUSEPRESENT	Mouse present flag	1	
SM_CYUSCROLL	Vertical scroll arrow height	16	
SM_CXHSCROLL	Horizontal scroll arrow width	20	
SM_DEBUG	Debug version flag	1	
SM_SWAPBUTTON	Mouse buttons swapped flag	0	
SM RESERVED1	Reserved	0	
SM_RESERVED2	Reserved	. 0	
SM RESERVEDS	Reserved	40	
AM BEAFBUERS			
A MAINTENANCE INC.			ALL AND THE

Figure 3-6. The SYSMETS1 display

Right now, SYSMETS1 doesn't even know how large its client area is. SYSMETS1 begins the text at the upper left corner and relies on Windows to clip everything that drifts beyond the edges of the client area. Our first job is determining how much of this display output can actually fit within the client area.

The Size of the Client Area

If you experiment with existing Windows applications, you'll find that window sizes can vary widely. At the maximum (assuming the window does not have a menu or scroll bars) the window can be maximized, and the client area will occupy the entire screen except for the caption bar. But the minimum size of the window can be quite small, sometimes almost nonexistent.

One common method for determining the size of a window's client area is to process the WM_SIZE message within your window function. Windows sends a WM_SIZE message to a window function whenever the size of the window changes. The *lParam* variable passed to the window function contains the width of the client area in the low word and the height in the high word. Code to process this message looks like this:

The LOWORD and HIWORD macros are defined in WINDOWS.H. Like xChar and yChar, the xClient and yClient variables are defined as static inside the window function because they are used later when processing other messages.

The WM_SIZE message will eventually be followed by a WM_PAINT message. Why? Because when we define the window class, we specify that the class style is:

```
CS_HREDRAW | CS_VREDRAW
```

This class style tells Windows to force a repaint if either the horizontal or vertical size changes.

You can calculate the number of full lines of text displayable within the client area with the formula:

```
yClient / yChar
```

This may be 0 if the height of the client area is too small to display a full character. Similarly, the number of full characters you can display horizontally within the client area is equal to:

```
xClient / xChar
```

If you determine xChar and yChar during a WM_CREATE message, don't worry about dividing by 0 in these calculations. Your window function receives a WM_CREATE message when WinMain calls CreateWindow. The first WM_SIZE message comes a little later when Win-Main calls ShowWindow, at which point xChar and yChar have already been assigned positive values.

Knowing the size of the window's client area is the first step in providing a way for the user to move the text within the client area if the client area is not large enough to hold everything. If you're familiar with other Windows applications that have similar requirements, you probably know what we need: This is a job for scroll bars.

SCROLL BARS

Scroll bars are one of the best features of a graphics and mouse interface. They are easy to use and provide good visual feedback. You can use scroll bars whenever you need to display anything—text, graphics, a spreadsheet, database records, pictures—that requires more space than the available client area of the window.

Scroll bars are positioned either vertically (for up and down movement) or horizontally (for left and right movement). You can click with the mouse on the arrows at each end of a scroll bar or on the area between the arrows. A "scroll box," or "thumb," travels the length of the scroll bar to indicate the approximate location of the material shown on the display in relation to the entire document. You can also drag the thumb with the mouse to move to a particular location. Figure 3-7 shows the recommended use of a vertical scroll bar for text.

Programmers sometimes have problems with scrolling terminology because their perspective is different from the user's: A user who scrolls down wants to bring a lower part of the document into view. However, the program actually moves the document up in relation to the display window. The Windows documentation and the WINDOWS.H identifiers are based on the user's perspective: Scrolling up means moving toward the top of the document; scrolling down means moving toward the bottom.




Figure 3-7. The vertical scroll bar

The Two Types of Scroll Bars

Windows defines two types of scroll bars: "window scroll bars" and "scroll bar controls."

You can include window scroll bars in a window simply by adding WS_VSCROLL (vertical scroll) or WS_HSCROLL (horizontal scroll) or both to the window style in the *CreateWindow* statement. These scroll bars are always placed against the right side or bottom of the window and extend for the full length or width of the client area. The client area does not include the space occupied by the scroll bar. The width of a vertical window scroll bar and the height of a horizontal window scroll bar are constant for a particular display driver. If you need these values, you can obtain them (as you may have observed) from the *GetSystem-Metrics* call.

A scroll bar control, however, is a child window. It can be any size: You can make long, thin scroll bar controls or short, pudgy scroll bar controls. You can put them anywhere in the client area of a window. Scroll bar controls require that you use the *CreateWindow* call to create a child window with a scroll bar style. (The COLORSCR program in Chapter 7 shows you how to do this.) Scroll bar controls are also used in dialog boxes, where they are defined in a dialog box template. (Chapter 11 discusses dialog boxes.) Let's leave scroll bar controls for later chapters and use window scroll bars in the SYSMETS program.

Windows takes care of all mouse logic for the scroll bars. However, window scroll bars do not have an automatic keyboard interface. If you want the cursor keys to duplicate some of the window scroll bars' functions, you must explicitly provide logic for that (as we'll do in the next chapter).

Scroll Bar Range and Position

Scroll bars have a "range" and a current "position." The range is defined by minimum and maximum integer values. When the thumb is at the top (or left) of the scroll bar, the position of the thumb is the minimum value of the range. At the bottom (or right) of the scroll bar, the thumb position is the maximum value of the range.

The position of the thumb is always a discrete integral value. For instance, a scroll bar with a range from 0 to 4 has five thumb positions, as shown in Figure 3-8 (on the following page). By default, the range of a scroll bar is 0 (top or left) to 100 (bottom or right), but it's easy to change the range to something that is more convenient for the program:

SetScrollRange (hWnd, nBar, nMin, nMax, bRedraw)

The *nBar* parameter is either SB_VERT or SB_HORZ, *nMin* and *nMax* are the minimum and maximum positions of the range, and *bRedraw* is set to TRUE if you want Windows to redraw the scroll bar based on the new range.




Figure 3-8. Scroll bars with five thumb positions

You can use SetScrollPos to set a new thumb position within the range:

SetScrollPos (hWnd, nBar, nPos, nRedraw)

The *nPos* parameter is the new position and must be within the range of *nMin* through *nMax*. Windows provides similar functions (*GetScrollRange* and *GetScrollPos*) to obtain the current range and position of a scroll bar.

When you use scroll bars within your program, you share responsibility with Windows for maintaining the scroll bars and updating the position of the scroll bar thumb. These are Windows' responsibilities for scroll bars:

- Handle all scroll bar mouse logic.
- · Provide a "reverse video" flash when the user clicks on the scroll bar.
- · Display a "ghost" box when the user drags the thumb within the scroll bar.
- Send scroll bar messages to the window function for the window containing the scroll bar.

These are your program's responsibilities:

- Initialize the range of the scroll bar.
- Process the scroll bar messages.
- · Update the position of the scroll bar thumb.

Scroll Bar Messages

Windows sends the window functionWM_VSCROLL and WM_HSCROLL messages when the scroll bar is clicked with the mouse or the thumb is dragged. Each mouse action on the scroll bar generates at least two messages, one when the mouse button is pressed and another when it is released.

The value of wParam that accompanies the WM_VSCROLL and WM_HSCROLL messages describes what the mouse is doing to the scroll bar. These values of wParam have WINDOWS.H identifiers that begin with SB, which stands for "scroll bar." Although some of these identifiers use the words "UP" and "DOWN," they apply to horizontal as well as vertical scroll bars, as you see in Figure 3-9.




Figure 3-9. WINDOWS.H identifiers for the wParam values of scroll bar messages

Your window function can receive multiple SB_LINEUP, SB_PAGEUP, SB_LINEDOWN, or SB_PAGEDOWN messages if the mouse button is held down while positioned on the scroll bar. The SB_ENDSCROLL message signals that the mouse button has been released. You can generally ignore SB_ENDSCROLL messages.

When wParam is SB_THUMBTRACK or SB_THUMBPOSITION, the low word of IParam is the current position of the dragged scroll bar. This position is within the minimum and maximum values of the scroll bar range. For other values of wParam, the low word of IParam should be ignored. (The high word of IParam is 0 for window scroll bars and a handle to the child window for scroll bar controls. You can ignore the high word of IParam for window scroll bars.)

The Windows documentation claims that the wParam value can also be SB_TOP and SB_BOTTOM, indicating that the scroll bar has been moved to its minimum or maximum position. However, you will never receive these values for a window scroll bar. You will receive these values only for child window scroll bar controls. (We'll explore this more in Chapter 7.)

Handling the SB_THUMBTRACK and SB_THUMBPOSITION messages is problematic. If you set a large scroll bar range and the user quickly drags the thumb inside the scroll bar, Windows sends your window function a barrage of SB_THUMBTRACK messages. Your program may have problems keeping up with these messages. For this reason, most Windows applications ignore these messages and take action only on receipt of SB_THUMBPOSITION, which means that the thumb is again at rest.

One exception is the dialog box containing help information in PIFEDIT. This dialog box processes SB_THUMBTRACK messages and scrolls the text as you drag the thumb. If you can update your display as quickly as PIFEDIT, you may want to include SB_THUMBTRACK processing in your program. But be aware that users who discover that your program scrolls as they move the scroll bar thumb will undoubtedly try to move it as quickly as possible to see if your program can keep up. They will get an inordinate amount of satisfaction if it cannot.

Scrolling SYSMETS

Enough explanation. It's time to put this stuff into practice. But let's start simply. We'll begin with vertical scrolling since that is what we desperately need. The horizontal scrolling can wait. SYSMETS2 is shown in Figure 3-10.

```
sysmets2.obj : sysmets2.c sysmets.h
cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp sysmets2.c

sysmets2.exe : sysmets2.obj sysmets2.def
link4 sysmets2, /align:l6, /map, slibw, sysmets2
```

Figure 3-10. The SYSMETS2 program

Figure 3-10. Continued

```
static
                char szAppName [] = "SysMets2" ;
      HWND
                hWnd ;
      MSG
                msq ;
      WNDCLASS wndclass :
      if (!hPrevInstance)
           wndclass.cbWndExtra = 0;
wndclass.cbWndExtra = 0;
hInstance;
           wndclass.hinstance = hinstance;
wndclass.hicon = Loadicon (NULL, IDI_APPLICATION);
wndclass.hCursor = Loadicon (NULL, IDI_ARROW);
           wndclass.hbrBackground = GetStockObject (WHITE BRUSH) ;
           wndclass.lpszMenuName = NULL;
wndclass.lpszClassName = szAppName;
           if (!RegisterClass (&wndclass))
                 return FALSE ;
     hWnd = CreateWindow (szAppName, "Get System Metrics",
                            WS_OVERLAPPEDWINDOW | WS_VSCROLL,
CW_USEDEFAULT, 0,
CW_USEDEFAULT, 0,
                            NULL, NULL, hInstance, NULL) ;
     ShowWindow (hWnd, nCmdShow) ;
     UpdateWindow (hWnd) ;
     while (GetMessage (&msg, NULL, 0, 0))
           TranslateMessage (&msg) ;
           DispatchMessage (&msg) ;
     return msg.wParam ;
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
     HWND
                  hWnd ;
     unsigned
                    iMessage ;
     WORD
                    wParam ;
                    1Param ;
     static short xChar, yChar, xClient, yClient, nVscrollPos; char szBuffer [80];
     HDC
                    hDC ;
     int
     TEXTMETRIC tm ;
     PAINTSTRUCT ps ;
     switch (iMessage)
           case WM CREATE:
                hDC = GetDC (hWnd) ;
                GetTextMetrics (hDC, &tm) ;
```

Figure 3-10. Continued

```
xChar = tm.tmAveCharWidth :
    yChar = tm.tmHeight + tm.tmExternalLeading ;
ReleaseDC (hWnd, hDC) ;
    SetScrollRange (hWnd, SB_VERT, 0, NUMLINES, FALSE) ;
SetScrollPos (hWnd, SB_VERT, nVscrollPos, TRUE) ;
    break ;
case WM SIZE:
     yclient = HIWORD (1Param) ;
     xClient = LOWORD (1Param) ;
     break :
case WM VSCROLL:
     switch (wParam)
          case SB LINEUP:
               nVacrollPos -= 1 ;
                break :
          case SB LINEDOWN:
                nVscrollPos += 1 ;
                break ;
          case SB PAGEUP:
                nVscrollPos -= yClient / yChar ;
                break :
          case SB PAGEDOWN:
                nVscrollPos += yClient / yChar ;
                break :
          case SB THUMBPOSITION:
                nVscrollPos = LOWORD (1Param) ;
                break :
           default:
                break :
     nVscrollPos = max (0, min (nVscrollPos, NUMLINES)) ;
      if (nVscrollPos != GetScrollPos (hWnd, SB_VERT))
           SetScrollPos (hWnd, SB VERT, nVscrollPos, TRUE) ;
           InvalidateRect (hWnd, NULL, TRUE) ;
      break ;
case WM PAINT:
      BeginPaint (hWnd, &ps) ;
      for (i = 0 ; i < NUMLINES ; i++)
           TextOut (ps.hdc, xChar, yChar * (1 - nVscrollPos + i),
                      szBuffer,
                sysmetrics[i].szDesc,
                      GetSystemMetrics (sysmetrics[i].nIndex))) ;
```

Figure 3-10. Continued

```
EndPaint (hWnd, &ps);
break;

case WM_DESTROY:
    PostQuitMessage (0);
    break;

default:
    return DefWindowProc (hWnd, iMessage, wParam, lParam);

return OL;
}

return OL;
```

```
NAME
              SYSMETS2
DESCRIPTION
              'System Metrics Display No. 2 (C) Charles Petzold, 1987'
              'WINSTUB. EXE'
STUB
CODE
              MOVEABLE
DATA
              MOVEABLE MULTIPLE
HEAPSIZE
              1024
STACKSIZE
              4096
EXPORTS
              WndProc
```

The new *CreateWindow* call adds a vertical scroll bar to the window; the scroll bar has this window style:

```
WS_OVERLAPPEDWINDOW | WS_VSCROLL
```

The WndProc window function has two additional lines to set the range and position of the vertical scroll bar during processing of the WM_CREATE message:

```
SetScrollRange (hWnd, SB_VERT, 0, NUMLINES, FALSE);
SetScrollPos (hWnd, SB_VERT, nVscrollPos, TRUE);
```

The sysmetrics structure has NUMLINES lines of text, so the scroll bar range is set from 0 to NUMLINES. Each position of the scroll bar corresponds to a line of text displayed at the top of the client area. If the scroll bar thumb is at position 0, a blank line is left at the top of the screen for a margin. As you increase the position of the scroll bar by scrolling down, the text should move up. When the scroll bar position is at the bottom, the last line of the structure is at the top.

To help with processing of the WM_VSCROLL messages, a static variable called nVscrollPos is defined within the WndProc window function. This variable is the current position of the scroll bar thumb. For SB_LINEUP and SB_LINEDOWN, all we need to do is adjust the scroll position by 1. For SB_PAGEUP and SB_PAGEDOWN, we want to move the text by the contents of one screen, or yClient divided by yChar. For SB_THUMBPOSITION, the new thumb position is the low word of lParam. SB_ENDSCROLL and SB_THUMBTRACK messages are ignored.

The nVscrollPos is then adjusted using the min and max macros (defined in WIN-DOWS.H) to ensure that it is between the minimum and maximum range values. If the scroll position has changed, then it is updated using SetScrollPos, and the entire window is invalidated by an InvalidateRect call.

The InvalidateRect call generates a WM_PAINT message. When the original SYSMETS1 processed WM_PAINT messages, the y coordinate of each line was calculated as:

```
yChar * (1 + i)
```

In SYSMETS2, the formula is:

```
vChar * (1 - nVscrollPos + i)
```

The loop still displays NUMLINES lines of text, but for values of nVscrollPos of 2 and above, the loop begins displaying lines above the client area. Windows merely ignores these lines.

I told you we'd start simply. This is rather wasteful and inefficient code. We'll fix it shortly, but first consider how we updated the client area after a WM_VSCROLL message.

Structuring Your Program for Painting

The window function in SYSMETS2 does not repaint the client area after processing a scroll bar message. Instead, it calls *InvalidateRect* to invalidate the client area. This causes Windows to place a WM_PAINT message in the message queue.

It is best to structure your Windows programs so that you do all client-area painting in response to a WM_PAINT message. Because your program should be able to repaint the entire client area of the window at any time on receipt of a WM_PAINT message, you will probably duplicate code if you also paint in other parts of the program.

At first, you may rebel at this dictum because it is so different from normal PC programming. I won't deny that, on occasion, painting in response to messages other than WM_PAINT is much more convenient. (The KEYLOOK program in the next chapter is an example of such a program.) But in many cases it's simply unnecessary, and after you master the discipline of accumulating all the information you need to paint in response to a WM_PAINT message, you'll be pleased with the results. However, your program will often determine that it must repaint a particular area of the display when processing a message other than WM_PAINT. This is where *InvalidateRect* comes in handy. You can use it to invalidate specific rectangles of the client area or the entire client area.

Simply marking areas of the window as invalid to generate WM_PAINT messages may not be entirely satisfactory in some applications. After you make an *InvalidateRect* call, Windows places a WM_PAINT message in the message queue, and the window function eventually processes it. However, Windows treats WM_PAINT messages as low priority. If your message queue contains only a WM_PAINT message and another application has other messages waiting, Windows switches to the other application when you make a *GetMessage* call.

If you prefer to update the invalid area immediately, you can call *UpdateWindow* after you call *InvalidateRect*:

```
UpdateWindow (hWnd) ;
```

UpdateWindow causes the window function to be called immediately with a WM_PAINT message if any part of the client area is invalid. (It will not call the window function if the entire client area is valid.) This WM_PAINT message bypasses the message queue. The window function is called directly from Windows. When the window function is finished repainting, it exits and Windows returns control to the program at the statement following the UpdateWindow call.

You'll note that *UpdateWindow* is the same function used in *WinMain* to generate the first WM_PAINT message. When a window is first created, the entire client area is invalid. *UpdateWindow* directs the window function to paint it.

Building a Better Scroll

Because SYSMETS2 is too inefficient a model to be imitated in other programs, let's clean it up. SYSMETS3—our final version of the SYSMETS program in this chapter—is shown in Figure 3-11. This version adds a horizontal scroll bar for left and right scrolling and repaints the client window more efficiently.

```
sysmets3.obj : sysmets3.c sysmets.h
    c1 -c -D LINT_ARGS -Gsw -Os -W2 -Zp sysmets3.c

sysmets3.exe : sysmets3.obj sysmets3.def
    link4 sysmets3, /align:16, /map, slibw, sysmets3
```

```
/* SYSMETS3.C -- System Metrics Display Program No. 3 */
#include <windows.h>
#include <stdio.h>
#include "sysmets.h"
long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG) ;
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
    HANDLE hinstance, hPrevinstance;
    LPSTR
             lps2CmdLine ;
             nCmdShow ;
    WNDCLASS wndclass ;
     HWND
            hWnd ;
             msg ;
     MSG
     static char szAppName [] = "SysMets3" ;
```

Figure 3-11. The SYSMETS3 program

Figure 3-11. Continued

```
if (!hPrevInstance)
                               = CS HREDRAW | CS VREDRAW ;
           wndclass.style
           wndclass.lpfnWndProc = WndProc ;
           wndclass.cbWndExtra = 0;
wndclass.cbWndExtra = 0;
           wndclass.hInstance = hInstance;
wndclass.hIcon = LoadIcon (NULL, IDI_APPLICATIO
wndclass.hCursor = LoadCursor (NULL, IDC_ARROW);
                                      = Loadicon (NULL, IDI_APPLICATION) ;
           wndclass.hbrBackground = (HBRUSH) GetStockObject (WHITE_BRUSH) : wndclass.lpszMenuName = NULL ;
           wndclass.lpszClassName = szAppName ;
           if (!RegisterClass (&wndclass))
                 return FALSE ;
     hwnd = CreateWindow (szAppName, "Get System Metrics", WS_OVERLAPPEDWINDOW | WS_HSCROLL | WS_VSCROLL, CW_USEDEFAULT, 0,
                             CW USEDEFAULT, 0,
                             NULL, NULL, hInstance, NULL) ;
     ShowWindow (hWnd, nCmdShow) ;
     UpdateWindow (hWnd) ;
     while (GetMessage (&msg, NULL, 0, 0))
           TranslateMessage (&msg) ;
           DispatchMessage (&msg) ;
     return msg.wParam ;
#define MAXWIDTH 60 /* maximum width of formatted output */
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
                hWnd ;
iMessage ;
     HWND
      unsigned
      WORD
                    wParam ;
                     lParam ;
      LONG
     static short xChar, yChar;
     static short xClient, yClient;
     static short nVscrollMax, nHscrollMax;
static short nVscrollPos, nHscrollPos;
char szBuffer [80];
     char
                   hDC ;
      HDC
     PAINTSTRUCT ps ;
      short nVscrollInc, nHscrollInc;
                     nPaintBeg, nPaintEnd, i ;
      short
      TEXTMETRIC tm ;
```

Figure 3-11. Continued

```
switch (iMessage)
     case WM CREATE:
           hDC = GetDC (hWnd) ;
           GetTextMetrics (hDC, &tm) ;
           xChar = tm.tmAveCharWidth ;
           yChar = tm.tmHeight + tm.tmExternalLeading ;
           ReleaseDC (hWnd, hDC) ;
           break ;
     case WM SIZE:
           yClient = HIWORD (1Param) ;
           xClient = LOWORD (1Param) ;
           nVscrollMax = max (0, NUMLINES + 2 - yClient / yChar) ;
           nVscrollPos = min (nVscrollPos, nVscrollMax) ;
           nHscrollMax = max (0, MAXWIDTH + 2 - xClient / xChar);
nHscrollPos = min (nHscrollPos, nHscrollMax);
           SetScrollRange (hWnd, SB_VERT, 0, nVscrollMax, FALSE) ;
           SetScrollPos (hwnd, SB_VERT, nvscrollPos, TRUE);
SetScrollRange (hwnd, SB_HORZ, 0, nHscrollMax, FALSE);
SetScrollPos (hwnd, SB_HORZ, nHscrollPos, TRUE);
           break ;
     case WM VSCROLL:
           switch (wParam)
                 case SB TOP:
                       nVscrollInc = -nVscrollPos ;
                       break :
                 case SB BOTTOM:
                       nVscrollInc = nVscrollMax - nVscrollPos ;
                      break ;
                 case SB LINEUP:
                      nVscrollInc = -1 ;
                      break ;
                 case SB LINEDOWN:
                      nVscrollInc = 1;
                      break ;
                 case SB PAGEUP:
                      nVscrollInc = min (-1, -yClient / yChar) ;
                      break ;
                case SB PAGEDOWN:
                      nVscrollInc = max (1, yClient / yChar) ;
                      break ;
                 case SB THUMBTRACK:
                      nVscrollInc = LOWORD (1Param) - nVscrollPos ;
                      break ;
                default:
                      nVscrollInc = 0 ;
```

Figure 3-11. Continued

```
if (nVscrollInc = max (-nVscrollPos,
                min (nVscrollInc, nVscrollMax - nVscrollPos)))
          nVscrollPos += nVscrollInc ;
          ScrollWindow (hWnd, 0, -yChar * nVscrollInc, NULL, NULL) ;
           SetScrollPos (hWnd, SB VERT, nVscrollPos, TRUE) ;
          UpdateWindow (hWnd) ;
     break :
case WM HSCROLL:
     switch (wParam)
           case SB LINEUP:
                nHscrollInc = -1 ;
                break ;
           case SB LINEDOWN:
                nHscrollInc = 1 ;
                break :
           case SB PAGEUP:
                nHscrollInc = -8 ;
                break :
           case SB PAGEDOWN:
                nHscrollInc = 8 ;
                break ;
           case SB THUMBPOSITION:
                nHscrollInc = LOWORD (1Param) - nHscrollPos ;
                break :
           default:
                nHscrollInc = 0 ;
      if (nHscrollInc = max (-nHscrollPos,
                min (nHscrollInc, nHscrollMax - nHscrollPos)))
           nHscrollPos += nHscrollInc ;
           ScrollWindow (hWnd, -xChar * nHscrollInc, 0, NULL, NULL) ;
SetScrollPos (hWnd, SB_HORZ, nHscrollPos, TRUE) ;
      break ;
case WM PAINT:
      BeginPaint (hWnd, &ps) ;
      nPaintBeg = max (0, nVscrollPos + ps.rcPaint.top / yChar - 1) ;
      nPaintEnd = min (NUMLINES,
                      nVscrollPos + ps.rcPaint.bottom / yChar) ;
      for (i = nPaintBeg ; i < nPaintEnd ; i++)
           TextOut (ps.hdc,

xChar * (1 - nHscrollPos),

yChar * (1 - nVscrollPos + i),
                       szBuffer,
```

Figure 3-11. Continued

```
NAME
              SYSMETS3
DESCRIPTION
              'System Metrics Display No. 3 (C) Charles Petzold, 1987'
              'WINSTUB.EXE'
STUB
CODE
              MOVEABLE
DATA
              MOVEABLE MULTIPLE
            1024
HEAPSIZE
STACKSIZE
              4096
EXPORTS
              WndProc
```

These are the improvements in SYSMETS3 and how they are implemented in the program:

You can no longer scroll the display so that the last line appears at the top of the client area. You can only scroll far enough to see the last line at the bottom of the client area. This requires that the program calculate a new scroll bar range (and possibly a new thumb position) when it processes a WM_SIZE message. The WM_SIZE logic calculates the scroll bar range based on the number of lines of text, the width of the text, and the size of the client area. This approach results in a smaller range—only that necessary to bring into view the text that falls outside the client area.

This offers an interesting dividend. Suppose that the client area of the window is large enough to display the entire text with top and bottom margins. In this case, both the minimum position and maximum position of the scroll bar range will equal zero. What will Windows do with this information? It will remove the scroll bar from the window! It's no longer needed. Similarly, if the client area is wide enough to show the full 60-column width of the text, no horizontal scroll bar is displayed in the window.

 The WM_VSCROLL and WM_HSCROLL messages are processed by first calculating an increment of the scroll bar position for each value of wParam. This value is then used to scroll the existing contents of the window using the Windows ScrollWindow call. This function has the following format:

ScrollWindow (hWnd, xInc, yInc, 1pRect, 1pClipRect);
The xInc and yInc values specify an amount to scroll in pixels. In SYSMETS3, the IpRect and IpClipRect values are set to NULL to specify that the entire client area should be scrolled. Windows invalidates the rectangle in the client area "uncovered" by the scrolling operation. This generates a WM_PAINT message. InvalidateRect is no longer needed. (Note that ScrollWindow is not a GDI function because it does not require a handle to a device context. It is one of the few non-GDI Windows functions that change the appearance of the client area of a window.)

- The WM_PAINT processing now determines which lines are within the invalid
 rectangle and rewrites only those lines. It does this by analyzing the top and
 bottom coordinates of the invalid rectangle stored in the PAINTSTRUCT structure.
 The program paints only those text lines within the invalid rectangle. The code is
 more complex, but it is much faster.
- Because WM_PAINT was speeded up, I decided to let SYSMETS3 process SB_THUMBTRACK operations for WM_VSCROLL messages. Previously, the program ignored SB_THUMBTACK messages (which occur as the user drags the scroll bar thumb) and acted only on SB_THUMBPOSITION messages, which occur when the user stops dragging the thumb. The WM_VSCROLL code also calls *UpdateWindow* to update the client area immediately. When you move the thumb on the vertical scroll bar, SYSMETS will continually scroll and update the client area. I'll let you decide whether SYSMETS3 (and Windows) is fast enough to justify this change.

But I Don't Like to Use the Mouse

If you don't have a mouse on your PC, you can't scroll SYSMETS3 at all. Window scroll bars do not have an automatic keyboard interface. Because Windows can be installed without a mouse, it is highly recommended that you write programs that do not require the mouse.

In the next chapter you will learn how to use the keyboard and how to add a keyboard interface to SYSMETS. You'll notice that SYSMETS3 seemingly processes WM_VSCROLL messages where wParam equals SB_TOP and SB_BOTTOM. I mentioned earlier that a window function never receives these messages for window scroll bars, so right now this is superfluous code. When we come back to this program in the next chapter, you'll see the reason for including this code.

SECTION II

GETTING INPUT



Chapter 4

The Keyboard

Like most interactive programs that run on personal computers, Windows applications rely heavily on the keyboard for user input. Although Windows also supports a mouse as an input device, you can't depend on a mouse being present in an installed version of Windows. For this reason, program developers must ensure that all the functions of their programs can be controlled solely from the keyboard.

Often a program uses the keyboard by displaying typed characters in the client area of a window or by creating a document based on keystrokes that is eventually saved in a disk file. Sometimes a program requires that the user enter an MS-DOS filename. These apparently simple and straightforward chores raise issues related to the support of international characters. For this reason, topics such as the character sets supported by Windows and multibyte character codes are also covered in this chapter.

KEYBOARD BASICS

As the user presses and releases keys, the keyboard driver passes the keystrokes to Windows. Windows saves the keystrokes in the system message queue and then transfers them to the message queue of the program with "input focus." These messages are processed in the program's window function. In most cases, the keyboard information encoded in these messages is probably more than your program needs. Part of the job of handling the keyboard is knowing which messages are important and which are not.

The Keyboard Driver

Windows is shipped with several keyboard drivers for the support of international keyboard configurations. Keyboards for European languages must include additional characters (such as letters with diacritics) and symbols (such as the British pound sign). When you install

Windows, the SETUP program merges the appropriate keyboard driver into WIN200.BIN. In the "slow boot" version of Windows, a keyboard driver file called KEYBOARD.DRV must be in the Windows subdirectory when Windows loads.

KEYBOARD.DRV is a relatively simple driver. It exports six functions: *Inquire*, *Enable*, *Disable*, *ToAscii*, *AnsiToOem*, and *OemToAnsi*. Only the last two are called directly by Windows applications; the others are for internal use by Windows. Windows installs the keyboard driver by calling the *Enable* function and uninstalls it by calling *Disable*. On the IBM PC and compatibles, the *Enable* function saves the original interrupt vector addresses for Interrupts 09H (the hardware keyboard interrupt) and 1BH (the software-generated Ctrl-Break interrupt) and sets these interrupt vectors to routines within the driver.

Pressing or releasing a key generates an Interrupt 09H. This is sometimes called an "asynchronous" interrupt because it can occur at any time. The interrupt suspends the program currently running and passes control to the Interrupt 09H keyboard handler. When the keyboard handler is finished, it passes control back to the interrupted program. The Interrupt 09H keyboard handler within KEYBOARD.DRV decodes the key and calls a routine within the Windows USER module. (The keyboard driver ignores some keys, such as the PrtSc key, and passes them to the old Interrupt 09H handler.) The USER module translates keystrokes into queued messages. The Windows program then obtains the keyboard messages when the program calls GetMessage.

Because a Windows program effectively polls for keyboard input by calling Get-Message, Windows programs are not very different from PC programs that obtain keystrokes by polling through the software Interrupts 16H and 21H. However, the quantity of information that Windows encodes in the keyboard messages is much greater than that available from Interrupts 16H and 21H.

Some application programs written for the IBM PC intercept Interrupt 09H and do their own hardware keyboard processing. This allows the program to use all possible combinations of keystrokes, not only those defined by the PC BIOS. Windows programs are not very different from these programs, because the window function is a message handler that receives messages about all keyboard events. The only real difference between message handling and interrupt handling is that the Windows messages are not asynchronous. A Windows program is never interrupted to be notified of a keystroke; the program receives a new keyboard message only from the message queue. In short, Windows provides programs with all the benefits of intercepting the hardware Interrupt 09H but with none of the hassles.

When a user types on the keyboard faster than a program can process the keys, Windows stores the extra keystrokes in a system message queue rather than in an individual program's message queue. One of these extra keystrokes (Alt-Tab, for instance) may have the effect of switching to another program. The keys following Alt-Tab should then go to the other program. Windows correctly synchronizes such keyboard messages.

Windows sends eight different messages to programs to indicate various keyboard events. That may seem like a lot, but your program can safely ignore many of them.

Ignoring the Keyboard

Although the keyboard is the primary source of user input to Windows programs, your program does not need to act on every keyboard message it receives. Windows handles many keyboard functions itself. For instance, you can ignore keystrokes that pertain to system functions. These are keystrokes generally involving the Alt key.

A program need not monitor these keystrokes itself because Windows notifies a program of the effect of the keystrokes. (A program can monitor the keystrokes if it wants to, however.) For instance, if the Windows user selects a menu item with the keyboard, Windows sends the program a message that the menu item has been selected, regardless of whether it was selected by the mouse or by the keyboard. (Menus are covered in Chapter 10.)

Some Windows programs use "keyboard accelerators" to invoke common menu items. The accelerators generally involve the function keys, special noncharacter keys such as Insert or Delete, or a letter in combination with the Ctrl key. These keyboard accelerators are defined in a program's resource script. (Chapter 10 shows how Windows translates the accelerators into menu command messages. You don't have to do the translation yourself.)

Dialog boxes (covered in Chapter 11) also have a keyboard interface, but programs usually do not need to monitor the keyboard when a dialog box is active. The keyboard interface is handled by Windows, and Windows sends your program messages about the effects of the keystrokes. Dialog boxes can contain "edit" controls for text input. These are generally small boxes in which the user types a character string. Windows handles all the editing control logic and gives your program the final contents of the edit control when the user is done.

Even within your main window you can define child windows that function as edit controls. An extreme example of this is the Windows NOTEPAD program, which is little more than a large multiline edit control. NOTEPAD does little keyboard processing on its own and relies on Windows to handle all the dirty work. (Chapter 7 discusses how this works.)

Focus, Focus, Who's Got the Focus?

The keyboard must be shared by all applications running under Windows. Some applications may have more than one window, and the keyboard must be shared by these windows within the same application. When a key is pressed on the keyboard, only one window function can receive a message that the key has been pressed. The window that receives this keyboard message is the window with the "input focus."

The concept of input focus is closely related to the concept of "active window." The window with the input focus is either the active window or a child window of the active window. The active window is usually easy to identify. If the active window is an overlapped or popup window with a caption bar, Windows highlights the caption bar. If the active window has a dialog frame instead of a caption bar (a form most commonly seen in dialog boxes), Windows highlights the frame. If the active window is an icon, Windows displays the window's caption bar text below the icon.

The most common child windows are controls such as push buttons, radio buttons, check boxes, scroll bars, edit boxes, and list boxes that usually appear in a dialog box. Child windows are never themselves active windows. If a child window has the input focus, then the active window is its parent. Child window controls indicate that they have the input focus generally by using a flashing cursor or caret.

If the active window is an icon, then no window has the input focus. Windows continues to send keyboard messages to the icon, but these messages are in a different form from keyboard messages sent to active windows that are not icons. A window function can determine when it has the input focus by trapping WM_SETFOCUS and WM_KILLFOCUS messages. WM_SETFOCUS indicates that the window is receiving the input focus, and WM_KILLFOCUS signals that the window is losing the input focus.

Keystrokes and Characters

The messages that an application receives from Windows about keyboard events distinguish between "keystrokes" and "characters." You can think of the keyboard as a collection of keys. The keyboard has only one A key. Pressing that key is a keystroke. Releasing that key is a keystroke. But the keyboard is also an input device that generates displayable characters. The A key can generate several characters depending on the status of the Ctrl, Shift, and Caps Lock keys. Normally, the character is a lowercase a. If the Shift key is down or Caps Lock is toggled, the character is an uppercase A. If Ctrl is down, the character is a Ctrl-A. On a foreign language keyboard, the A keystroke may be preceded by a "dead-character key." This combination generates a lowercase or uppercase A with an accent mark.

For keystroke combinations that result in displayable characters, Windows sends a program both keystroke messages and character messages. Some keys do not generate characters. These include the shift keys, the function keys, the cursor movement keys, and special keys such as Insert and Delete. For these keys, Windows generates only keystroke messages.

KEYSTROKE MESSAGES

When you press a key, Windows places either a WM_KEYDOWN or WM_SYSKEYDOWN message in the message queue of the window with the input focus. When you release a key, Windows places either a WM_KEYUP or WM_SYSKEYUP message in the message queue.

	Key Pressed	Key Released	
Nonsystem keystroke	WM_KEYDOWN	WM_KEYUP	
System keystroke	WM_SYSKEYDOWN	WM_SYSKEYUP	

Usually the "down" and "up" messages occur in pairs. However, if you hold down a key so that the typematic (autorepeat) action takes over, Windows sends the window function a

series of WM_KEYDOWN (or WM_SYSKEYDOWN) messages and a single WM_KEYUP (or WM_SYSKEYUP) message when the key is finally released. Like all messages, keystroke messages are time-stamped. You can obtain the relative time a key was pressed or released by calling <code>GetMessageTime</code>.

System and Nonsystem Keystrokes

The "SYS" in WM_SYSKEYDOWN and WM_SYSKEYUP stands for "system" and refers to keystrokes that are more important to Windows than to the Windows application. The WM_SYSKEYDOWN and WM_SYSKEYUP messages are usually generated for keys typed in combination with the Windows "menu" key. On the IBM PC and compatibles, the menu key is the Alt key. Below, I refer to the menu key as the Alt key, but a non-IBM keyboard could use another key for this purpose.

Windows uses the system key messages for system functions such as switching the active window (Alt-Tab or Alt-Esc) and for system menu acceleraters (Alt in combination with a function key). Programs usually ignore the WM_SYSKEYUP and WM_SYSKEYDOWN messages and pass them to <code>DefWindowProc</code>. Because Windows takes care of all the Alt-key logic, you really have no need to trap these messages. Your window function will eventually receive other messages concerning the result of these keystrokes (such as a menu selection). If you want to include code in your window function to trap the system keystroke messages (as we will do in the KEYLOOK program later in this chapter), pass the messages to <code>DefWindowProc</code> after you process them so that Windows can still use them for their normal purposes.

But think about this for a moment. Almost everything that affects your program's window passes through your window function first. Windows does something with the message only if you pass the message to *DefWindowProc*. For instance, if you add the lines:

```
case WM_SYSKEYDOWN:
case WM_SYSKEYUP:
    break;
```

to a window function, then you effectively disable all Alt key operations (Alt-Tab, Alt-Esc, and so on) when your program has the input focus. Although I doubt you would want to do this, I trust you're beginning to sense the power in your window function.

The WM_KEYDOWN and WM_KEYUP messages are usually generated for keys that are pressed and released without the Alt key. Your program may use or discard these keystroke messages. Windows doesn't care about them.

The IParam Variable

For all four keystroke messages, the 32-bit *IParam* variable passed to the window function is divided into five fields: Repeat Count, OEM Scan Code, Context Code, Previous Key State, and Transition State. (See Figure 4-1 on the following page.)




Figure 4-1. The five keystroke-message fields of the lParam variable

Repeat Count

The Repeat Count is the number of keystrokes represented by the message. In most cases the Repeat Count is set to 1. However, if a key is held down and your window function is not fast enough to process key-down messages at the typematic rate (approximately 10 characters per second default on IBM machines), Windows combines several WM_KEYDOWN or WM_SYSKEYDOWN messages into a single message and increases the repeat count accordingly. The Repeat Count is always 1 for a WM_KEYUP or WM_SYSKEYUP message.

Because a Repeat Count greater than 1 indicates that typematic keystrokes are occurring faster than your program can process them, you may want to ignore the Repeat Count when processing the keyboard messages. Almost everyone has had the experience of "overscrolling" a word-processing document or spreadsheet because extra keystrokes have stacked up in the keyboard buffer. Ignoring the Repeat Count in your program will significantly reduce the possibilities for overscrolling. However, in other cases you will want to use the Repeat Count. You should probably try your programs both ways and see which approach feels the most natural.

OEM Scan Code

The OEM Scan Code is the keyboard scan code generated by the hardware of the computer. In the IBM PC, this scan code is the same as the value obtained from register 60H following an Interrupt 09H or—for many keys—the value passed back to a program in register AH during a BIOS Interrupt 16H call. Windows applications generally ignore the OEM Scan Code. Using this field may make your programs machine dependent.

Context Code

The Context Code is 1 if the Alt key is pressed. This bit will always be 1 for WM_SYSKEYUP and WM_SYSKEYDOWN messages and 0 for WM_KEYUP and WM_KEYDOWN messages with two exceptions:

If the active window is an icon, it does not have the input focus. All keystrokes
generate WM_SYSKEYUP and WM_SYSKEYDOWN messages. If the Alt key is not
pressed, the Context Code field is set to 0. (Windows uses SYS keyboard messages
so that the active window that is an icon doesn't process these keystrokes.)

 On some foreign-language keyboards, certain characters are generated by combining Alt and Ctrl with another key. In these cases the *lParam* variable that accompanies WM_KEYUP and WM_KEYDOWN messages has a 1 in the Context Code field, but the messages are not system keystroke messages.

Previous Key State

The Previous Key State is 0 if the key was previously up and 1 if the key was previously down. It is always set to 1 for a WM_KEYUP or WM_SYSKEYUP message, but it can be 0 or 1 for a WM_KEYDOWN or WM_SYSKEYDOWN message. A 1 indicates second and subsequent messages for keys that are the result of typematic action.

Transition State

The Transition State is 0 if the key is being pressed and 1 if the key is being released. The field is set to 0 for a WM_KEYDOWN or WM_SYSKEYDOWN message and to 1 for a WM_KEYUP or WM_SYSKEYUP.

Virtual Key Codes

Although some information in *IParam* might be useful for processing WM_KEYUP, WM_KEYDOWN, WM_SYSKEYUP, and WM_SYSKEYDOWN messages, the *wParam* parameter is much more important. This parameter contains the "virtual key code" that identifies the key that was pressed or released. The developers of Windows have attempted to define virtual keys that may be applied to the IBM PC, PC compatibles, and other machines. For this reason, some virtual key codes cannot be generated on the IBM PC.

The virtual key codes you use most often have names defined in WINDOWS.H. The following table shows these names along with the numeric key codes and the IBM PC key that corresponds to the virtual key. Although all keys cause keystroke messages, the table does not include any symbol keys (such as the key with the / and? symbols). These keys have virtual key codes of 128 and above, and they are often defined differently for international keyboards. You can determine the values of these virtual key codes using the KEYLOOK program that is shown later in this chapter, but normally you should not process keystroke messages for these keys.

An asterisk in the column labeled "Required" indicates that the key is mandatory for any Windows implementation. Windows also requires that a keyboard and keyboard driver allow the Shift, Ctrl, and Shift and Ctrl keys together to be combined with all letter keys, all required cursor keys, and all required function keys. The VK_LBUTTON, VK_RBUTTON, and VK_MBUTTON virtual key codes refer to the left, right, and middle buttons of a mouse. However, you will never receive keystroke messages with wParam set to these values. The mouse generates its own messages.

VIRTUAL KEY CODES					
Decimal	Hex	WINDOWS.H Identifier	Required	IBM Keyboard	
1	01	VK_LBUTTON			
2	02	VK_RBUTTON			
3	03	VK_CANCEL		Ctrl-Break	
4	04	VK_MBUTTON			
8	08	VK_BACK		Backspace	
9	09	VK_TAB		Tab	
12	0C	VK_CLEAR		Number pad 5 with Num Lock OFF	
13	0D	VK_RETURN		Enter	
16	10	VK_SHIFT		Shift	
17	11	VK_CONTROL		Ctrl	
18	12	VK_MENU		Alt	
19	13	VK_PAUSE			
20	14	VK_CAPITAL		Caps Lock	
27	1B	VK_ESCAPE		Esc	
32	20	VK_SPACE		Spacebar	
33	21	VK_PRIOR		Page Up	
34	22	VK_NEXT		Page Down	
35	23	VK_END		End	
36	24	VK_HOME		Home	
37	25	VK_LEFT		Left Arrow	
38	26	VK_UP		Up Arrow	
39	27	VK_RIGHT		Right Arrow	
40	28	VK_DOWN		Down Arrow	
41	29	VK_SELECT			
42	2A	VK_PRINT			
43	2B	VK_EXECUTE			
45	2D	VK_INSERT	(*)	Ins	
46	2E	VK_DELETE	2.00	Del	
47	2F	VK_HELP			
48-57	30-39		(*8	0 through 9 on main keyboard	
65-90	41-5A			A through Z	
96	60	VK_NUMPAD0		Number pad 0 with Num Lock ON	
97	61	VK_NUMPAD1		Number pad 1 with Num Lock ON	
98	62	VK_NUMPAD2		Number pad 2 with Num Lock ON	
99	63	VK_NUMPAD3		Number pad 3 with Num Lock ON	
100	64	VK_NUMPAD4		Number pad 4 with Num Lock ON	
101	65	VK_NUMPAD5		Number pad 5 with Num Lock ON	
102	66	VK_NUMPAD6		Number pad 6 with Num Lock ON	
103	67	VK_NUMPAD7		Number pad 7 with Num Lock ON	
104	68	VK_NUMPAD8		Number pad 8 with Num Lock ON	
105	69	VK_NUMPAD9		Number pad 9 with Num Lock ON	
106	6A	VK_MULTIPY		Number pad • (Enhanced Keyboard)	

Continued

VIRTUAL KEY CODES						
Decimal	Hex	WINDOWS.H Identifier	Required	IBM Keyboard		
107	6B	VK_ADD		Number pad + (Enhanced Keyboard)		
108	6C	VK_SEPARATOR				
109	6D	VK_SUBTRACT		Number pad - (Enhanced Keyboard)		
110	6E	VK_DECIMAL		Number pad		
111	6F	VK_DIVIDE		Number pad / (Enhanced Keyboard)		
112	70	VK_F1		Function key F1		
113	71	VK_F2		Function key F2		
114	72	VK_F3		Function key F3		
115	73	VK_F4		Function key F4		
116	74	VK_F5	1.83	Function key F5		
117	75	VK_F6		Function key F6		
118	76	VK_F7		Function key F7		
119	77	VK_F8		Function key F8		
120	78	VK_F9		Function key F9		
121	79	VK_F10		Function key F10		
122	7A.	VK_F11		Function key F11 (Enhanced Keyboard)		
123	7B	VK_F12		Function Key F12 (Enhanced Keyboard)		
124	7C	VK_F13				
125	7D	VK_F14				
126	7E	VK_F15				
127	7F	VK_F16				
144	90	VK_NUMLOCK		Num Lock		

Shift States

The wParam and IParam parameters that accompany WM_KEYDOWN, WM_KEYUP, WM_SYSKEYDOWN, and WM_SYSKEYUP messages do not tell your program about the state of the shift keys. You can obtain the current state of any virtual key using the GetKeyState function. This function is generally used to obtain the state of shift keys (Shift, Ctrl, and Alt) and toggle keys (Caps Lock and Num Lock). For instance:

GetKeyState (VK_SHIFT)

returns a negative value (that is, the high bit is set) if the Shift key is down. The value returned from:

GetKeyState (VK_CAPITAL)

has the low bit set if the Caps Lock key is toggled on. You can also obtain the state of the mouse buttons using the virtual key codes VK_LBUTTON, VK_RBUTTON, and VK_MBUTTON. However, most Windows programs that need to monitor a combination of mouse buttons and keystrokes usually do it the other way around—by checking keystrokes when they

receive a mouse message. In fact, shift-state information is included in the mouse messages (as you'll see in the next chapter).

Be careful with *GetKeyState*. It is not a real-time keyboard status check. Rather, it is a check of the keyboard status up to and including the current message being processed. *GetKeyState* does not let you retrieve keyboard information independent of normal keyboard messages. For instance, you may want to hold up processing in your window function until the user presses the F1 function key:

```
while (GetKeyState (VK_F1) >= 0); /* WRONG !!! */
```

This statement will execute a very long time—until you reset your machine with Ctrl-Alt-Delete. Your program must retrieve the keyboard message from the queue before *GetKey-State* can retrieve the state of the key. This synchronization actually works to your advantage, because if you need to know the shift state for a particular keystroke message, *GetKeyState* is guaranteed to be accurate, even if you are processing the message after the shift key has been released. If you really need the current state of the key, you can use *GetAsyncKeyState*.

Using Keystroke Messages

The idea of a program getting information about every keystroke is certainly nice, but most Windows programs ignore all but a few keystroke messages. The WM_SYSKEYDOWN and WM_SYSKEYUP messages are for Windows system functions, and you don't need to look at them. If you process WM_KEYDOWN messages, you can also ignore WM_KEYUP messages.

Windows programs generally use WM_KEYDOWN messages for keystrokes that do not generate characters. Although you may think that it's possible to use keystroke messages in combination with shift-state information to translate keystroke messages into character messages, don't do it. You'll have problems with international keyboard differences. For instance, if you get a WM_KEYDOWN message with wParam equal to 33H, you know the user pressed the 3 key. So far, so good. If you use GetKeyState and find out that the Shift key is down, you might assume that the user is typing a pound (#) sign. Not necessarily so. A British user is typing a £. So the WM_KEYDOWN messages are most useful for the cursor movement keys, the function keys, and special keys such as Insert and Delete. However, Insert, Delete, and the function keys often appear as menu accelerators. Because Windows translates menu accelerators into menu command messages, you don't have to process the keystrokes themselves. Some non-Windows programs for the PC use function keys extensively in combination with the Shift, Ctrl, and Alt keys. You can do something similar in your Windows programs, but it's not recommended. If you want to use the function keys, they should duplicate menu commands. One of the objectives in Windows is to provide a user interface that does not require memorizing or consulting complex command charts.

We've managed to eliminate everything except one final case: Most of the time, you will process WM_KEYDOWN messages only for cursor movement keys. When you use the cursor keys, you can check the Shift-key and Ctrl-key states through *GetKeyState*. Windows functions often use the Shift key in combination with the cursor keys to extend a selection in

(for instance) a word-processing document. The Ctrl key is often used to alter the meaning of the cursor key. (For example, Ctrl in combination with the Right Arrow key might mean to move the cursor forward by a word.)

The Windows Application Style Guide contains a list of recommended keyboard definitions. You can also examine how the keyboard is used in existing Windows programs. If you don't like those definitions, you are free to do something different. But keep in mind that doing so may be detrimental to a user's ability to quickly learn your program.

ENHANCING SYSMETS: ADDING A KEYBOARD INTERFACE

When we wrote the three versions of the SYSMETS program in Chapter 3, we didn't know anything about the keyboard. We were able to scroll the text only by using the mouse on the scroll bars. Now that we know how to process keystroke messages, let's add a keyboard interface to SYSMETS. This is obviously a job for cursor movement keys. We'll use most of the cursor movement keys (Home, End, Page Up, Page Down, Up Arrow, and Down Arrow) for vertical scrolling. The Left Arrow and Right Arrow keys can take care of the less-important horizontal scrolling.

Adding WM_KEYDOWN Logic

One obvious way to create a keyboard interface is to add some WM_KEYDOWN logic to the window function that parallels the WM_VSCROLL and WM_HSCROLL logic:

```
case WM_KEYDOWN:
    nVscrollInc = nHscrollInc = 0 ;
    switch (wParam)
                             /* same as WM_VSCROLL, SB_TOP */
         case VK_HOME:
              nVscrollInc = -nVscrollPos ;
              break ;
         case VK_END:
                             /* same as WM_VSCROLL, SB_BOTTOM */
              nVscrollInc = nVscrollMax - nVscrollPos ;
                             /* same as WM_VSCROLL, SB_LINEUP */
         case VK_UP:
              nVscrollInc = -1;
              break ;
                             /* same as WM_VSCROLL, SB_LINEDOWN */
         case VK_DOWN:
nVscrollInc = 1;
              break ;
                             /* same as WM_VSCROLL, SB_PAGEUP */
         case VK_PRIOR:
              nVscrollInc = min (-1, -yClient / yChar) ;
              break ;
```

```
case VK_NEXT: /* same as WM_VSCROLL, SB_PAGEDOWN */
         nVscrollInc = max (1, yClient / yChar);
          break ;
    case VK_LEFT:
                       /* same as WM_HSCROLL, SB_PAGEUP */
         nHscrollInc = -8;
         break ;
     case VK_RIGHT:
                        /* same as WM_HSCROLL, SB_PAGEDOWN */
         nHscrollInc = 8;
         break ;
     default:
         break :
if (nVscrollInc = max (-nVscrollPos,
         min (nVscrollInc, nVscrollMax - nVscrollPos)))
    nVscrollPos += nVscrollInc ;
     ScrollWindow (hWnd, 0, -yChar * nVscrollInc, NULL, NULL) ;
    SetScrollPos (hWnd, SB_VERT, nVscrollPos, TRUE);
    UpdateWindow (hWnd) ;
if (nHscrollInc = max (-nHscrollPos,
         min (nHscrollInc, nHscrollMax - nHscrollPos)))
    nHscrollPos += nHscrollInc ;
     ScrollWindow (hWnd, -xChar * nHscrollInc, 0, NULL, NULL) ;
    SetScrollPos (hWnd, SB_HORZ, nHscrollPos, TRUE) ;
break ;
```

Do you dislike this code as much as I do? Simply duplicating all the scroll bar code is unwise, because if we ever wanted to change the scroll bar logic, we'd have to make parallel changes in WM_KEYDOWN. There has to be a better way. And there is.

Sending Messages

Wouldn't it be better to simply translate each of these WM_KEYDOWN messages into an equivalent WM_VSCROLL and WM_HSCROLL message and then perhaps fool WndProc into thinking that it's getting a WM_VSCROLL or WM_HSCROLL message, perhaps by sending a phony scroll bar message to the window function? Windows lets you do this. The function is called SendMessage, and it takes the same parameters as those passed to the window function:

```
SendMessage (hWnd, iMessage, wParam, 1Param);
```

When you call SendMessage, Windows calls the window function whose window handle is hWnd, passing to it these four parameters. When the window function has completed processing the message, Windows returns control to the next statement following the SendMessage call. The window function to which you send the message could be the same window function, another window function in the same program, or a window function in another application.

Here's how we might use SendMessage for processing WM_KEYDOWN codes in the SYSMETS program:

```
case WM_KEYDOWN:
    switch (wParam)
{
        case VK_HOME:
            SendMessage (hWnd, WM_VSCROLL, SB_TOP, 0L);
            break;

        case VK_END:
            SendMessage (hWnd, WM_VSCROLL, SB_BOTTOM, 0L);
            break;

        case VK_UP:
            SendMessage (hWnd, WM_VSCROLL, SB_LINEUP, 0L);
            break;
            lother program lines/
```

OK, you get the general idea. Now let's clean this code even more and whittle down the logic to something a little more compact. First, let's define a structure that contains the information needed for sending the window function a scroll bar message based on the keystroke message:

Now the logic for a WM_KEYDOWN message is almost trivial:

Our goal was to add a keyboard interface to the scroll bars, and that's exactly what we've done. We've made the cursor movement keys duplicate scroll bar logic by actually sending the window function a scroll bar message. Now you see why I included SB_TOP and SB_BOTTOM processing for WM_VSCROLL messages in the SYSMETS3 program. It wasn't used then, but it's used now for processing the Home and End keys. The final SYSMETS program, shown in Figure 4-2, incorporates these changes. You'll also need the SYSMETS.H file from Chapter 3 (Figure 3-4) to compile this program.

```
sysmets.obj : sysmets.c sysmets.h

cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp sysmets.c

sysmets.exe : sysmets.obj sysmets.def

link4 sysmets, /align:16, /map, slibw, sysmets
```

```
/* SYSMETS.C -- System Metrics Display */
#include <windows.h>
#include <stdio.h>
#include "sysmets.h"
long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG) ;
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
    HANDLE hInstance, hPrevInstance;
             lpszCmdLine ;
     LPSTR
     int
             nCmdShow ;
     static
             char szAppName [] = "SysMets" ;
     HWND
             hWnd ;
             msg ;
     WNDCLASS wndclass ;
```

Figure 4-2. The SYSMETS program

Figure 4-2. Continued

```
if (!hPrevInstance)
                                        = CS HREDRAW | CS VREDRAW ;
            wndclass.style
            wndclass.lpfnWndProc = WndProc ;
            wndclass.cbClsExtra = 0;
            wndclass.cbWndExtra = 0;
wndclass.hInstance = hInstance;
wndclass.hIcon = LoadIcon (NULL, IDI_APPLICATION);
wndclass.hCursor = LoadCursor (NULL, IDC_ARROW);
            wndclass.hbrBackground = (HBRUSH) GetStockObject (WHITE_BRUSH)
            wndclass.lpszMenuName = NULL ;
            wndclass.lpszClassName = szAppName ;
            if (!RegisterClass (&wndclass))
                   return FALSE ;
      hWnd = CreateWindow (szAppName, "Get System Metrics", WS_OVERLAPPEDWINDOW | WS_HSCROLL | WS_VSCROLL,
                                 CW USEDEFAULT, 0,
                                 CW USEDEFAULT, 0,
                                 NULL, NULL, hInstance, NULL) ;
      ShowWindow (hWnd, nCmdShow);
      UpdateWindow (hWnd) ;
      while (GetMessage (&msg, NULL, 0, 0))
             TranslateMessage (&msg) ;
             DispatchMessage (&msg) ;
      return msg.wParam ;
#define MAXWIDTH 60 /* maximum width of formatted output */
#define NUMKEYS (sizeof key2scroll / sizeof key2scroll[0])
struct
      WORD wVirtKey ;
int iMessage ;
      WORD wRequest ;
      key2scroll [] =
      VK HOME, WM_VSCROLL, SB_TOP,
      VR END, WM VSCROLL, SB BOTTOM,
VK PRIOR, WM VSCROLL, SB PAGEUP,
VK NEXT, WM VSCROLL, SB PAGEDOWN,
VK UP, WM VSCROLL, SB LINEUP,
      VK DOWN, WM VSCROLL, SB LINEDOWN, VK LEFT, WM HSCROLL, SB PAGEUP, VK RIGHT, WM HSCROLL, SB PAGEDOWN
      ) ;
```

Figure 4-2. Continued

```
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
                  hWnd ;
     HWND
                    iMessage ;
     unsigned
                    wParam ;
     WORD
     LONG
                    1Param ;
     static short xChar, yChar;
     static short xClient, yClient; static short nVscrollMax, nHscrollMax;
     static short nVscrollPos, nHscrollPos;
                    szBuffer [80] ;
     char
     HDC
                    hDC ;
     PAINTSTRUCT ps ;
     short
                    nVscrollInc, nHscrollInc ;
                    nPaintBeg, nPaintEnd, i ;
     short
     TEXTMETRIC tm ;
     switch (iMessage)
           case WM CREATE:
                 hDC = GetDC (hWnd) ;
                 GetTextMetrics (hDC, &tm) ;
                 xChar = tm.tmAveCharWidth ;
                 yChar = tm.tmHeight + tm.tmExternalLeading ;
                 ReleaseDC (hWnd, hDC) ;
                 break ;
           case WM SIZE:
                 yClient = HIWORD (1Param) ;
xClient = LOWORD (1Param) ;
                 nVscrollMax = max (0, NUMLINES + 2 - yClient / yChar) ;
                 nVscrollPos = min (nVscrollPos, nVscrollMax);
nHscrollMax = max (0, MAXWIDTH + 2 - xClient / xChar);
nHscrollPos = min (nHscrollPos, nHscrollMax);
                 SetScrollRange (hWnd, SB_VERT, 0, nVscrollMax, FALSE) ;
                 SetScrollPos (hWnd, SB VERT, nVscrollPos, TRUE) ;
SetScrollRange (hWnd, SB_HORZ, 0, nHscrollMax, FALSE) ;
                 SetScrollPos (hWnd, SB HORZ, nHscrollPos, TRUE) ;
                 break ;
           case WM VSCROLL:
                 switch (wParam)
                       case SB TOP:
                             nVscrollInc = -nVscrollPos ;
                             break :
                        case SB BOTTOM:
                             nVscrollInc = nVscrollMax - nVscrollPos ;
                             break ;
                        case SB LINEUP:
                             nVscrollInc = -1 ;
                             break ;
                        case SB LINEDOWN:
                             nVscrollInc = 1 ;
                             break ;
```

Figure 4-2. Continued

```
case SB PAGEUP:
                 nVscrollInc = min (-1, -yClient / yChar) ;
                 break ;
           case SB PAGEDOWN:
                 nVscrollInc = max (1, yClient / yChar) ;
                 break :
           case SB THUMBTRACK:
                 nVscrollInc = LOWORD (1Param) - nVscrollPos ;
                 break ;
           default:
                 nVscrollInc = 0 ;
      if (nVscrollInc = max (-nVscrollPos,
                 min (nVscrollInc, nVscrollMax - nVscrollPos)))
           nVscrollPos += nVscrollInc ;
           ScrollWindow (hWnd, 0, -yChar * nVscrollInc, NULL, NULL) ; SetScrollPos (hWnd, SB_VERT, nVscrollPos, TRUE) ;
           UpdateWindow (hWnd) ;
     break ;
case WM HSCROLL:
     switch (wParam)
           case SB LINEUP:
                 nHscrollInc = -1 ;
                 break ;
           case SB LINEDOWN:
                 nHscrollInc = 1 ;
                 break :
           case SB PAGEUP:
                 nHscrollInc = -8 ;
                 break :
           case SB PAGEDOWN:
                 nHscrollInc = 8 ;
                 break ;
           case SB THUMBPOSITION:
                 nHscrollInc = LOWORD (1Param) - nHscrollPos ;
                 break ;
           default:
                 nHscrollInc = 0 ;
      if (nHscrollInc = max (-nHscrollPos,
                 min (nHscrollInc, nHscrollMax - nHscrollPos)))
           nHscrollPos += nHscrollInc ;
           ScrollWindow (hWnd, -xChar * nHscrollInc, 0, NULL, NULL) ; SetScrollPos (hWnd, SB_HORZ, nHscrollPos, TRUE) ;
      break ;
```

Figure 4-2. Continued

```
case WM KEYDOWN:
          for (i = 0 ; i < NUMKEYS ; i++)
               if (wParam == key2scroll[i].wVirtKey)
                     SendMessage (hWnd, key2scrol1[i].iMessage,
                          key2scroll[i].wRequest, OL) ;
                     break ;
          break ;
     case WM PAINT:
          BeginPaint (hWnd, &ps) ;
          nPaintBeg = max (0, nVscrollPos + ps.rcPaint.top / yChar - 1) ;
          nPaintEnd = min (NUMLINES,
                          nVscrollPos + ps.rcPaint.bottom / yChar) ;
          for (i = nPaintBeg ; i < nPaintEnd ; i++)
               TextOut (ps.hdc,
                          xChar * (1 - nHscrollPos),
yChar * (1 - nVscrollPos + i),
                          szBuffer,
                     sprintf (szBuffer, "%-20s%-35s%5d",
                          sysmetrics[i].szLabel,
                          sysmetrics[i].szDesc,
                          GetSystemMetrics (sysmetrics[i].nIndex))) ;
          EndPaint (hWnd, &ps) ;
          break ;
     case WM DESTROY:
          PostQuitMessage (0) ;
          break ;
     default:
          return DefWindowProc (hWnd, iMessage, wParam, lParam) ;
return OL ;
```

```
SYSMETS
NAME
DESCRIPTION
              'System Metrics Display (C) Charles Petzold, 1987'
              'WINSTUB.EXE'
STUB
       MOVEABLE
CODE
DATA
             MOVEABLE MULTIPLE
            1024
HEAPSIZE
              4096
STACKSIZE
              WndProc
EXPORTS
```

Remember: To send a message to a window function, use the SendMessage function. Do not try to call the window function directly like this:

```
WndProc (hWnd, WM_VSCROLL, SB_PAGEUP, OL) ; /* WRONG !!! */
```

This statement will cause "unpredictable results" (if you call a system crash "unpredictable"). You may define and call other subroutines within a Windows program, but you must not call a window function directly. You'll find out why in Chapter 8.

CHARACTER MESSAGES

Earlier I discussed the idea of translating keystroke messages into character messages by taking into account shift-state information, and I warned that shift-state information is not enough: You also need to know about country-dependent keyboard configurations. For this reason, you should not attempt to translate keystroke messages into character codes yourself.

Windows does it for you. You've see this code before:

```
while (GetMessage (&msg, NULL, 0, 0))
{
   TranslateMessage (&msg) ;
   DispatchMessage (&msg) ;
}
```

This is a typical message loop that appears in *WinMain*. The *GetMessage* function fills in the *msg* structure fields with the next message from the queue. *DispatchMessage* calls the appropriate window function with this message.

Between these two functions is *TranslateMessage*, which translates keystroke messages into character messages. If the message is WM_KEYDOWN or WM_SYSKEYDOWN, and if the keystroke in combination with the shift states produces a character, then *TranslateMessage* places a character message in the message queue. This character message will be the next message that *GetMessage* retrieves from the queue after the keystroke message.

There are four character messages:

	Characters	Dead Characters	
Nonsystem characters	WM_CHAR	WM_DEADCHAR	
System characters	WM_SYSCHAR	WM_SYSDEADCHAR	

The WM_CHAR and WM_DEADCHAR messages are derived from WM_KEYDOWN messages. WM_SYSCHAR and WM_SYSDEADCHAR messages are derived from WM_SYSKEYDOWN messages. In most cases, your Windows program can ignore everything except WM_CHAR messages. The *IParam* parameter passed to the window function with the character code message is the same as the *IParam* parameter for the keystroke message that generated the character code message. The *wParam* parameter is the ASCII code for the character (yes, good old familiar ASCII).

The character messages are delivered to your window function sandwiched between keystroke messages. For instance, if Caps Lock is not toggled and you press and release the A key, the window function receives the following three messages:

Message	Key or Code			
WM_KEYDOWN	Virtual key A			
WM_CHAR	For ASCII code a			
WM_KEYUP	For Virtual key A			

If you type an uppercase A by pressing the Shift key, pressing the A key, releasing the A key, and then releasing the Shift key, the window function receives five messages:

Message	Key or Code	
WM_KEYDOWN	Virtual key VK_SHIFT	
WM_KEYDOWN	Virtual key A	
WM_CHAR	ASCII code A	
WM_KEYUP	Virtual key A	
WM_KEYUP	Virtual key VK_SHIFT	

The Shift key by itself does not generate a character message.

If you hold down the A key so that the typematic action generates keystrokes, you'll get a character message for each WM_KEYDOWN message:

Message	Key or Code	
WM_KEYDOWN	Virtual key A	
WM_CHAR	ASCII code a	
WM_KEYDOWN	Virtual key A	
WM_CHAR	ASCII code a	
WM_KEYDOWN	Virtual key A	
WM_CHAR	ASCII code a	
WM_KEYDOWN	Virtual key A	
WM_CHAR	ASCII code a	
WM_KEYUP	Virtual key A	

If some of the WM_KEYDOWN messages have a Repeat Count greater than 1, the corresponding WM_CHAR messages will have the same Repeat Count.

The Ctrl key in combination with a letter key generates ASCII control codes from 01H (Ctrl-A) through 1AH (Ctrl-Z). You can also use other keys to generate these control codes. The following table shows the value of wParam in a WM_CHAR message for keys that generate control codes:

Key	ASCII Code	Duplicated by	
Backspace	08H	Ctrl-H	
Tab	09H	Ctrl-I	
Ctrl-Enter	0Ah	Ctrl-J	
Enter	0Dh	Ctrl-M	
Esc	1BH	Ctrl-[

Windows programs sometimes use the Ctrl key in combination with letter keys for menu accelerators, in which case the letter keys are not translated into character messages.

WM_CHAR Messages

When your Windows program needs to process characters from the keyboard (for instance, in a word-processing or communications program), it will process WM_CHAR messages. You'll probably want some special processing for the Backspace, Tab, and Enter keys (and perhaps the Linefeed key), but you'll treat all other characters the same:

```
case WM_CHAR:
     switch (wParam)
          case 8:
                           /* backspace */
                (other program lines)
                break ;
          case 9:
                          /* tab */
                (other program lines)
                break ;
          case 10:
                           /* linefeed, maybe */
                (other program lines)
                break ;
          case 13:
                           /* carriage return */
                [other program lines]
                break ;
          default:
                           /* character code */
                [other program lines]
                break ;
```

This program fragment is virtually identical to keyboard character processing in regular MS-DOS programs.

Dead-Character Messages

Windows programs can ususally ignore WM_DEADCHAR and WM_SYSDEADCHAR messages. On some non-U.S. keyboards, certain keys are defined to add a diacritic to a letter. These are called "dead keys" because they don't create characters by themselves. For instance, when the German keyboard is installed, the key that is in the same position as the + and = key on a U.S. keyboard is a dead key for the acute accent (*) when unshifted and the grave accent (*) when shifted.

When a user presses this dead key, your window function receives a WM_DEADCHAR message with wParam equal to the ASCII code for the diacritic by itself. When the user then presses a letter key (for instance, the letter a), the window function receives a WM_CHAR message where wParam is the ASCII code for the letter a with the diacritic. Thus, your program does not have to process the WM_DEADCHAR message, because the WM_CHAR message gives the program all the information it needs. The Windows logic even has built-in error handling: If the dead key is followed by a letter that can't take a diacritic (such as the letter s), then the window function receives two WM_CHAR messages in a row—the first with wParam equal to the ASCII code for the diacritic by itself (the same wParam value delivered with the WM_DEADCHAR message) and the second with wParam equal to the ASCII code for the letter s.

LOOKING AT KEYBOARD MESSAGES

If you'd like to see how Windows sends keyboard messages to a program, KEYLOOK, shown in Figure 4-3, will help. This program displays in its client area all the information that Windows sends the window function for the eight different keyboard messages.

```
keylook.obj : keylook.c
    cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp keylook.c

keylook.exe : keylook.obj keylook.def
    link4 keylook, /align:16, /map, slibw, keylook
```

```
/* KEYLOOK.C -- Displays keyboard & character messages */

#include <windows.h>
#include <stdio.h>

long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG) ;

RECT rect;
short xChar, yChar;
```

Figure 4-3. The KEYLOOK program

Figure 4-3. Continued

```
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
     HANDLE hInstance, hPrevInstance;
     LPSTR lpszCmdLine ;
     int
             nCmdShow ;
     static
              char szAppName [] = "KeyLook" ;
     HWND
              hWnd :
     MSG
              msg ;
     WNDCLASS wndclass ;
     if (!hPrevInstance)
          wndclass.style
                                 = CS HREDRAW | CS VREDRAW :
          wndclass.lpfnWndProc = WndProc ;
          wndclass.cbClsExtra = 0 ;
          wndclass.cbWndExtra = 0;
wndclass.hInstance = hInstance;
wndclass.hIcon = LoadIcon (NULL, IDI_APPLICATION);
wndclass.hCursor = LoadCursor (NULL, IDC_ARROW);
          wndclass.hbrBackground = (HBRUSH) GetStockObject (WHITE BRUSH) ;
          wndclass.lpszMenuName = NULL ;
          wndclass.lpszClassName = szAppName ;
          if (!RegisterClass (&wndclass))
               return FALSE ;
     hWnd = CreateWindow (szAppName, "Keyboard Message Looker",
                          WS OVERLAPPEDWINDOW,
                          CW_USEDEFAULT, 0,
                          CW USEDEFAULT, 0,
                          NULL, NULL, hinstance, NULL) ;
     ShowWindow (hWnd, nCmdShow) ;
     UpdateWindow (hWnd) ;
     while (GetMessage (&msg, NULL, 0, 0))
          TranslateMessage (&msg) ;
          DispatchMessage (&msg) ;
     return msg.wParam ;
void ShowKey (hWnd, iType, szMessage, wParam, 1Param)
     HWND
                hWnd ;
     int
                 iType ;
     char
                 *szMessage ;
     WORD
                 wParam ;
     LONG
                 lParam :
     "%-11s %3d %c %6u %4d %3s %4s %4s" ) ;
     char
                 szBuffer [80] ;
     HDC
                 hDC :
     ScrollWindow (hWnd, 0, -yChar, &rect, &rect) ;
     hDC = GetDC (hWnd) ;
```

Figure 4-3. Continued

```
TextOut (hDC, xChar, rect.bottom - yChar, szBuffer,
          LOWORD (1Param),
HIWORD (1Param) & 0x1FF,
               0x20000000 & 1Param ? "Yes" : "No",
0x40000000 & 1Param ? "Down" : "Up",
0x80000000 & 1Param ? "Up" : "Down"));
     ReleaseDC (hWnd, hDC) ;
     ValidateRect (hWnd, NULL) ;
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
                hWnd ;
     HWND
                 iMessage ;
     unsigned
                 wParam ;
     WORD
                 1Param ;
     LONG
     static char szTop [] = "Message Key Char Repeat Scan ALT Prev Tran" ;
     static char szUnd [] = "
                 hDC ;
     PAINTSTRUCT ps ;
     TEXTMETRIC tm ;
     switch (iMessage)
          case WM CREATE:
                hDC = GetDC (hWnd) ;
                GetTextMetrics (hDC, &tm) ;
                xChar = tm.tmAveCharWidth ;
                yChar = tm.tmHeight ;
                ReleaseDC (hWnd, hDC) ;
                rect.top = 3 * yChar / 2 ;
                break ;
           case WM SIZE:
                rect.right = LOWORD (1Param) ;
                rect.bottom = HIWORD (1Param) ;
                UpdateWindow (hWnd) ;
                break :
          case WM PAINT:
                InvalidateRect (hWnd, NULL, TRUE) ;
                hDC = BeginPaint (hWnd, &ps) ;
                SetBkMode (hDC, TRANSPARENT)
                TextOut (hDC, xChar, yChar / 2, szTop, (sizeof szTop) - 1);
TextOut (hDC, xChar, yChar / 2, szUnd, (sizeof szUnd) - 1);
                EndPaint (hWnd, &ps) ;
                break ;
           case WM KEYDOWN:
                ShowKey (hWnd, 0, "KEYDOWN", wParam, 1Param) ;
                break ;
           case WM KEYUP:
                ShowKey (hWnd, 0, "KEYUP", wParam, 1Param) ;
                break ;
```

Figure 4-3. Continued

```
case WM CHAR:
           ShowKey (hWnd, 1, "CHAR", wParam, 1Param) ;
           break ;
      case WM DEADCHAR:
           ShowKey (hWnd, 1, "DEADCHAR", wParam, 1Param);
           break ;
      case WM SYSKEYDOWN:
           ShowKey (hWnd, 0, "SYSKEYDOWN", wParam, 1Param) ;
           return DefWindowProc (hWnd, iMessage, wParam, 1Param) ;
      case WM SYSKEYUP:
           ShowKey (hWnd, 0, "SYSKEYUP", wParam, 1Param); return DefWindowProc (hWnd, iMessage, wParam, 1Param);
     case WM SYSCHAR:
           ShowKey (hWnd, 1, "SYSCHAR", wParam, 1Param); return DefWindowProc (hWnd, iMessage, wParam, 1Param);
     case WM SYSDEADCHAR:
           ShowKey (hWnd, 1, "SYSDEADCHAR", wParam, 1Param);
           return DefWindowProc (hWnd, iMessage, wParam, 1Param) ;
     case WM DESTROY:
           PostQuitMessage (0) ;
           break ;
     default:
           return DefWindowProc (hWnd, iMessage, wParam, 1Param) ;
return OL :
```

```
NAME
              KEYLOOK
DESCRIPTION
             'Key Look Program (C) Charles Petzold, 1987'
              'WINSTUB.EXE'
STUB
CODE
              MOVEABLE
              MOVEABLE MULTIPLE
DATA
HEAPSIZE
              1024
STACKSIZE
              4096
EXPORTS
              WndProc
```

KEYLOOK uses the display like an old-fashioned teletype output device. When KEYLOOK receives a keystroke message, it calls *ScrollWindow* to scroll the contents of the entire client area of the window so that the contents move up the height of one character. *TextOut* is used to display the line of new information beginning one character height from the bottom. This is about as simple as a teletype output can get. Figure 4-4 (on the following page) shows what the KEYLOOK display looks like when you type the word "Windows."

lessage	Kev	Char	Renea	Scan	ALI	Prev	Iran		
KEYBOWN	16			54	No	Down	Down		
KEYBOWN	87			1 17	No	Down	Down		
CHAR		87 1		1 17	Na	Down	Down		
KEYUP	87			1 17	No	Up	Up		
KEYUP	16			54	No	Up	Up		
KEYDOWN	73			1 23 1 23 1 23	No		Вомп		
CHAR		1.05		1 23	No		Down		
KEYUP	73				No	Up	Up		
KEYDOWN	78			1 49	No		Down		
CHAR		110	1	1 49	No		Down		
KEYUP	78			1 49	No	Up	Up		
KEYDOWN	68		10	1 32	No		Down		
CHAR	200	100	1	1 32	No		Down		
KEYUP	68			1 32			Up		
KEYDOWN	79			1 24			Down		
CHAR		111		1 24			Down		
KEYUP	79			1 24			Up		
KEYDOWN	87			1 17	No		Down		
CHAR		119	4	1 17	No				
KEYUP	87			1 17	No		Up		
KEYDOWN	83			1 31	No		Bown		
CHAR		115		1 31	No		Down		
KEYUP	83			1 31	No	Up	Up	 	

Figure 4-4. The KEYLOOK display

THE WINDOWS CHARACTER SETS

I mentioned earlier that letter keys preceded by dead-character keys generate WM_CHAR messages where wParam is the ASCII code for a character with a diacritic. This may be a little puzzling, because the ASCII character set doesn't include any codes for characters with diacritics. What exactly is the value of wParam in this case? The answer to this question requires that we tackle the subject of character sets, a topic that may at first seem more appropriate for a later discussion about character fonts. However, it is also of vital importance in keyboard handling.

The standard 7-bit ASCII character set defines codes from 0 through 31 (1FH) and 127 (7FH) as control characters, and codes from 32 (20H) through 126 (7EH) as displayable characters. None of these characters have diacritics. Because personal computers use 8-bit bytes, computer manufacturers often define character sets that use 256 codes rather than the 128 ASCII codes. The additional codes may be assigned characters with diacritics. The resultant "extended character set" then includes the ASCII character set and up to 128 other characters.

If Windows supported such an extended character set, displaying characters with diacritics would be easy. But Windows doesn't support a simple extended character set. Windows supports *two* extended character sets. Unfortunately, the presence of these two character sets doesn't make things twice as easy.

The OEM Character Set

First, let's go back to the hardware that Windows runs on today—the IBM PC and compatibles. In the early 1980s the developers of the IBM PC decided to extend the ASCII character set as shown in Figure 4-5. The codes from 20H through 7EH are displayable characters from the ASCII character set. The rest are nonstandard—or at least were at the time.




Figure 4-5. The IBM extended character set arranged by character code

This character set cannot be ignored. It is encoded in millions of ROM chips in IBM video adapters, printers, and system board BIOS's. It has been duplicated in the hardware of numerous manufacturers of IBM compatible computers and peripherals. This character set is part of what is meant by the phrase "the IBM standard." Many programs written for the IBM PC require this extended character set because they use the block-drawing and line-drawing characters (codes BOH through DFH) in their screen output.

The only problem is this: The IBM extended character set is inappropriate for Windows. First, the block-drawing and line-drawing characters commonly used by PC programs in text-mode applications are not needed in Windows because Windows does real graphics. If you want to draw a horizontal line in Windows, it's easier to draw a line than to display a string of C4H characters. Second, the Greek alphabet and mathematical symbols are less important in Windows than are the accented letters used in European languages. A program that needs to display mathematical symbols can best draw them using graphics functions.

In short, Windows supports the IBM character set, but it is relegated to secondary importance, mostly for old applications that run in a window. Windows applications do not normally use the IBM character set. In Windows documentation, the IBM character set is referred to as the "OEM character set." The OEM character set is more precisely defined as the character set that is native to the machine currently running Windows.

The ANSI Character Set

The extended character set that Windows and Windows programs use for most purposes is called the "ANSI character set." When your program receives a WM_CHAR message, the wParam parameter is the ANSI character code. The ANSI character set is shown in Figure 4-6. As you can see, the codes from 20H through 7EH represent the same characters as in the OEM character set and the ASCII character set. The characters displayed as solid blocks are undefined characters. They may appear differently on other output devices (such as a printer).





Figure 4-6. The ANSI extended character set arranged by character code

Figure 4-6. Continued



OEM, ANSI, and Fonts

Windows has different fonts for displaying the ANSI and OEM character sets. When you first obtain a handle to a display context, one of the attributes in the display context is a font. By default this is the SYSTEM_FONT or "system font", which uses the ANSI character set. If you want to display characters from the OEM character set, you can select the OEM_FIXED_FONT (also called the "terminal font") in the display context by using the following code:

```
SelectObject (hDC, GetStockObject (OEM_FIXED_FONT));
```

This is the only font in Windows guaranteed to support the OEM character set.

INTERNATIONALIZATION CONCERNS

Here's why we have to talk about fonts in the middle of the keyboard chapter. We've established that when a Windows user on a non-U.S. keyboard types a character with a diacritic, the *wParam* parameter of the WM_CHAR message is the code for that character in the ANSI character set. So, if you need to echo that character to the display, you had better be using a font with the ANSI character set (such as the SYSTEM_FONT). If you instead use the OEM_FIXED_FONT, the character you write to the display will be incorrect and will surprise the user. A few other simple rules will allow the keyboard logic in your Windows programs to survive intact when you convert your programs for a European market.

Working with the Character Set

When you get a WM_CHAR message, keep in mind that wParam may legitimately have values above 128. Don't assume that anything above 128 is an invalid character.

You may want to convert a character to uppercase. Don't use your own algorithm:

```
if (ch >= 'a' && ch <= 'z')
ch -= 32; /* WRONG !!! */
```

That's a poor practice even when writing non-Windows C. But don't use the standard C function either:

```
ch = toupper (ch) ; /* WRONG !!! */
```

Both these functions work only for the lower half of the ANSI character set. They will not convert a COH to a EOH.

Instead, you should use the Windows functions AnsiUpper and AnsiLower. If str is a NULL-terminated character string, you can convert it to uppercase using AnsiUpper:

```
AnsiUpper (str) ;
```

You can also use AnsiUpper to convert a single character, but some casting is required:

```
ch = AnsiUpper ((LPSTR) (LONG) (BYTE) ch);
```

If ch is defined as an unsigned character, the initial BYTE cast is not required. Windows also includes an AnsiLower function for converting to lowercase.

If you are really serious about writing Windows programs that can be easily converted to foreign languages, you should also investigate the *AnsiNext* and *AnsiPrev* functions. These functions facilitate handling of multibyte character sets. The Japanese character set requires more than 256 characters, some of which use 2 bytes. If you use normal C pointer arithmetic to scan a string (perhaps searching for a backslash character in a directory path string), you may think you've found the character when you've really found the second byte of a 2-byte character code. *AnsiNext* and *AnsiPrev* take a far pointer to a character string and return a far pointer that has been correctly incremented or decremented past 2-byte character codes.

Talking with MS-DOS

If Windows were the only operating environment running on a machine, then you could forget about the OEM character set and use only the ANSI character set. However, users can create files in the MS-DOS environment and use them in Windows; they can also create files in Windows and use them when back in MS-DOS. Unfortunately, MS-DOS uses the OEM character set.

Here's an example of the communications problems that can occur. Suppose a German PC user creates a file named ÜBUNGEN.TXT ("practice exercises") in an MS-DOS program

such as EDLIN. On the IBM PC, the Ü is part of the IBM (that is, OEM) character set and has a code of 154 or 9AH. (When using MS-DOS with a U.S. keyboard on an IBM PC, you can also create this letter by typing Alt-154 using the number pad.) MS-DOS uses that character code in the directory entry of the file.

If a Windows program uses MS-DOS function calls to obtain a directory of files and then displays them directly to the display using an ANSI character set font, the first letter of ÜBUNGEN will show up as a solid block, because the code 154 is one of the undefined characters in the ANSI character set. The Windows program needs to convert the IBM extended character set code of 154 (9AH) to an ANSI character set code of 220 (or DCH), which is the letter Ü in the ANSI character set. That's what the Windows function *OemToAnsi* does for you. It requires two far pointers to strings. The OEM characters in the first string are converted to ANSI characters and stored in the second string:

OemToAnsi (lpszOemStr, lpszAnsiStr)

Now let's take the opposite example. The German user wants your Windows program to create a file named ÜBUNGEN.TXT. The filename entered by the user has a 220 (DCH) as the first character. If you use an MS-DOS function call to open the file, MS-DOS uses that character in the filename. When the user later looks at the file under MS-DOS, the first character shows up as a block. Before you use the MS-DOS function calls, you must convert the filename to the OEM character set:

AnsiToOem (lpszAnsiStr, lpszOemStr)

This converts a 220 (DCH) to a 154 (9AH).

Windows has an *OpenFile* call that will convert this for you. If you use *OpenFile*, don't do your own *AnsiToOem* conversion. If you use MS-DOS function calls to obtain lists of filenames (as the MS-DOS EXECUTIVE program does), then these filenames should be passed through *OemToAnsi* before being displayed.

Converting the contents of files is another problem that arises when files are used in both Windows and MS-DOS. If your Windows program uses files that you know have been created in an MS-DOS program, then you may need to pass the text contents of the file through the *OemToAnsi* function. (For instance, Windows WRITE does this when converting Microsoft Word files to WRITE format.) Similarly, if your Windows program is preparing a file for use in an MS-DOS program, you may want to use *AnsiToOem* to convert the text.

The *OemToAnsi* and *AnsiToOem* functions are located in the keyboard driver. They incorporate very simple look-up tables. The *OemToAnsi* routine converts an OEM code from 80H through FFH to a character code in the ANSI set that most closely resembles the OEM character. In some cases, this conversion is only grossly approximate. For instance, most of the line-drawing characters in the IBM character set are translated as plus signs. The OEM codes from 00H through IFH are not translated to ANSI codes.

The AnsiToOem routine converts ANSI codes from A0H through FFH into codes in the OEM set. The accented characters in the ANSI character set that do not appear in the OEM character set are translated into regular ASCII codes for the characters without the diacritics.

Using the Number Pad

As you probably know, the IBM PC keyboard and BIOS let you enter codes for the IBM extended character set by pressing the Alt key, typing on the numeric keypad the three-digit decimal code representing the OEM character set, and releasing the Alt key. This facility is duplicated in Windows in two ways:

First, when you type Alt-[OEM code] on the number pad, Windows gives to you the ANSI character code in the wParam parameter of the WM_CHAR message that most closely approximates the OEM character represented by the OEM code. That is, Windows passes the code through the OemToAnsi function before generating the WM_CHAR message. This facility is for the user's convenience: If you do not have a foreign-language keyboard and you are accustomed to typing a Ü by typing Alt-154, you can do the same thing in a Windows program. You don't need to relearn the ANSI character codes.

Second, if you want to generate extended ANSI character codes from the U.S. keyboard, type Alt-0-[OEM code] on the number pad. The wParam parameter of the WM_CHAR message is that OEM code. Thus, Alt-0220 is also a Ü.

Chapter 5

The Mouse

The mouse is a pointing device with one or more buttons. Although a mouse is considered an important part of Window's user interface, it is an optional accessory. You can install Windows without a mouse, and you can run most Windows programs completely from the keyboard. Often, the most difficult aspect of using the mouse in your program is adding a keyboard interface to duplicate the mouse functions.

MOUSE BASICS

Windows can support a one-button, two-button, or three-button mouse or use a joystick or light pen to mimic a one-button mouse. The support of a second and third mouse button is rarely exploited, however. Unless you know your Windows program will run only on machines equipped with a two-button or three-button mouse, you must write programs for the least common denominator and use only the single button.

You can determine if a mouse is present by using the GetSystemMetrics function:

bMouse = GetSystemMetrics (SM_MOUSEPRESENT) ;

The value of *bMouse* will be TRUE (nonzero) if a mouse is installed. No method is documented for determining the number of buttons on the installed mouse.

Some Quick Definitions

When the Windows user moves the mouse, Windows moves a small bit-mapped picture on the display called the "mouse cursor." The mouse cursor has a single-pixel "hot spot" that points to a precise location on the display.

The display driver contains several predefined mouse cursors that programs may use. The most common is the slanted arrow called IDC_ARROW in WINDOWS.H. The hot spot is the tip of the arrow. The IDC_CROSS cursor (used in the BLOWUP program shown in this chapter) has a hot spot in the center of a cross-hair pattern. The IDC_WAIT cursor is an hourglass generally used by programs to indicate they are busy. Programmers can also design their own cursors (as we'll do in Chapter 9). The default cursor for a particular window is specified when defining the window class structure, for instance:

wndclass.hCursor = LoadCursor (NULL, IDC_ARROW) ;

The following terms describe the actions you take with mouse buttons:

- · Clicking-Pressing and releasing a mouse button
- Double-clicking—Pressing and releasing a mouse button twice in quick succession
- Dragging—Moving the mouse while holding down a button

On a three-button mouse, the buttons are called the left button, middle button, and right button. Mouse-related identifiers defined in WINDOWS.H use the abbreviations LBUTTON, MBUTTON, and RBUTTON. A two-button mouse has only a left button and a right button. The single button on a one-button mouse is a left button.

The Mouse Driver

The retail version of Windows includes mouse drivers for several manufacturers' mouse devices as well as light pens and joysticks. When you install Windows, the appropriate driver file is merged into WIN200.BIN. In the "slow-boot" version of Windows, the mouse driver is a file named MOUSE.DRV located in the Windows subdirectory. If you run the slow-boot version, you can easily test how your programs function without a mouse by copying the NOMOUSE.DRV driver file into the Windows subdirectory and renaming it MOUSE.DRV in the process.

The mouse driver exports three functions called *Inquire*, *Enable*, and *Disable*. Windows calls *Enable* to install the mouse and *Disable* to uninstall it. Mouse hardware usually generates a hardware interrupt when the mouse is moved or the button is pressed or released. The Windows mouse driver contains an interrupt handler to process these hardware interrupts and call a routine within the USER module. The USER module also creates a mouse message that it places in the system message queue, to be later transferred to the message queue of the appropriate Windows task. (Windows also physically moves the mouse cursor on the display when the mouse is moved.)

In this way, the mouse driver works much like the keyboard driver: Both drivers process hardware interrupts and inform Windows of these interrupts. Windows then generates synchronous messages from the asynchronous hardware interrupts.

Light pens and joysticks do not generate hardware interrupts. The drivers for these devices must obtain a "system timer" from the SYSTEM.DRV module and periodically poll the hardware device.

CLIENT-AREA MOUSE MESSAGES

In the previous chapter you saw how Windows sends keyboard messages only to the window with the input focus. Mouse messages are different: A window function receives mouse messages whenever the mouse passes over the window or is clicked within the window, even if the window is not active or does not have the input focus.

Windows defines 21 messages for the mouse. However, 11 of these are "nonclient-area" messages, and Windows programs usually ignore them. Of the 10 "client-area" mouse messages, 6 pertain to the right and middle buttons. Windows programs usually ignore these messages also.

When the mouse is moved over the client area of a window, the window function receives the message WM_MOUSEMOVE. When a mouse button is pressed or released within the client area of a window, the window function receives these messages:

Button	Pressed	Released	Pressed (2d Click)	
Left	WM_LBUTTONDOWN	WM_LBUTTONUP	WM_LBUTTONDBLCLK	
Right	WM_RBUTTONDOWN	WM_RBUTTONUP	WM_RBUTTONDBLCLK	
Middle	WM_MBUTTONDOWN	WM_MBUTTONUP	WM_MBUTTONDBLCLK	

Your window function receives "MBUTTON" messages only for a three-button mouse and "RBUTTON" messages only for a two-button or three-button mouse. The window function receives "DBLCLK" (double-click) messages only if the window class has been defined to receive them (as described below).

For all these messages, the value of *IParam* contains the position of the mouse. The low word is the x coordinate, and the high word is the y coordinate relative to the upper left corner of the client area of the window. You can extract the x and y coordinates from *IParam* using the LOWORD and HIWORD macros defined in WINDOWS.H. The value of *wParam* indicates the state of the mouse buttons and the Shift and Ctrl keys. You can test *wParam* using the bit masks defined in WINDOWS.H. The MK prefix stands for "mouse key."

MK_LBUTTON	Left button is down
MK_RBUTTON	Right button is down
MK_MBUTTON	Middle button is down
MK_SHIFT	Shift key is down
MK_CONTROL	Ctrl key is down

As you move the mouse over the client area of a window, Windows does *not* generate a WM_MOUSEMOVE message for every possible pixel position of the mouse. The number of WM_MOUSEMOVE messages your program receives depends on the mouse hardware and on the speed that your window function can process the mouse movement messages. You'll get a good idea of the rate of WM_MOUSEMOVE messages when you experiment with the CONNECT program described below.

If you click the left mouse button in the client area of an inactive window, Windows changes the active window to the window that is being clicked and then passes the WM_LBUTTONDOWN message to the window function. When your window function gets a WM_LBUTTONDOWN message, your program can safely assume the window is active. However, your window function can receive a WM_LBUTTONUP message without first receiving a WM_LBUTTONDOWN message. This can happen if the mouse button is pressed in one window, moved to another window, and released. Similarly, the window function can receive a WM_LBUTTONDOWN without a corresponding WM_LBUTTONUP message if the mouse button is released while positioned over another window.

There are two exceptions to these rules:

- A window function can "capture the mouse" and continue to receive mouse messages even when the mouse is outside the window's client area. You'll learn how to capture the mouse later in this chapter.
- If a "system-modal" message box or dialog box is on the display, no other program
 can receive mouse messages. System-modal message boxes and dialog boxes
 prohibit switching to another window or program while the box is active. (An
 example of a system-modal message box is the one that says "This will end your
 Windows session" when you close the MS-DOS Executive.)

Simple Mouse Processing: An Example

The CONNECT program, shown in Figure 5-1, does some simple mouse processing to let you get a good feel for how Windows sends your program mouse messages.

```
connect.obj : connect.c
    cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp connect.c

connect.exe : connect.obj connect.def
    link4 connect, /align:16, /map, slibw, connect
```

Figure 5-1. The CONNECT program

Figure 5-1. Continued

```
/* CONNECT.C -- Connect-the-Dots Mouse Demo Program */
#include <windows.h>
#define MAXPOINTS 1000
long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG) ;
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
                 hInstance, hPrevInstance;
     HANDLE
                  lpszCmdLine ;
     LPSTR
                  nCmdShow ;
     int
     static char szAppName [] = "Connect" ;
     HWND
              hWnd ;
     MSG
                 msg :
     WNDCLASS
                wndclass :
     if (!hPrevInstance)
          wndclass.style
                                   = CS_HREDRAW | CS_VREDRAW ;
          wndclass.style = CS_HREDRAY
wndclass.lpfnWndProc = WndProc;
wndclass.cbClsExtra = 0;
          wndclass.cbWndExtra = 0 ;
          wndclass.hInstance = hInstance ;
          wndclass.hIcon = LoadIcon (NULL, IDI_APPLICATION) ;
wndclass.hCursor = LoadCursor (NULL, IDC_ARROW) ;
          wndclass.hbrBackground = GetStockObject (WHITE BRUSH) ;
          wndclass.lpszMenuName = NULL;
          wndclass.lpszClassName = szAppName ;
          if (!RegisterClass (&wndclass))
                return FALSE ;
     hWnd = CreateWindow (szAppName, "Connect-the-Points Mouse Demo",
                           WS OVERLAPPEDWINDOW,
                           CW_USEDEFAULT, 0,
CW_USEDEFAULT, 0,
                           NULL, NULL, hInstance, NULL) ;
     ShowWindow (hWnd, nCmdShow) ;
     UpdateWindow (hWnd) ;
     while (GetMessage (&msg, NULL, 0, 0))
          TranslateMessage (&msg) ;
          DispatchMessage (&msg) ;
     return msg.wParam ;
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
                 hWnd ;
     unsigned
                   iMessage ;
     WORD
                   wParam ;
     LONG
                   lParam ;
     static POINT points [MAXPOINTS] ;
     static short nCount ;
```

Figure 5-1. Continued

```
HDC
             hDC ;
PAINTSTRUCT ps ;
short
switch (iMessage)
     case WM LBUTTONDOWN:
           nCount = 0 ;
           InvalidateRect (hWnd, NULL, TRUE) ;
           break ;
     case WM MOUSEMOVE:
           if (wParam & MK_LBUTTON && nCount < 1000)
                points [nCount++] = MAKEPOINT (1Param) ;
                hDC = GetDC (hWnd) ;
SetPixel (hDC, LOWORD (lParam), HIWORD (lParam), OL) ;
                ReleaseDC (hWnd, hDC) ;
           break :
     case WM LBUTTONUP:
           InvalidateRect (hWnd, NULL, FALSE) ;
           break ;
     case WM PAINT:
           hDC = BeginPaint (hWnd, &ps) ;
           for (i = 0 ; i < nCount - 1 ; i++)
                for (j = i ; j < nCount ; j++)
                      MoveTo (hDC, points[i].x, points[i].y);
LineTo (hDC, points[j].x, points[j].y);
           EndPaint (hWnd, &ps) ;
           break ;
     case WM DESTROY:
           PostQuitMessage (0) ;
           break ;
     default:
           return DefWindowProc (hWnd, iMessage, wParam, 1Param) ;
return OL ;
```

```
CONNECT
NAME
DESCRIPTION
               'Mouse Connect Program (C) Charles Petzold, 1987'
               'WINSTUB.EXE'
STUB
               MOVEABLE
CODE
               MOVEABLE MULTIPLE
DATA
HEAPSIZE
               1024
               4096
STACKSIZE
EXPORTS
               WndProc
```

CONNECT processes three mouse messages:

- WM_LBUTTONDOWN—CONNECT clears the client area.
- WM_MOUSEMOVE—If the left button is down, CONNECT draws a black dot on the client area at the mouse position.
- WM_LBUTTONUP—CONNECT connects every drawn dot in the client area to
 every other dot. Sometimes this results in a pretty design; sometimes in a dense
 blob. (See Figure 5-2.)




Figure 5-2. The CONNECT display

To use CONNECT, bring the mouse cursor into the client area, press the left button, move the mouse around a little, and release the left button. CONNECT works best for a curved pattern of a few dots, which you can draw by moving the mouse quickly when the left button is depressed. CONNECT uses several simple Graphics Device Interface (GDI) functions. Set-Pixel draws a one-pixel dot of a particular color, in this case black. (On high-resolution displays, the pixel may be nearly invisible.) Drawing the lines requires two functions: MoveTo marks the x and y coordinates of the beginning of the line, and LineTo draws the line.

If you move the mouse cursor out of the client area before releasing the button, CON-NECT does not connect the dots, because it doesn't receive the WM_LBUTTONUP message. If you move the mouse back into the client area and press the left button again, CONNECT clears the client area. (If you want to continue a design after releasing the button outside the client area, press the left button again while the mouse is outside the client area and then move the mouse back in.) CONNECT stores a maximum of 1000 points. The number of lines it draws is equal to:

where P is the number of points. With 1000 points, this involves almost 500,000 lines, which can take several minutes to draw. For anything but a demonstration program, this is too long for a Windows program to hog system resources.

If CONNECT is busy drawing lines, you can press the mouse button, move the mouse around, and release the mouse button, but nothing will happen. CONNECT does not receive these messages because it is busy and not making any *GetMessage* calls. After CONNECT finishes drawing the lines, it does not receive these messages because the mouse button has been released already. In this respect, the mouse is not like the keyboard. Windows treats every keystroke as if it were important. But if a mouse button is pressed and released in the client area while a program is busy, the mouse clicks are discarded.

Now try this: While CONNECT is engaged in a lengthy drawing routine, hold down the mouse button and move the mouse around. After CONNECT is finished drawing, it will retrieve the WM_LBUTTONDOWN message from the queue (and clear the client area) because the button is currently down. However, it receives only the WM_MOUSEMOVE messages that occur after it receives the WM_LBUTTONDOWN message.

Sometimes the word *tracking* is used to refer to the way that programs process mouse movement. Tracking does not mean, however, that your program sits in a loop in its window function attempting to follow the mouse as it is moved around the display. The window function instead processes each mouse message as it comes and then quickly exits.

POINT, RECT, and IParam

CONNECT uses an array of POINT structures for saving points. The POINT structure is defined in WINDOWS.H and has two fields named x and y:

Some Windows functions require a POINT structure (or a pointer to a POINT structure) as a parameter. You can define a POINT structure variable (named *point*, for instance) in your program with this definition:

```
POINT point ;
```

If you need to convert an IParam value—the x and y mouse coordinates—to a POINT structure, you can use the MAKEPOINT macro:

```
point = MAKEPOINT (1Param) ;
```

In WINDOWS.H, MAKEPOINT is defined like this:

```
#define MAKEPOINT(1) (*((POINT *)&1))
```

Despite the apparent complexity of this macro, it compiles very efficiently because all it does is store *lParam* at the address of *point*. WINDOWS.H defines the type PPOINT as a pointer to a POINT structure, so perhaps this statement (without using the macro) makes the conversion a little clearer:

```
point = * (PPOINT) &1Param ;
```

(Remember that normal C order-of-evaluation rules cause address, indirection, and type cast operators to be evaluated from right to left.)

The RECT structure defines a rectangle. Here's the WINDOWS.H definition:

```
typedef
{
   int left;
   int top;
   int right;
   int bottom;
}
RECT;
```

This structure really contains two points side by side: left and right are x coordinates, and top and bottom are y coordinates. You can define a structure variable (named rect, for instance) with the statement:

```
RECT rect ;
```

Transferring coordinates in a RECT structure to a POINT structure is also straightforward. This statement sets *point* to the upper left corner of the rectangle:

```
point = * (PPOINT) &rect.left
```

This does the same for the lower right corner:

```
point = * (PPOINT) &rect.right
```

You can also define an array of two points:

```
POINT points [2] ;
```

and transfer these two points into a RECT structure:

```
rect = * (PRECT) points;
```

PRECT is defined in WINDOWS.H as a pointer to a RECT structure. You don't need the & (address) operator before *points* because *points* is an array. In C, an array name is the address of the first element of the array.

Processing Shift Keys

When CONNECT receives a WM_MOUSEMOVE message, it performs a bitwise AND operation on the value of wParam and MK_LBUTTON to determine if the left button is depressed. You can also use wParam to determine the state of the shift keys. For instance, if processing must be dependent on the status of the Shift and Ctrl keys, you might use logic that looks like this:

The Windows function GetKeyState (described in Chapter 4) can also return the state of the mouse buttons or shift keys using the virtual key codes VK_LBUTTON, VK_RBUTTON, VK_MBUTTON, VK_SHIFT, and VK_CONTROL. The button or key is down if the value returned from GetKeyState is negative. Because GetKeyState returns mouse or key states as of the message currently being processed, the status information is properly synchronized with the messages. But just as you cannot use GetKeyState for a key that has yet to be pressed, so you cannot use it for a mouse button that has yet to be pressed. Don't do this:

```
while (GetKeyState (VK_LBUTTON) >= 0) ; /* WRONG !!! */
```

The GetKeyState function will report that the left button is depressed only if the button is already depressed when you process the message during which you call GetKeyState.

Mouse Double-Clicks

A mouse double-click is two clicks in quick succession. To qualify as a double-click, the two clicks must occur within a specific interval called the "double-click time." If you want your window function to receive double-click mouse messages, you must include the identifier CS_DBLCLKS when initializing the window style in the window class structure before calling RegisterClass:

```
wndclass.style = CS_HREDRAW | CS_VREDRAW | CS_DBLCLKS ;
```

If you do not include CS_DBLCLKS in the window style and the user clicks the left mouse button twice in quick succession, your window function receives these messages: WM_LBUTTONDOWN, WM_LBUTTONUP, WM_LBUTTONDOWN, and WM_LBUTTONUP. (The window function might also receive other messages between these button messages.) If you want to implement your own double-click logic, you can use the Windows function Get-MessageTime to obtain the relative times of the WM_LBUTTONDOWN messages. This function is discussed in more detail in Chapter 6.

If you include CS_DBLCLKS in your window class, the window function receives these messages for a double-click: WM_LBUTTONDOWN, WM_LBUTTONUP, WM_LBUTTONDBLCLK, and WM_LBUTTONUP. The WM_LBUTTONDBLCLK message simply replaces the second WM_LBUTTONDOWN message.

Double-click messages are much easier to process if the first click of a double-click performs the same action as a single click. The second click (the WM_LBUTTONDBLCLK message) then does something in addition to the first click. For example, look at how the mouse works with the file directory list in the MS-DOS Executive program. A single click selects the file or directory: The MS-DOS Executive highlights the file or directory with a reverse video bar. A double-click performs two actions: The first click selects the file or directory, just like a single click; the second click (which is a WM_LBUTTONDBLCLK message) directs the MS-DOS Executive to run the file or change to the directory. That's fairly easy logic.

Now take a look at how the MS-DOS Executive changes subdirectories based on clicks and double-clicks on the current directory name. A single click invokes a dialog box requesting confirmation that the directory be changed. A double-click changes the directory without confirmation. Now this is tricky, because the MS-DOS Executive can't act on a click until it knows that the click is not the first click of a double-click. When the MS-DOS Executive receives a single click on the directory name, it must wait before it brings up the dialog box. This wait involves a loop that calls <code>PeekMessage</code> and <code>GetMessageTime</code>. If the window function does not receive a double-click message within the double-click time, the MS-DOS Executive then uses the dialog box for a confirmation.

The Double-Click Time

The default value of the double-click time is 500 milliseconds (one-half second). During installation of Windows, the SETUP program includes this value in the [windows] section of the WIN.INI file following the keyword DoubleClickSpeed. The WIN.INI file looks like this:

[windows]
/other WIN.INI lines/
DoubleClickSpeed=500

Your Windows program can retrieve the double-click time value stored in WIN.INI. However, do not, from your program, open WIN.INI as a file to read it. Windows includes simple functions to read from and write to WIN.INI. To retrieve the *DoubleClickSpeed* value, you can use *GetProfileInt*:

```
wTime = GetProfileInt ("windows", "DoubleClickSpeed", 500);
```

The last parameter to GetProfileInt is a default value that the function returns if it cannot find the DoubleClickSpeed keyword in the [windows] section of WIN.INI. The wTime value returned from the function is the double-click time in milliseconds.

You can also retrieve the current double-click time value without accessing WIN.INI by using the function:

```
wTime = GetDoubleClickTime () ;
```

This should return the same value stored in WIN.INI. However, Windows uses the Double-ClickSpeed setting from WIN.INI only when it first loads. Some other not-so-nice program (certainly not one of yours) could have used an undocumented Windows function to set the double-click time without updating WIN.INI:

```
SetDoubleClickTime (wTime) ;
```

Following this function call, the double-click time that Windows uses will be different from the value in WIN.INI. The *DoubleClickSpeed* value in WIN.INI can be changed with this function:

```
WriteProfileString ("windows", "DoubleClickSpeed", itoa (wTime, szBuffer, 10));
```

Users can change the double-click time using the CONTROL program. CONTROL calls both SetDoubleClickTime and WriteProfileString to change the current setting and the value stored in WIN.INI. Because the same double-click time applies to all programs running under Windows, you'll probably want to leave the settings alone.

Another mouse-related function you probably shouldn't use is:

```
SwapMouseButton (bSwap) ;
```

If bSwap is TRUE (nonzero), Windows switches the meaning of the left and right buttons. The left button then generates RBUTTON messages, and the right button generates LBUTTON messages. This is primarily for left-handed users who want to use their index finger to press the "left button." To swap the two buttons for future Windows sessions, you can change the Swap-MouseButtons value in the [windows] section of WIN.INI from:

```
SwapMouseButtons=No
```

to:

```
SwapMouseButtons=Yes
```

Because the CONTROL program allows users to swap the meanings of the mouse buttons, it's probably best for other applications to avoid doing so.

NONCLIENT-AREA MOUSE MESSAGES

The 10 mouse messages discussed so far occur when the mouse is moved or clicked within the client area of a window. If the mouse is outside a window's client area but still within the window, Windows sends the window function a "nonclient-area" mouse message. The nonclient area of a window includes the caption bar, the menu, and window scroll bars.

You do not usually need to process nonclient-area mouse messages. Instead, you simply pass them on to <code>DefWindowProc</code> so Windows can perform system functions. In this respect, the nonclient-area mouse messages are similar to the system keyboard messages <code>WM_SYSKEYDOWN</code>, <code>WM_SYSKEYUP</code>, and <code>WM_SYSCHAR</code>.

The nonclient-area mouse messages parallel almost exactly the client-area mouse messages. The messages include the letters "NC" to indicate "nonclient." If the mouse is moved in a nonclient area of a window, then the window function receives the message WM_NCMOUSEMOVE. The mouse buttons generate these messages:

Button	Pressed	Released	Pressed (2d Click)
Left	WM_NCLBUTTONDOWN	WM_NCLBUTTONUP	WM_NCLBUTTONDBLCLK
Right	WM_NCRBUTTONDOWN	WM_NCRBUTTONUP	WM_NCRBUTTONDBLCLK
Middle	WM_NCMBUTTONDOWN	WM_NCMBUTTONUP	WM_NCMBUTTONDBLCLK

However, the *wParam* and *lParam* parameters for nonclient-area mouse messages are different from those for client-area mouse messages. The *wParam* parameter indicates the nonclient area where the mouse was moved or clicked. It is set to one of the identifiers beginning with HT that are defined in WINDOWS.H (such as HTCAPTION and HTSYSMENU).

The *lParam* variable contains an x coordinate in the low word and a y coordinate in the high word. However, these are screen coordinates, not client-area coordinates as they are for client-area mouse messages. For screen coordinates, the upper left corner of the display area has x and y values of 0. Values of x increase as you move to the right, and values of y increase as you move down. (See Figure 5-3 on the following page.)

You can convert screen coordinates to client-area coordinates and vice versa with two Windows functions:

```
ScreenToClient (hWnd, lpPoint) ;
ClientToScreen (hWnd, lpPoint) ;
```

The *IpPoint* parameter is a far (or long) pointer to a structure of type POINT. These two functions convert the values stored in the structure without preserving the old values. Note that if a screen coordinate point is above the window's client area, then the converted client-area *y* coordinate will be negative. Similarly, a screen coordinate to the left of a client area is a negative *x* value when expressed as a client-area coordinate.




Figure 5-3. Screen coordinates and client-area coordinates

The Hit-Test Message

If you've been keeping count, you know that we've covered 20 of the 21 mouse messages. The last message is WM_NCHITTEST, which stands for "nonclient hit test." This message precedes all other client-area and nonclient-area mouse messages. The Param parameter contains the x and y screen coordinates of the mouse position. The Param parameter is not used.

Windows applications usually pass this message to *DefWindowProc*. Windows then uses the WM_NCHITTEST message to generate all other mouse messages based on the position of the mouse. For nonclient-area mouse messages, the value returned from *DefWindowProc* when processing WM_NCHITTEST becomes the *wParam* parameter in the mouse message. This value can be any of the *wParam* values that accompany the nonclient-area mouse messages plus the following:

HTCLIENT	Client area	
HTNOWHERE	Not on any window	
HTTRANSPARENT	A window covered by another window	
HTERROR	Causes Def WindowProc to produce a beep	

If *DefWindowProc* returns HTCLIENT after it processes a WM_NCHITTEST message, then Windows converts the screen coordinates to client-area coordinates and generates a client-area mouse message.

If you remember how we disabled all system keyboard functions by trapping the WM_SYSKEYDOWN message, you may wonder if you can do something similar by trapping mouse messages. Sure. If you include the lines:

```
case WM_NCHITTEST:
    return (long) HTNOWHERE;
```

in your window function, you will effectively disable all client-area and nonclient-area mouse messages to your window. The mouse buttons will simply not work while the mouse is anywhere within your window, including the system menu box and size box.

Messages Beget Messages

Windows uses the WM_NCHITTEST message to generate all other mouse messages. The idea of messages giving birth to other messages is common in Windows. Let's take an example. As you know, if you double-click the system menu box of a Windows program, the program will be terminated. The double-click generates a series of WM_NCHITTEST messages. Because the mouse is positioned over the system menu box, <code>DefWindowProc</code> returns a value of HTSYSMENU and Windows puts a WM_NCLBUTTONDBLCLK message in the message queue with <code>wParam</code> equal to HTSYSMENU.

The window function usually passes that mouse message to <code>DefWindowProc</code>. When <code>DefWindowProc</code> receives the WM_NCLBUTTONDBLCLK message with <code>wParam</code> equal to HTSYSMENU, it puts a WM_SYSCOMMAND message with <code>wParam</code> equal to SC_CLOSE in the message queue. (This WM_SYSCOMMAND message is also generated when a user selects Close from the system menu box.) Again, the window function usually passes that message to <code>DefWindowProc</code> processes the message by putting a WM_CLOSE message in the message queue.

If a program wants to require confirmation from a user before terminating, the window function can trap WM_CLOSE. Otherwise, <code>DefWindowProc</code> processes WM_CLOSE by calling the <code>DestroyWindow</code> function. Among other actions, <code>DestroyWindow</code> puts a WM_DESTROY message in the message queue. Normally, a window function processes WM_DESTROY with the code:

```
case WM_DESTROY:
    PostQuitMessage (0);
    break;
```

The PostQuitMessage causes Windows to place a WM_QUIT message in the message queue. This message never reaches the window function because it causes GetMessage to return 0, which terminates the message loop and the program.

HIT-TESTING IN YOUR PROGRAMS

A little earlier I discussed how the MS-DOS Executive processes mouse clicks and double-clicks. Let's look at the MS-DOS Executive again. The client area is divided into three sections: the disk drive icons, the current directory path, and the directory list. When you click on something in any of these three areas, the MS-DOS Executive must determine what you are clicking. This is called "hit-testing." Just as <code>DefWindowProc</code> must do some hit-testing when processing WM_NCHITTEST messages, very often a window function must do hit-testing within the client area. In general, hit-testing involves calculations using the <code>x</code> and <code>y</code> coordinates passed to your window function in the <code>IParam</code> parameter of the mouse message.

A Hypothetical Example

Here's an example. Your program displays several columns of alphabetically sorted files similar to the MS-DOS Executive file list. The file list starts at the top of the client area, which is xClient pixels wide and yClient pixels high; each character is xChar pixels wide and yChar pixels high. The filenames are stored in a sorted array of pointers to character strings called szFileNames. Your columns are 14 characters wide, so the column width in pixels is:

```
xColWidth = 14 * xChar ;
```

The number of files you can fit in each column is:

```
nNumInCol = yClient / yChar ;
```

You receive a mouse click message with the coordinates xMouse and yMouse derived from IParam. You can determine which column of filenames the user is pointing to using the formula:

```
nColumn = xMouse / xColWidth ;
```

The position of the filename from the top of the column is:

```
nFromTop = yMouse / yChar ;
```

Now you can calculate an index to the szFileNames array:

```
nIndex = nColumn * nNumInCol + nFromTop;
```

Obviously, if *nIndex* exceeds the number of files in the array, the user is clicking on a blank area of the display.

In many cases, hit-testing is more complex than this example shows. For example, it can become very messy in a word-processing program that uses variable font sizes (such as WRITE). When you display something to the client area, you must determine the coordinates for each item you display. In hit-testing calculations, you must go backward from the coordinates to the object. However, if the objects you display are strings, then going backward involves finding the character position within the string.

A Sample Program

The CHECKER1 program, shown in Figure 5-4, demonstrates some simple hit-testing. The program divides the client area into a 5-by-5 array of 25 rectangles. If you click the mouse in one of the rectangles, the rectangle is filled with an X. If you click again, the X is removed.

```
checker1.obj : checker1.c
    cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp checker1.c

checker1.exe : checker1.obj checker1.def
    link4 checker1, /align:16, /map, slibw, checker1
```

```
/* CHECKER1.C -- Mouse Hit-Test Demo Program No. 1 */
#include <windows.h>
#define DIVISIONS 5
long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG) ;
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
     HANDLE hInstance, hPrevInstance;
      LPSTR
                    lpszCmdLine ;
                   nCmdShow ;
     static char szAppName [] = "Checker1" ;
     HWND hWnd;
     MSG
                   msg ;
     WNDCLASS
                   wndclass :
      if (!hPrevInstance)
           wndclass.style = CS_HREDRAW | CS_VREDRAW ;
wndclass.lpfnWndProc = WndProc ;
wndclass.cbClsExtra = 0 ;
wndclass.cbWndExtra = 0 ;
wndclass.bWndExtra = 0 ;
           wndclass.hInstance = hInstance;
wndclass.hIcon = NULL;
wndclass.hCursor = LoadCursor (NULL, IDC_ARROW);
           wndclass.hbrBackground = GetStockObject (WHITE BRUSH) ;
           wndclass.lpszMenuName = NULL ;
           wndclass.lpszClassName = szAppName ;
           if (!RegisterClass (&wndclass))
                 return FALSE ;
     hWnd = CreateWindow (szAppName, "Checkerl Mouse Hit-Test Demo",
                             WS OVERLAPPEDWINDOW,
                             CW_USEDEFAULT, 0,
CW_USEDEFAULT, 0,
                             NULL, NULL, hinstance, NULL) ;
```

Figure 5-4. The CHECKER1 program

Figure 5-4. Continued

```
ShowWindow (hWnd, nCmdShow) ;
     UpdateWindow (hWnd) ;
     while (GetMessage (&msg, NULL, 0, 0))
           TranslateMessage (&msg) ;
           DispatchMessage (&msg) ;
      return msg.wParam ;
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
                     hWnd ;
                     iMessage :
     unsigned
     WORD
                     wParam ;
                     1Param ;
     LONG
     static BOOL bState [DIVISIONS] [DIVISIONS] ;
     static short xBlock, yBlock ;
                     hDC ;
     PAINTSTRUCT
                    ps ;
                     rect ;
     RECT
     short
                    x, y ;
     switch (iMessage)
            case WM SIZE:
                 xBlock = LOWORD (lParam) / DIVISIONS ;
yBlock = HIWORD (lParam) / DIVISIONS ;
                  break :
            case WM LBUTTONDOWN:
                 x = LOWORD (lParam) / xBlock;
y = HIWORD (lParam) / yBlock;
                  if (x < DIVISIONS && y < DIVISIONS)
                        bState [x][y] = 1 ;
                        rect.left = x * xBlock;
rect.top = y * yBlock;
rect.right = (x + 1) * xBlock;
rect.bottom = (y + 1) * yBlock;
                        InvalidateRect (hWnd, &rect, FALSE) ;
                  else
                        MessageBeep (0) ;
                  break ;
            case WM PAINT:
                  hDC = BeginPaint (hWnd, &ps) ;
                  for (x = 0 ; x < DIVISIONS ; x++)
                         for (y = 0 ; y < DIVISIONS ; y++)
                              Rectangle (hDC, x * xBlock, y * yBlock, (x + 1) * xBlock, (y + 1) * yBlock) ;
```

Figure 5-4. Continued

```
NAME CHECKER1
DESCRIPTION 'Mouse Hit-Test Demo Program No. 1 (C) Charles Petzold, 1987'
STUB 'WINSTUB.EXE'
CODE MOVEABLE
DATA MOVEABLE MULTIPLE
HEAPSIZE 1024
STACKSIZE 4096
EXPORTS WndProc
```

Figure 5-5 (on the following page) shows the CHECKER1 display. All 25 rectangles have the same width and height. These width and height values are stored in <code>xBlock</code> and <code>yBlock</code> and are recalculated when the size of the client area changes. The <code>WM_LBUTTONDOWN</code> logic uses the mouse coordinates to determine which rectangle has been clicked. It flags the current state of the rectangle in the array <code>bState</code> and invalidates the rectangle to generate a <code>WM_PAINT</code> message. If the width or height of the client area is not equally divisible by five, then a small strip of client area at the left or bottom will not be covered by a rectangle. For error processing, CHECKER1 responds to a mouse click in this area by calling <code>MessageBeep</code>.

When CHECKER1 receives a WM_PAINT message, it repaints the entire client area by drawing rectangles using the GDI Rectangle function. If the bState value is set, CHECKER1 draws two lines using the MoveTo and LineTo functions. During WM_PAINT processing, CHECKER1 does not check the validity of each rectangular section before repainting it, but it could. One method for checking validity involves building a RECT structure for each rectangular block within the loop (using the same formulas as in the WM_LBUTTONDOWN logic) and checking if




Figure 5-5. The CHECKER1 display

it intersects the invalid rectangle (ps.rcPaint) by using the function IntersectRect. Another method is to use PtInRect to determine if any of the four corners of the rectangular block are within the invalid rectangle.

Emulating the Mouse with the Keyboard

CHECKER1 works only if you have a mouse. We'll be adding a keyboard interface to the program shortly, as we did for the SYSMETS program in Chapter 4. However, adding a keyboard interface to a program that uses the mouse cursor for pointing purposes requires that we also must worry about displaying and moving the mouse cursor.

Even if a mouse device is not installed, Windows can still display a mouse cursor. Windows maintains a "display count" for this cursor. If a mouse is installed, the display count is initially 0; if not, the display count is initially –1. The mouse cursor is displayed only if the display count is 0 or positive. You can increment the display count by calling:

```
ShowCursor (TRUE);
and decrement it by:
ShowCursor (FALSE);
```

You do not need to determine if a mouse is installed before using ShowCursor. If you want to display the mouse cursor regardless of the presence of the mouse, simply increment

the display count. After you increment the display count once, decrementing it will hide the cursor if no mouse is installed but leave it displayed if a mouse is present. The display count applies to all of Windows, so you should ensure that you increment and decrement the display count an equal number of times.

You may want to use the following simple logic in your window function:

```
WM_SETFOCUS:
    ShowCursor (TRUE);
    break;

WM_KILLFOCUS:
    ShowCursor (FALSE);
    break;
```

A window function receives the WM_SETFOCUS message when the window obtains the key-board input focus and WM_KILLFOCUS when it loses the input focus. These are ideal times to display and "un-display" the mouse cursor. First, the WM_SETFOCUS and WM_KILLFOCUS calls are balanced—that is, the window function will increment and decrement the mouse cursor display count an equal number of times. Second, for versions of Windows installed without a mouse, using the WM_SETFOCUS and WM_KILLFOCUS messages causes the cursor to be visible only when the window has the input focus. That is also the only time the user can move the cursor using the keyboard interface that you'll design.

Windows maintains a current mouse cursor position even if a mouse is not installed. If a mouse is not installed, and you display the mouse cursor, it may appear in any part of the display, and will remain in that position until you explicitly move it. You can obtain the cursor position by:

```
GetCursorPos (lpPoint) ;
```

where *lpPoint* is a far pointer to a POINT structure. The function fills in the POINT fields with the x and y coordinates of the mouse. You can set the cursor position using:

```
SetCursorPos (x, y) ;
```

In both cases, the x and y values are screen coordinates, not client-area coordinates. (This should be evident because the functions do not require a hWnd parameter.) As noted earlier, you can convert screen coordinates to client-area coordinates and vice versa by using Screen-ToClient and ClientToScreen.

If you call <code>GetCursorPos</code> while processing a mouse message and convert to client-area coordinates, the coordinates may still be slightly different from those in <code>IParam</code> of the mouse message. The coordinates returned from <code>GetCursorPos</code> indicate the current position of the mouse. The coordinates in <code>IParam</code> of a mouse message are the coordinates of the mouse when the message was generated.

You'll probably want to write keyboard logic to move the mouse cursor with the keyboard arrow keys and simulate the mouse button with the Spacebar or Enter key. What you don't want to do is move the mouse cursor one pixel per keystroke. That forces a user to hold down an arrow key for more than a minute to move the mouse cursor from one side of the display to another.

If you need to implement a keyboard interface to the mouse cursor but still maintain the ability to position the cursor at precise pixel locations, take a look at Windows PAINT. When you hold down the arrow keys in PAINT, the mouse cursor starts moving slowly but then speeds up. You'll recall that the *IParam* parameter in WM_KEYDOWN messages indicates if the keystroke messages are the result of typematic action. This is an excellent application of that information.

Adding a Keyboard Interface to CHECKER

The CHECKER2 program, shown in Figure 5-6, is the same as CHECKER1 except that it includes a keyboard interface. You can use the Left, Right, Up, and Down Arrow keys to move the cursor among the 25 rectangles. The Home key sends the cursor to the upper left rectangle; the End key drops it down to the lower right rectangle. Both the Spacebar and Enter keys toggle the X mark.

```
checker2.obj : checker2.c
     cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp checker2.c

checker2.exe : checker2.obj checker2.def
     link4 checker2, /align:16, /map, slibw, checker2
```

Figure 5-6. The CHECKER2 program

Figure 5-6. Continued

```
if (!hPrevInstance)
            wndclass.stvle
                                      = CS HREDRAW | CS VREDRAW ;
            wndclass.lpfnWndProc = WndProc;
            wndclass.prwndroc;
wndclass.cbClsExtra = 0;
wndclass.cbWndExtra = 0;
wndclass.hInstance = hInstance;
wndclass.hIcon = NULL;
wndclass.hCursor = LoadCursor (NULL, IDC_ARROW);
            wndclass.hbrBackground = GetStockObject (WHITE BRUSH) ;
            wndclass.lpszMenuName = NULL ;
            wndclass.lpszClassName = szAppName ;
            if (!RegisterClass (&wndclass))
                  return FALSE :
      hWnd = CreateWindow (szappName, "Checker2 Mouse Hit-Test Demo", WS_OVERLAPPEDWINDOW,
                             CW USEDEFAULT, 0,
                             CW USEDEFAULT, 0,
                             NULL, NULL, hinstance, NULL) ;
      ShowWindow (hWnd, nCmdShow);
      UpdateWindow (hWnd) ;
      while (GetMessage (&msg, NULL, 0, 0))
           TranslateMessage (&msg) ;
           DispatchMessage (&msg) ;
      return msq.wParam :
long FAR PASCAL WndProc (hWnd, iMessage, wParam, lParam)
                  hWnd ;
     unsigned
                    iMessage ;
     WORD
                    wParam ;
     LONG
                    lParam ;
     static BOOL bState [DIVISIONS] [DIVISIONS] ;
     static short xBlock, yBlock;
     HDC
                   hDC ;
     PAINTSTRUCT ps ;
     POINT
                    point ;
     RECT
                    rect ;
     short
                    x, y ;
     switch (iMessage)
           case WM SIZE:
                 xBlock = LOWORD (1Param) / DIVISIONS ;
yBlock = HIWORD (1Param) / DIVISIONS ;
                 break ;
           case WM SETFOCUS:
                 ShowCursor (TRUE) ;
                 break :
```

Figure 5-6. Continued

```
case WM_KILLFOCUS:
     ShowCursor (FALSE) ;
     break :
case WM KEYDOWN:
     GetCursorPos (&point) ;
     ScreenToClient (hWnd, &point) ;
     x = max (0, min (DIVISIONS - 1, point.x / xBlock));
y = max (0, min (DIVISIONS - 1, point.y / yBlock));
      switch (wParam)
            case VK UP:
                 y -- ;
                 break :
            case VK DOWN:
                  y ++ ;
                  break ;
            case VK LEFT:
                  x -- ;
                  break :
            case VK RIGHT:
                  x ++ ;
                  break ;
            case VK_HOME:
                  x = y = 0;
                  break ;
            case VK END:
                  x = y = DIVISIONS - 1;
                  break ;
            case VK RETURN:
            case VK SPACE:
                 SendMessage (hWnd, WM_LBUTTONDOWN, MK_LBUTTON,
                             MAKELONG (x * xBlock, y * yBlock));
                  break ;
      x = (x + DIVISIONS) % DIVISIONS ;
      y = (y + DIVISIONS) % DIVISIONS ;
      point.x = x * xBlock + xBlock / 2 ;
point.y = y * yBlock + yBlock / 2 ;
      ClientToScreen (hWnd, &point) ;
      SetCursorPos (point.x, point.y) ;
      break ;
 case WM LBUTTONDOWN:
      x = LOWORD (lParam) / xBlock;
y = HIWORD (lParam) / yBlock;
```

Figure 5-6. Continued

```
if (x < DIVISIONS && y < DIVISIONS)
                     bState [x][y] = 1 ;
                     rect.left = x * xBlock;
                     rect.top = y * yBlock;
rect.right = (x + 1) * xBlock;
rect.bottom = (y + 1) * yBlock;
                     InvalidateRect (hWnd, &rect, FALSE) ;
              else
                     MessageBeep (0) ;
              break ;
       case WM PAINT:
              hDC = BeginPaint (hWnd, &ps) ;
              for (x = 0 ; x < DIVISIONS ; x++)
                     for (y = 0 ; y < DIVISIONS ; y++)
                            Rectangle (hDC, x * xBlock, y * yBlock, (x + 1) * xBlock, (y + 1) * yBlock);
                            if (bState [x][y])
                                  MoveTo (hDC, x * xBlock, y * yBlock);
LineTo (hDC, (x+1) * xBlock, (y+1) * yBlock);
MoveTo (hDC, x * xBlock, (y+1) * yBlock);
LineTo (hDC, (x+1) * xBlock, y * yBlock);
              EndPaint (hWnd, &ps) ;
             break ;
      case WM DESTROY:
             PostQuitMessage (0) ;
             break :
      default:
             return DefWindowProc (hWnd, iMessage, wParam, 1Param) ;
return OL ;
```

```
NAME
DESCRIPTION 'Mouse Hit-Test Demo Program No. 2 (C) Charles Petzold, 1987'
STUB 'WINSTUB.EXE'
CODE MOVEABLE
DATA MOVEABLE MULTIPLE
HEAPSIZE 1024
STACKSIZE 4096
EXPORTS WndProc
```

The WM_KEYDOWN logic in CHECKER2 determines the position of the cursor (Get-CursorPos), converts the screen coordinates to client-area coordinates (ScreenToClient), and divides the coordinates by the width and height of the rectangular block. This produces x and y values that indicate the position of the rectangle in the 5-by-5 array. The mouse cursor may or may not be in the client area when a key is pressed, so x and y must be passed through the WINDOWS.H min and max macros to ensure that they range from 0 to 4.

For arrow keys, CHECKER2 increments or decrements x and y appropriately. If the key is the Enter key (VK_RETURN) or Spacebar (VK_SPACE), CHECKER2 uses SendMessage to send a WM_LBUTTONDOWN message to itself. This technique is similar to the method used in the SYSMETS program in Chapter 4 to add a keyboard interface to the window scroll bar. The WM_KEYDOWN logic finishes by calculating client-area coordinates that point to the center of the rectangle, converting to screen coordinates (ClientToScreen), and setting the cursor (SetCursorPos).

Using Child Windows for Hit-Testing

Earlier I discussed a hypothetical hit-testing problem involving lists of filenames similar to those displayed by the MS-DOS Executive. I simplified this problem by stating that the list of files began at the top of the client area. In the MS-DOS Executive, however, the file list does not begin at the top of the client area. Instead, the MS-DOS Executive must take into account the section of the client area occupied by the disk drive icons and the current directory path. This is obvious.

Or is it? The MS-DOS Executive actually uses a different technique that helps simplify its hit-testing. The MS-DOS Executive creates three "child windows" within its client area: the first for the disk drive icons, the second for the current directory path, and the third for the file list. (See Figure 5-7.)

The child windows divide the entire client area into several smaller rectangular regions. Each child window has its own window handle, window function, and client area. Each window function receives mouse messages that apply only to its child window. The *IParam* parameter in the mouse message contains coordinates relative to the upper left corner of the client area of the child window, not of the parent window.

Child windows used in this way can help you structure and modularize your programs. If the child windows use different window classes, each child window can have its own window function. The different window classes can also define different background colors and different default cursors. In Chapter 7, we'll look at "child window controls"—predefined child windows that take the form of scroll bars, buttons, and edit boxes. Right now, let's see how we can make use of child windows in the CHECKER program.




Figure 5-7. The three child windows created by the MS-DOS Executive

Child Windows in CHECKER

Figure 5-8 shows CHECKER3. This version of the program creates 25 child windows to process mouse clicks. It does not have a keyboard interface, but one could be easily added.

```
checker3.obj : checker3.c
    cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp checker3.c
checker3.exe : checker3.obj checker3.def
    link4 checker3, /align:16, /map, slibw, checker3
```

```
/* CHECKER3.C -- Mouse Hit-Test Demo Program No. 3 */
#include <windows.h>
#define DIVISIONS 5
long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG);
long FAR PASCAL ChildWndProc (HWND, unsigned, WORD, LONG);
```

Figure 5-8. The CHECKER3 program

Figure 5-8. Continued

```
char szChildClass [] = "Checker3 Child" ;
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
                  hInstance, hPrevInstance;
     HANDLE
                   lpszCmdLine ;
     LPSTR
                   nCmdShow ;
     int
     static char szAppName [] = "Checker3" ;
                   hWnd :
                   msq ;
     MSG
                   wndclass ;
     WNDCLASS
     if (!hPrevInstance)
                                   = CS HREDRAW | CS VREDRAW ;
           wndclass.style
           wndclass.lpfnWndProc = WndProc ;
           wndclass.cbClsExtra = 0;
wndclass.cbWndExtra = 0;
           wndclass.cbWndExtra
                                   = hInstance ;
           wndclass.hInstance
           wndclass.hIcon = LoadIcon (NULL, IDI APPLICATION);
wndclass.hCursor = LoadCursor (NULL, IDC_ARROW);
wndclass.hbrBackground = GetStockObject (WHITE_BRUSH);
           wndclass.lpszMenuName = NULL ;
           wndclass.lpszClassName = szAppName ;
           if (!RegisterClass (&wndclass))
                 return FALSE ;
           wndclass.lpfnWndProc = ChildWndProc;
           wndclass.cbWndExtra = sizeof (WORD) ;
wndclass.hICon = NULL ;
           wndclass.hIcon
           wndclass.lpszClassName = szChildClass ;
           if (!RegisterClass (&wndclass))
                 return FALSE ;
     hWnd = CreateWindow (szAppName, "Checker3 Mouse Hit-Test Demo",
                            WS OVERLAPPEDWINDOW,
                            CW_USEDEFAULT, 0, CW_USEDEFAULT, 0,
                            NULL, NULL, hInstance, NULL) ;
      ShowWindow (hWnd, nCmdShow) ;
      UpdateWindow (hWnd) ;
      while (GetMessage (&msg, NULL, 0, 0))
            TranslateMessage (&msg) ;
            DispatchMessage (&msg) ;
      return msg.wParam ;
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
      HWND
                   hWnd ;
      unsigned
                   iMessage ;
                    wParam ;
      WORD
      LONG
                    1Param ;
      1
```

Figure 5-8. Continued

```
static HWND hchild [DIVISIONS] [DIVISIONS] ;
     short xBlock, yBlock, x, y ;
     switch (iMessage)
          case WM CREATE:
                for (x = 0 ; x < DIVISIONS ; x++)
                     for (y = 0 ; y < DIVISIONS ; y++)
                          hChild [x][y] = CreateWindow (szChildClass, NULL,
                               WS_CHILDWINDOW | WS_VISIBLE, 0, 0, 0, 0, 0,
                               hWnd, y << 8
                               GetWindowWord (hWnd, GWW HINSTANCE), NULL) ;
                break ;
          case WM_SIZE:
               xBlock = LOWORD (1Param) / DIVISIONS ;
               yBlock = HIWORD (1Param) / DIVISIONS ;
               for (x = 0 ; x < DIVISIONS ; x++)
                     for (y = 0 : y < DIVISIONS : y++)
                         MoveWindow (hChild [x][y],
                              x * xBlock, y * yBlock, xBlock, yBlock, TRUE) ;
               break ;
          case WM LBUTTONDOWN:
               MessageBeep (0);
               break ;
          case WM DESTROY:
               PostQuitMessage (0) ;
               break ;
          default:
               return DefWindowProc (hWnd, iMessage, wParam, 1Param) ;
     return OL ;
long FAR PASCAL ChildWndProc (hWnd, iMessage, wParam, 1Param)
                hWnd :
     unsigned
                iMessage ;
     WORD
                 wParam ;
     LONG
                lParam ;
    HDC
    PAINTSTRUCT ps ;
    RECT
    switch (iMessage)
         case WM CREATE:
              SetWindowWord (hWnd, 0, 0); /* on/off flag */
               break ;
```

Figure 5-8. Continued

```
case WM LBUTTONDOWN:
          SetWindowWord (hWnd, 0, 1 GetWindowWord (hWnd, 0));
InvalidateRect (hWnd, NULL, FALSE);
           break ;
     case WM PAINT:
          hDC = BeginPaint (hWnd, &ps) ;
          GetClientRect (hWnd, &rect) ;
           Rectangle (hDC, 0, 0, rect.right, rect.bottom) ;
           if (GetWindowWord (hWnd, 0))
                 MoveTo (hDC, 0,
                 LineTo (hDC, rect.right, rect.bottom) ;
                MoveTo (hDC, 0, rect.
LineTo (hDC, rect.right, 0) ;
                                             rect.bottom) ;
           EndPaint (hWnd, &ps) ;
           break :
     default:
           return DefWindowProc (hWnd, iMessage, wParam, 1Param) ;
return OL ;
```

```
NAME
               CHECKER3
               'Mouse Hit-Test Demo Program No. 3 (C) Charles Petzold, 1987'
DESCRIPTION
               'WINSTUB.EXE'
STUB
               MOVEABLE
CODE
DATA
               MOVEABLE MULTIPLE
HEAPSIZE
               1024
STACKSIZE
               4096
EXPORTS
               WndProc
               ChildWndProc
```

CHECKER3 has two window functions called *WndProc* and *ChildWndProc*. *WndProc* is still the window function for the main (or parent) window. *ChildWndProc* is the window function for the 25 child windows. The names of both window functions must appear as EXPORTS in the CHECKER3.DEF file because both functions are called from Windows.

Because the window function is defined by the window class structure that you register with Windows using the *RegisterClass* call, the two window functions in CHECKER3.C require two window classes. The first window class is for the main window and has the name "Checker3." The second window class is given the name "Checker3_Child".

Most of the fields of the *undclass* structure are simply reused when "Checker3_Child" is registered in *WinMain*. The *lpszClassName* field is set to "Checker3_Child"—the name of the class. The *lpfnWndProc* field is set to *ChildWndProc*, the window function for this window class, and the *hlcon* field is set to NULL, because icons are not used with child windows. For the "Checker3_Child" window class, the *cbWndExtra* field in the *undclass* structure is set to 2 bytes, or more precisely, *sizeof* (WORD). This field tells Windows to reserve 2 bytes of extra space in a structure Windows maintains for each window based on this window class. You can use this space to store information that may be different for each window.

The CreateWindow call in WinMain creates the main window based on the "Checker3" class. This is normal. However, when WndProc receives a WM_CREATE message, it calls CreateWindow 25 times to create 25 child windows based on the "Checker3_Child" window class. Here's a comparison of the parameters to the CreateWindow call in WinMain that creates the main window and the CreateWindow call in WndProc that creates the 25 child windows:

	Main Window	Child Window
window class	"Checker3"	"Checker3Child"
window caption	"Checker3"	NULL
window style	WS_OVERLAPPEDWINDOW	WS_CHILDWINDOW WS_VISIBLE
horizontal position	CW_USEDEFAULT	0
vertical position	0	0
width	CW_USEDEFAULT	0
height	0	0
parent window handle	NULL	hWnd
menu handle / child ID	NULL	y << 8 x
instance handle	hInstance	GetWindowWord (hWnd, GWW_HINSTANCE)
extra parameters	NULL	NULL

Normally, the position, width, and height parameters are required for child windows, but in CHECKER3 the child windows are positioned and resized later in *WndProc*. The parent window handle is NULL for the main window because it is the parent. The parent window handle is required when using the *CreateWindow* call to create a child window.

The main window doesn't have a menu, so that parameter is NULL. For child windows, the same parameter position is a "child ID." This is a number that uniquely identifies the child window. The child ID becomes much more important when working with child window controls because messages to the parent window are identified by this child ID. For CHECKER3, I've used the child ID to identify the position in the 5-by-5 array that each child window occupies within the main window.

The instance handle is *hInstance* in both cases. When the child window is created, the *hInstance* value is extracted using the function *GetWindowWord* from the structure that Windows maintains for the window. (Rather than use *GetWindowWord* I could have saved the value of *hInstance* in a global variable and used it directly.)

Each child window has a different window handle that is stored in the hChild array. When WndProc receives a WM_SIZE message, it calls MoveWindow for each of the 25 child windows. The parameters indicate the upper left corner of the child window relative to the parent window client-area coordinates, the width and height of the child window, and whether the child window needs repainting.

Now let's take a look at ChildWndProc. This window function processes messages for all 25 child windows. The hWnd parameter to ChildWndProc is the handle to the child window receiving the message. When ChildWndProc processes a WM_CREATE message (which will happen 25 times because there are 25 child windows), it uses SetWindowWord to store a 0 in the extra area reserved within the window structure. (Recall that we reserved this space using the cbWndExtra field when defining the window class structure.) ChildWndProc uses this value to store the current state (X or no X) of the rectangle. When the child window is clicked, the WM_LBUTTONDOWN logic simply flips the value of this word (from 0 to 1 or from 1 to 0) and invalidates the entire child window client area. This area is the single rectangle being clicked. The WM_PAINT processing is trivial, because the size of the rectangle it draws is the same size as the client window.

Because the C source code file and the EXE file of CHECKER3 are larger than those for CHECKER1 (to say nothing of my explanation of the programs), I will not try to convince you that CHECKER3 is "simpler" than CHECKER1. But note that we no longer have to do any mouse hit-testing! If a child window in CHECKER3 gets a WM_LBUTTONDOWN message, the window has been hit, and that's all it needs to know.

If you want to add a keyboard interface to CHECKER3, be aware that the main window still gets keyboard messages, because it has the input focus. We'll explore child windows more in Chapter 7.

CAPTURING THE MOUSE

As you've seen, a window function normally receives mouse messages only when the mouse cursor is positioned over the client or nonclient area of the window. A program that needs to receive mouse messages when the mouse is outside the window can "capture" the mouse.

Capturing the mouse is easier than baiting a mousetrap. You need only call:

```
SetCapture (hWnd) ;
```

Following this function call, Windows sends all mouse messages to the window function for the window whose handle is *hWnd*. The mouse messages are always client-area messages, even when the mouse is in a nonclient area of the window. The *lParam* parameter still indicates the position of the mouse in client-area coordinates. However, these *x* and *y* coordinates can be negative if the mouse is to the left of or above the client area.

During the time the mouse is captured, system keyboard functions are also disabled. When you want to release the mouse, call:

```
ReleaseCapture () ;
```

This returns processing to normal.

The BLOWUP Program

The BLOWUP program, shown in Figure 5-9, uses SetCapture and ReleaseCapture and a few other interesting techniques. The program lets you use the mouse to block out any rectanglar area of the screen. BLOWUP then copies the contents of that rectangular area into its own client area, stretching or compressing the image as appropriate. (See Figure 5-10 on page 192.)

```
blowup.obj : blowup.c
cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp blowup.c
blowup.exe : blowup.obj blowup.def
link4 blowup, /align:16, /map, slibw, blowup
```

Figure 5-9. The BLOWUP program

Figure 5-9. Continued

```
static char szAppName [] = "BlowUp" ;
    HWND
             hWnd ;
    MSG
                 msq ;
    WNDCLASS
                wndclass ;
    if (!hPrevInstance)
         wndclass.hInstance = hInstance;
wndclass.hIcon = LoadIcon (NULL, IDI_APPLICATION);
wndclass.hCursor = LoadCursor (NULL, IDC_ARROW);
          wndclass.hbrBackground = GetStockObject (WHITE_BRUSH) ;
          wndclass.lpszMenuName = NULL ;
          wndclass.lpszClassName = szAppName ;
          if (!RegisterClass (&wndclass))
               return FALSE ;
    hWnd = CreateWindow (szAppName, "Blow-Up Mouse Demo",
                          WS OVERLAPPEDWINDOW,
                          CW_USEDEFAULT, 0,
CW_USEDEFAULT, 0,
                          NULL, NULL, hInstance, NULL) ;
     ShowWindow (hWnd, nCmdShow) ;
     UpdateWindow (hWnd) ;
     while (GetMessage (&msg, NULL, 0, 0))
          TranslateMessage (&msg) ;
          DispatchMessage (&msg) ;
     return msg.wParam ;
void InvertBlock (hWnd, beg, end)
     HWND hWnd ;
     POINT beg, end;
     HDC
         hDC ;
     hDC = CreateDC ("DISPLAY", NULL, NULL, NULL) ;
     ClientToScreen (hWnd, &beg) ;
     ClientToScreen (hWnd, &end) ;
     PatBlt (hDC, beg.x, beg.y, end.x - beg.x, end.y - beg.y, DSTINVERT) ;
     DeleteDC (hDC) ;
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
                  hWnd :
     HWND
     unsigned
                   iMessage :
                   wParam ;
     WORD
     LONG
                   1Param ;
```

Figure 5-9. Continued

```
static BOOL bCapturing, bBlocking;
static POINT beg, end;
RECT
              rect ;
switch (iMessage)
     case WM LBUTTONDOWN:
           if (!bCapturing)
                bCapturing = TRUE ;
                 SetCapture (hWnd) ;
                 SetCursor (LoadCursor (NULL, IDC CROSS)) :
           else if (!bBlocking)
                bBlocking = TRUE ;
                beg = MAKEPOINT (1Param) ;
           break ;
     case WM MOUSEMOVE:
           if (bBlocking)
                end = MAKEPOINT (1Param) ;
                InvertBlock (hWnd, beg, end) ;
InvertBlock (hWnd, beg, end) ;
           break :
     case WM LBUTTONUP:
           if (bBlocking)
                bCapturing = bBlocking = FALSE ;
                end = MAKEPOINT (1Param) ;
                SetCursor (LoadCursor (NULL, IDC WAIT)) ;
                hDC = GetDC (hWnd) ;
                GetClientRect (hWnd, &rect) ;
                StretchBlt (hDC, 0, 0, rect.right, rect.bottom, hDC, beg.x, beg.y, end.x - beg.x, end.y - beg.y,
                              SRCCOPY) ;
                ReleaseDC (hWnd, hDC) ;
                SetCursor (LoadCursor (NULL, IDC_ARROW)) ;
                ReleaseCapture () ;
           break ;
     case WM_DESTROY:
           PostQuitMessage (0) ;
           break ;
     default:
           return DefWindowProc (hWnd, iMessage, wParam, 1Param) ;
return OL ;
```

Figure 5-9. Continued

```
NAME
               BLOWUP
                'Blow Up Mouse Demo Program (C) Charles Petzold, 1987'
DESCRIPTION
STUB
               'WINSTUB.EXE'
CODE
               MOVEABLE
DATA
               MOVEABLE MULTIPLE
HEAPSIZE
               1024
STACKSIZE
               4096
               WndProc
EXPORTS
```




Figure 5-10. The BLOWUP client area

The job of stretching and compressing bitmapped images may seem complex, but it's simplified for us by a Windows GDI function called *StretchBlt*. (The abbreviation "*Blt*" is pronounced "blit." The function is related to the Windows *BitBlt* function, which stands for "bit block transfer." These functions are discussed in more detail in Chapter 14.)

Here's how to use BLOWUP:

- 1. Click the mouse in BLOWUP's client area. The mouse cursor changes to a cross hair.
- Position the mouse cursor over the upper left corner of the area of the screen you want to transfer.
- Press the mouse button, drag the mouse to the lower right corner, and release the mouse button. The mouse cursor changes to an hourglass.

 In a few seconds (or maybe a little longer), the area you blocked out is copied to BLOWUP's client area, compressed or expanded appropriately.

If you block out a rectangle by moving from the upper right corner to the lower left corner, BLOWUP displays a mirror image. If you move from the lower left to the upper right, BLOWUP displays an upside-down image. And if you move from lower right to upper left, the program combines the two effects.

Changing the Mouse Cursor

BLOWUP uses the *SetCursor* calls to change the cursor image from an arrow to a cross hair, then to an hourglass, and back to an arrow. All these are stock cursors available in Windows. You obtain the handle to the cursor using the *LoadCursor* function. In Chapter 9 we'll use *LoadCursor* to display customized mouse cursors.

Many applications display an hourglass cursor (defined in WINDOWS.H as IDC_WAIT) while doing processing that may take some time to complete. This is fairly simple to implement. You can save the handle to the original cursor by storing the return value from SetCursor and using it to reset the cursor later. First, you'll need a variable of type HCURSOR (defined in WINDOWS.H as a HANDLE, or 16-bit WORD) to store that value:

```
HCURSOR hCursor ;
```

Right before you start the lengthy processing, use the following two lines:

```
hCursor = SetCursor (LoadCursor (NULL, IDC_WAIT));
ShowCursor (TRUE);
```

After you're done with the work, call:

```
ShowCursor (FALSE);
SetCursor (hCursor);
```

The two ShowCursor calls display and then hide the hourglass cursor if a mouse is not actually present.

Normally, Windows changes the mouse cursor to the cursor included in the window class structure whenever the window function receives a WM_MOUSEMOVE message. If you use SetCursor to change the mouse cursor and then exit the window function, the mouse cursor will be restored to the cursor in the window class structure the next time the mouse is moved. This does not happen in BLOWUP, because the mouse is captured during the time the cross-hair (IDC_CROSS) cursor is displayed. Windows will not change the cursor to the window class cursor when the mouse is captured. Also, if you need to display an hourglass cursor when doing some lengthy work (as BLOWUP does when it calls StretchBlt), you don't have to worry about the problem, because you're not receiving any other messages during that time.

But if you want to use different mouse cursors for other purposes, you should define a NULL cursor handle in your window class:

```
wndclass.hCursor = NULL ;
```

In your window function, you then call SetCursor for each WM_MOUSEMOVE message. The SetCursor call is fast if the mouse cursor is not being changed.

The StretchBit Call

BLOWUP calls the *StretchBlt* function during processing of the WM_LBUTTONUP message to transfer the blocked-out image to BLOWUP's client area:

This function is discussed in more detail in Chapter 14, but let's take a quick look at it here.

StretchBlt transfers a bitmapped image from a source to a destination. The first five parameters are for the destination of the image, defining the device context handle, the x and y coordinates of the upper left corner, and the width and height. The next five parameters give the same information for the source of the image. The last parameter is the operation, which in this case is a simple copy from source to destination.

The source of the image involves two POINT structures named beg (beginning of the block) and end (end of the block). These two points have negative coordinate values if you block out an image to the left of or above the client area. StretchBlt can read a bitmapped image that falls outside the client area, but like all GDI functions it cannot write outside the client area.

Drawing the Capture Block

But wait. When you use BLOWUP to block out an image outside its client area, the program briefly displays the image in reverse video and then restores it to normal. BLOWUP is apparently writing outside its client area. Can that be so?

It certainly is. This little trick is carried off in BLOWUP's InvertBlock function. Rather than obtain a device context handle from GetDC, InvertBlock uses CreateDC:

```
hDC = CreateDC ("DISPLAY", NULL, NULL, NULL) ;
```

This returns a device context handle for the entire display. Using this device context handle, you can write outside your client area.

InvertBlock uses the GDI PatBlt function (a "pattern bit block transfer") to invert the blocked-out image. BLOWUP calls InvertBlock twice in succession. When called the second time, the block is restored to normal. This means that you can see the block briefly only when you move the mouse cursor.

Why do it like this? BLOWUP doesn't leave the block in an inverted state because other Windows programs can receive messages between BLOWUP's WM_MOUSEMOVE messages. (For instance, the Windows CLOCK gets WM_TIMER messages every second.) If BLOWUP left the block inverted when it exited its window function, then the program with the altered client area could write over the inverted block. When BLOWUP then reinverted the block—that is, returned it to normal—the result would start looking like a mess. Keep considerations like this in mind when you start working with powerful functions like *CreateDC*. Windows gives you the power to do almost anything, but your programs must share resources like the display with other programs. Try to exercise a little restraint.

Chapter 6

The Timer

The Windows timer is an input device that periodically notifies an application when a specified interval of time has elapsed. Your program tells Windows the interval, in effect saying, for example, "Give me a nudge every 10 seconds." Windows then sends your program recurrent WM_TIMER messages to signal the intervals.

At first, the Windows timer may seem a less important input device than the keyboard or mouse, and certainly it is for many applications. But the timer is more useful than you may think, and not only for programs (like the Windows CLOCK) that keep time. The CALENDAR, CONTROL, REVERSI, SPOOLER, TERMINAL, and WRITE programs supplied with Windows also use the timer. Here are some uses for the Windows timer, some obvious and some maybe not so obvious:

- Keeping time—Both the CLOCK and CONTROL programs that come with Windows display the current time. The timer tells the programs when to update the clock.
 The DIGCLOCK program described later in this chapter uses the timer to display a digital clock.
- Maintaining an updated status report—The FREEMEM program shown in this
 chapter uses the timer to display available memory in Windows. The display is
 updated every second.
- Waking up—The Windows CALENDAR program uses the timer to trigger a preset alarm.
- Multitasking—Windows is a nonpreemptive multitasking environment, and it is
 important that programs return control to Windows as quickly as possible. If a
 program must do a large amount of processing, it can divide the job into smaller
 pieces and process each piece on receipt of a WM_TIMER message.

- Implementing an "autosave" feature—The timer can prompt a Windows program
 to save a user's work to disk whenever a specified amount of time has elapsed.
- Pacing movement—Graphical objects in a game or successive displays in a computer-assisted instruction program may need to proceed at a set rate. Using the timer eliminates the inconsistencies that might result from variations in microprocessor speed.
- Terminating demonstration versions of programs—Some demonstration versions
 of programs are designed to terminate, say, 30 minutes after they begin. The timer
 can signal such applications when the time is up.
- Using serial or parallel communications—Unlike most other input devices in Windows, serial or parallel communications ports do not generate messages.
 Rather, these programs must poll for input, and the timer can tell them when to do so. (An alternative to using the timer for polling involves a message loop built around the *PeekMessage* call. This technique is discussed in Chapter 16.)

This chapter also explores topics that extend beyond the timer to other areas of Windows programming. Foremost among these topics is that of "call-back" functions. To the uninitiated, these important functions might seem to work in mysterious ways, and the timer is not the only place you will encounter them. This chapter also discusses what to do when a program cannot gain access to a timer—a problem that occurs because Windows maintains only a limited number of timers. Solving this problem is fundamental to working with the Windows timer, but the method presented here can also be applied to error handling in other programs. Finally, the sample programs shown here deal with such decidedly nontimer issues as forcing an application to be loaded as an icon, obtaining the amount of free memory available in Windows, and using the WIN.INI file to obtain information about international time and date formats.

TIMER BASICS

You can allocate a timer for your Windows program by calling the *SetTimer* function. *Set-Timer* includes a parameter specifying an interval that can range (in theory) from 1 msec (millisecond) to 65,535 msec, or about 65.5 seconds. The value indicates the rate at which Windows sends your program WM_TIMER messages. For instance, an interval of 1000 msec causes Windows to send your program a WM_TIMER message every second.

When your program is done using the timer, it calls the *KillTimer* function to stop the timer messages. You can program a "one-shot" timer by calling *KillTimer* during the processing of the WM_TIMER message. The *KillTimer* call purges the message queue of any pending WM_TIMER messages. Your program will never receive a stray WM_TIMER message following a *KillTimer* call.

As you've undoubtedly learned from experimenting with loading multiple instances of CLOCK, Windows allows only 16 timers to be active at any one time. If all 16 timers are already allocated, *SetTimer* returns NULL. Windows programs that use a timer must include some way to deal with this problem.

SYSTEM.DRV and the Windows Timer

For the IBM PC and compatibles, the Windows timer is a relatively simple extension of the timer logic built into the computer's hardware and ROM BIOS. The PC's ROM BIOS initializes an Intel 8259 timer chip to generate the hardware Interrupt 08H. This interrupt is sometimes called the "clock tick" or "timer tick" interrupt. In the PC, an Interrupt 08H occurs every 54.925 msec, or about 18.2 times per second. Among other purposes, the PC's BIOS uses Interrupt 08H to update a "time-of-day" value stored in the BIOS data area. MS-DOS uses this value to calculate the current time.

The SYSTEM.DRV driver in Windows handles hardware timer interrupts. SYSTEM.DRV sets a new Interrupt 08H vector address during initialization and restores the original vector address before Windows terminates. The Interrupt 08H routine within SYSTEM.DRV calls the original Interrupt 08H handler before doing its own processing so that underlying system functions that require this interrupt will continue to work normally.

The SYSTEM.DRV driver has six exported functions, but none of them are directly available to Windows applications. The SetTimer and KillTimer functions are instead part of the USER module. When SYSTEM.DRV receives an Interrupt 08H, it calls a routine within USER that decrements counters for each timer set by Windows applications. When a counter reaches 0, USER places a WM_TIMER message in that application's message queue and resets the counter to the original value.

Because a Windows application retrieves WM_TIMER messages from the normal message queue, you never have to worry about your program being "interrupted" by a sudden WM_TIMER message while doing other processing. In this way, the timer is similar to the keyboard and mouse: The driver handles the asynchronous hardware interrupt events, and Windows translates these events into orderly, structured messages.

SYSTEM.DRV does not attempt to reprogram the 8259 timer chip in the IBM PC. The Windows timer has the same 54.925 msec resolution as the underlying PC timer. This fact has two important implications:

- A Windows application cannot receive WM_TIMER messages at a rate faster than about 18.2 times per second when using a single timer.
- The time interval you specify in the SetTimer call is always rounded down to an
 integral multiple of clock ticks. For instance, a 1000-msec interval divided by 54.925
 msec is 18.207 clock ticks, which is rounded down to 18 clock ticks, which is really
 a 989-msec interval. For intervals less than 55 msecs, each clock tick generates a
 single WM_TIMER message.

Timer Messages Are Not Asynchronous

Non-Windows programs written for the IBM PC and compatibles can use the timer tick interrupt by intercepting Interrupt 08H or Interrupt 1CH (a software interrupt called by the BIOS Interrupt 08H handler). When the hardware interrupt occurs, the program currently running is suspended, and control passes to the interrupt handler. When the interrupt handler is done, it passes control back to the interrupted program.

Like the hardware keyboard and mouse interrupts, the hardware timer tick interrupt is sometimes called an asynchronous interrupt because it occurs randomly with respect to the program that it interrupts. (Actually, the term *isochronous* is more accurate than *asynchronous* for a timer interrupt because the interrupts occur at equal intervals. But the interrupts are still asynchronous with respect to other processing.)

Although the SYSTEM.DRV driver also handles asynchronous Interrupt 08H clock ticks, the WM_TIMER messages that Windows sends to applications are not asynchronous. The WM_TIMER messages are placed in the normal message queue and ordered with all the other messages. Therefore, if you specify 1000 msecs in the SetTimer call, your program is not guaranteed to receive a WM_TIMER message every second or even (as I mentioned above) every 989 msecs. If another application is busy for more than a second, your program will not get any WM_TIMER messages during that time. Only when the other application yields control to Windows (by calling GetMessage, PeekMessage, or WaitMessage) will your program retrieve its next WM_TIMER message from the queue.

You can easily demonstrate this to yourself with the CLOCK program included with Windows or with the sample programs shown in this chapter. If another program has a long paint job and does not immediately relinquish control, CLOCK will stop. When CLOCK regains control, it will jump ahead to the correct time. In fact, Windows handles WM_TIMER messages much like WM_PAINT messages. Both these messages are low priority. If a program's message queue contains only WM_PAINT or WM_TIMER messages, and another program's message queue contains messages other than WM_PAINT or WM_TIMER, Windows will pass control to the other application.

The WM_TIMER messages are similar to WM_PAINT messages in another respect: Windows does not keep loading up the message queue with multiple WM_TIMER messages. Instead, Windows combines several WM_TIMER messages in the message queue into a single message. Therefore, the application won't get a bunch of them all at once, although it may get two WM_TIMER messages in quick succession. An application cannot determine the number of "missing" WM_TIMER messages that result from this process.

When CLOCK regains control and jumps ahead to the correct time, it is not because it gets several WM_TIMER messages in a row. CLOCK must determine the actual time and then set itself. The WM_TIMER messages only inform CLOCK when it should be updated. A program can't keep time itself solely by counting WM_TIMER messages. (Later in this chapter we will write a clock application that updates every second, and we'll see precisely how this is accomplished.)

For convenience, I'll be talking about the timer in terms like "getting a WM_TIMER message every second." But keep in mind that these messages are not precise clock tick interrupts.

USING THE TIMER: THREE METHODS

If you need a timer for the entire duration of your program, you'll probably call SetTimer from the WinMain function or while processing the WM_CREATE message and KillTimer in response to a WM_DESTROY message. Setting the timer in WinMain provides the easiest error handling if a timer is unavailable. You can use a timer in one of three ways, depending on the parameters to the SetTimer call.

Method One

This method, the easiest, causes Windows to send WM_TIMER messages to the normal window function of the application. The SetTimer call looks like this:

```
SetTimer (hWnd, 1, wMsecInterval, NULL) ;
```

The first parameter is a handle to the window whose window function will receive the WM_TIMER messages. The second parameter is the timer ID, which should be a nonzero number. I have arbitrarily set it to 1. The third parameter is a WORD (16-bit unsigned integer) that specifes an interval in milliseconds. The largest value (65535) will deliver a WM_TIMER message about once a minute.

You can stop the WM_TIMER messages at any time (even while processing a WM_TIMER message) by calling:

```
KillTimer (hWnd, 1);
```

The second parameter is the same timer ID used in the SetTimer call. You should kill any active timers in response to a WM_DESTROY message before your program terminates.

When your window function receives a WM_TIMER message, wParam is equal to the timer ID (which in the above case is simply 1) and IParam is 0. If you need to set more than one timer, use different timer IDs for each timer. The value of wParam will differentiate the WM_TIMER messages passed to your window function. To make your program more readable, you may want to use #define statements for the different timer IDs:

```
#define TIMER_SEC 1
#define TIMER_MIN 2
```

You can then set the two timers with two SetTimer calls:

```
SetTimer (hWnd, TIMER_SEC, 1000, NULL);
SetTimer (hWnd, TIMER_MIN, (WORD) 60000, NULL);
```

The WM_TIMER logic might look something like this:

If you want to set an existing timer to a different elapsed time, kill the timer and call Set-Timer again. This code assumes the timer ID is 1:

```
KillTimer (hWnd, 1) ;
SetTimer (hWnd, 1, wMsecInterval, NULL) ;
```

The wMsecInterval parameter is the new elapsed time in milliseconds. The Windows CLOCK application uses this method to change the timer from 1000 msecs to 60,000 msecs when it becomes an icon. As an icon, CLOCK needs to update the clock every minute rather than every second. When it is expanded from an icon to a window, CLOCK changes the timer back to 1000 msecs.

Dealing with no available timers

Windows allows only 16 timers to be active at any time. If no timer is available, SetTimer returns NULL. Your program might be able to function reasonably without the timer, but if you need the timer (as CLOCK certainly does), the application has no choice but to terminate if it can't get one. If you call SetTimer in WinMain, you can terminate the program simply by returning FALSE from WinMain.

Let's assume you want a 1000 msec timer. Following the *CreateWindow* call but before the message loop, you might have a statement like this:

```
if (!SetTimer (hWnd, 1, 1000, NULL))
    return FALSE;
```

This is the unfriendly way to terminate. The user is left wondering why the application will not load. (Surely the 16 clocks sitting down in the icon area have nothing to do with it!) It's much friendlier—and fairly easy—to use a Windows message box for displaying a message. A complete discussion of messages boxes awaits you in Chapter 11, but this will get you started.

A message box is a popup window that always appears in the center of the display. Message boxes have a caption bar but no close box or size box. The caption bar usually contains the name of the application. The message box encloses a message and one, two, or three buttons (some combination of OK, Retry, Cancel, Yes, No, and some others). The message box can also contain a predefined icon: an asterisk, an exclamation point, a question mark, or a hand signaling "stop." You have probably seen plenty of message boxes when working with Windows.

This code creates an informatory message box that you can use when SetTimer fails to allocate a timer:

```
if (!SetTimer (hWnd, 1, 1000, NULL))
{
    MessageBox (hWnd,
        "Too many clocks or timers!",
        "Program Name",
        MB_ICONEXCLAMATION | MB_OK);
    return FALSE;
}
```

The message box is shown in Figure 6-1. When the user presses Enter or clicks the OK button, WinMain terminates by returning FALSE.




Figure 6-1. A message box for "friendly termination"

By default, message boxes are "application modal" windows. This means that a user must respond to the message box before the application will continue. However, the user can switch to other applications by pressing Alt-Tab or Alt-Esc or by clicking the mouse in the window of another program.

Why not give the user the opportunity to close one of those 16 minimized clocks at the bottom of the display and successfully load your application? That's what this code does:

This message box, shown in Figure 6-2 (on the following page), has two buttons labeled Retry and Cancel. If the user selects Cancel, the *MessageBox* function returns a value equal to IDCANCEL, and the program terminates. If the user selects Retry, *SetTimer* is called again.




Figure 6-2. A message box that offers a choice

A sample program

Figure 6-3 shows a sample program that uses the timer. This program, called BEEPER1, does nothing but beep every second by calling the function *MessageBeep*. (Although *MessageBeep* is documented as a companion to *MessageBox*, it's really an all-purpose beep function. The *WORD* parameter to *MessageBeep* can be any value.)

```
beeperl.obj : beeperl.c
cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp beeperl.c
beeperl.exe : beeperl.obj beeperl.def
link4 beeperl, /align:16, /map, slibw, beeperl
```

```
/* BEEPER1.C -- Timer Demo Program No. 1 */
#include <windows.h>
long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG) ;
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
     HANDLE
               hInstance, hPrevInstance;
     LPSTR
                 lpszCmdLine ;
               nCmdShow ;
     int
     static char szAppName [] = "Beeperl" ;
                 hWnd ;
     MSG
                 msg ;
     WNDCLASS
                 wndclass ;
     if (!hPrevInstance)
                                  = CS HREDRAW | CS VREDRAW ;
          wndclass.style
          wndclass.lpfnWndProc
                                  = WndProc ;
          wndclass.cbClsExtra
                                  = 0 ;
          wndclass.cbWndExtra
                                = 0 ;
          wndclass.hInstance
                                  = hInstance ;
          wndclass.hIcon = LoadIcon (NULL, IDI_APPLICATION) ;
wndclass.hCursor = LoadCursor (NULL, IDC_ARROW) ;
          wndclass.hbrBackground = GetStockObject (WHITE_BRUSH)
          wndclass.lpszMenuName = NULL ;
          wndclass.lpszClassName = szAppName ;
```

Figure 6-3. The BEEPER1 program

Figure 6-3. Continued

```
if (!RegisterClass (&wndclass))
               return FALSE ;
     hWnd = CreateWindow (szAppName, "Beeperl Timer Demo",
                          WS OVERLAPPEDWINDOW,
                          CW USEDEFAULT, 0,
                          CW USEDEFAULT, 0,
                          NULL, NULL, hInstance, NULL) ;
     while (!SetTimer (hWnd, 1, 1000, NULL))
          if (IDCANCEL == MessageBox (hWnd,
                               "Too many clocks or timers!", szAppName,
                               MB ICONEXCLAMATION | MB RETRYCANCEL) )
               return FALSE ;
     ShowWindow (hWnd, nCmdShow);
     UpdateWindow (hWnd) ;
     while (GetMessage (&msg, NULL, 0, 0))
          TranslateMessage (&msg) ;
          DispatchMessage (&msg) ;
     return msg.wParam ;
long FAR PASCAL WndProc (hWnd, iMessage, wParam, lParam)
     HWND
             hWnd ;
     unsigned iMessage ;
     WORD
           wParam ;
     LONG
              lParam ;
     switch (iMessage)
          case WM TIMER:
               MessageBeep (0) ;
               break ;
          case WM_DESTROY:
               KillTimer (hWnd, 1) ;
               PostQuitMessage (0) ;
               break ;
          default:
               return DefWindowProc (hWnd, iMessage, wParam, 1Param) ;
     return OL ;
```

```
NAME
               BEEPER1
DESCRIPTION
               'Timer Demo Program No. 1 (C) Charles Petzold, 1987'
               'WINSTUB.EXE'
STUB
CODE
               MOVEABLE
               MOVEABLE MULTIPLE
DATA
HEAPSIZE
               1024
STACKSIZE
               4096
EXPORTS
               WndProc
```

Because BEEPER1 audibly indicates every WM_TIMER message it receives, you can get a good idea of the erratic nature of WM_TIMER messages by loading BEEPER1 and performing some other actions within Windows. For instance, try moving or resizing a window. This stops all messages, and BEEPER1 stops beeping. When you complete the move or resize, you'll note that BEEPER1 doesn't get all the WM_TIMER messages it has missed, although the first two messages may be less than a second apart.

Method Two

The first method for setting the timer causes WM_TIMER messages to be sent to the normal window function. With this second method, you can direct Windows to send the timer messages to another function within your program.

The function that will receive these timer messages is termed a "call-back" function. This is a function within your program that is called by Windows. You tell Windows the address of this function (well, not really the address of the function, but we'll get to that), and Windows later calls the function. This should sound familiar, because a program's window function is really a type of call-back function. You tell Windows the address of the function when registering the window class, and Windows calls the function when sending messages to the program. However, call-back functions that are not window functions must be handled a little differently.

SetTimer is not the only Windows function that uses a call-back function. The CreateDialog and DialogBox functions (discussed in Chapter 11) use call-back functions to process messages in a dialog box; several Windows functions (EnumChildWindows, EnumFonts, EnumObjects, EnumProps, and EnumWindows) pass enumerated information to call-back functions; and several less commonly used functions (GrayString, LineDDA, LocalNotify, SetResourceHandler, and SetWindowsHook) also require call-back functions. Call-back functions are often a major hang-up for beginning Windows programmers. Some strange things are involved. I'm first going to tell you how to use call-back functions, and then I'll tell you the reasons for what you're doing.

Like a window function, a call-back function must be defined as FAR PASCAL because it is called by Windows from outside the code segment of the program. The parameters to the call-back function and the value returned from the call-back function depend on the purpose of the call-back function. In the case of the call-back function associated with the timer, the input parameters are the same as the input parameters to a window function. The timer call-back function does not need to return a value to Windows.

Let's name the call-back function *TimerProc*. (You can name it anything you like.) It will process only WM_TIMER messages.

The hWnd input parameter is the handle to the window specified when you call SetTimer. Windows will send only WM_TIMER messages to TimerProc, so iMessage will always equal WM_TIMER. The wParam value is the timer ID, and the lParam value can be ignored. (It is set to the address of the function.)

Just as you must include your regular window function in the EXPORTS section of the module definition (.DEF) file, you must also include the names of any call-back functions within your program. When using a call-back function named *TimerProc*, your module definition file contains the following lines:

```
EXPORTS WndProc
TimerProc
```

As I noted earlier, the first method for setting a timer requires a SetTimer call that looks like this:

```
SetTimer (hWnd, 1, wMsecInterval, NULL) ;
```

When you use a call-back function to process WM_TIMER messages, the fourth parameter to SetTimer is instead the far address of the call-back function.

But not really.

Now listen carefully: The far address that you must pass to Windows as the fourth parameter of the SetTimer call is not the address of the function within the program. It is instead a far address obtained from the Windows function MakeProcInstance. To use MakeProcInstance, first define a variable that is a far pointer to a function. You can use the WINDOWS.H identifier FARPROC for this definition:

```
FARPROC lpfnTimerProc ;
```

In WinMain (or any other section of your program that is executed only once for each instance), call MakeProcInstance. The parameters to MakeProcInstance are the address of TimerProc and the value of hInstance. MakeProcInstance returns a far pointer that you save in lpfnTimerProc:

```
lpfnTimerProc = MakeProcInstance (TimerProc, hInstance) ;
You can now use this lpfnTimerProc value when you call SetTimer:
```

```
SetTimer (hWnd, 1, wMsecInterval, lpfnTimerProc);
You're done. Now that's not too bad, is it?
```

Well, you may say, "This is so weird that I'll never use this method for setting a timer. I'll use the first method where I don't have to bother with call-back functions." That's fine. But you're going to be forced to deal with call-back functions, EXPORTS, and MakeProcInstance when we start discussing dialog boxes. You can't do a dialog box without them. So you can pay your dues now, or you can pay them later.

A sample program

Let's look at some sample code so you can see how this stuff fits together. Then we'll explore MakeProcInstance some more. The BEEPER2 program, shown in Figure 6-4, is functionally the same as BEEPER1 except that Windows sends the timer messages to TimerProc rather than WndProc. To tell the C compiler that TimerProc is a function so we can use the name of the function when calling MakeProcInstance, we declare TimerProc at the top of the program along with WndProc. Notice that the program calls MakeProcInstance for each instance.

```
beeper2.obj : beeper2.c
cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp beeper2.c
beeper2.exe : beeper2.obj beeper2.def
link4 beeper2, /align:16, /map, slibw, beeper2
```

```
/* BEEPER2.C -- Timer Demo Program No. 2 */
#include <windows.h>
long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG) ;
void FAR PASCAL TimerProc (HWND, unsigned, WORD, LONG) ;
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
    HANDLE hInstance, hPrevInstance;
LPSTR lpszCmdLine;
               nCmdShow ;
     int
     static char szAppName [] = "Beeper2" ;
     FARPROC lpfnTimerProc;
HWND hWnd;
     MSG
                msg ;
     WNDCLASS
                wndclass :
     if (!hPrevInstance)
                                 = CS HREDRAW | CS VREDRAW ;
          wndclass.style
          wndclass.lpfnWndProc
                                = WndProc ;
          wndclass.cbClsExtra
                                 = 0 :
          wndclass.cbWndExtra = 0;
          wndclass.hInstance
                                 = hInstance ;
                               = LoadIcon (NULL, IDI_APPLICATION) ;
          wndclass.hIcon
```

Figure 6-4. The BEEPER2 program

Figure 6-4. Continued

```
wndclass.hCursor = LoadCursor (NULL, IDC ARROW) ;
          wndclass.hbrBackground = GetStockObject (WHITE BRUSH) ;
          wndclass.lpszMenuName = NULL ;
          wndclass.lpszClassName = szAppName ;
          if (!RegisterClass (&wndclass))
               return FALSE ;
     hWnd = CreateWindow (szAppName, "Beeper2 Timer Demo", WS_OVERLAPPEDWINDOW,
                          CW USEDEFAULT, 0,
                          CW USEDEFAULT, 0,
                          NULL, NULL, hInstance, NULL) ;
     lpfnTimerProc = MakeProcInstance (TimerProc, hInstance) ;
     while (!SetTimer (hWnd, 1, 1000, lpfnTimerProc))
   if (IDCANCEL == MessageBox (hWnd,
                               "Too many clocks or timers!", szAppName,
                               MB ICONEXCLAMATION | MB RETRYCANCEL))
               return FALSE :
     ShowWindow (hWnd, nCmdShow) ;
     UpdateWindow (hWnd) ;
     while (GetMessage (&msg, NULL, 0, 0))
          TranslateMessage (&msg) ;
          DispatchMessage (&msg) ;
     return msg.wParam ;
void FAR PASCAL TimerProc (hWnd, iMessage, wParam, 1Param)
     HWND
              hWnd ;
     unsigned iMessage ;
     WORD
            wParam ;
     LONG
              lParam ;
     MessageBeep (0) ;
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
              hWnd ;
     HWND
     unsigned iMessage ;
     WORD
            wParam ;
     LONG
              lParam ;
     switch (iMessage)
          case WM DESTROY:
                KillTimer (hWnd, 1) ;
                PostQuitMessage (0) ;
               break ;
          default:
               return DefWindowProc (hWnd, iMessage, wParam, lParam) ;
     return OL ;
```

Figure 6-4. Continued

NAME BEEPER2 DESCRIPTION 'Timer Demo Program No. 2 (C) Charles Petzold, 1987' 'WINSTUB.EXE' STUB MOVEABLE CODE MOVEABLE MULTIPLE DATA HEAPSIZE 1024 4096 STACKSIZE EXPORTS WndProc TimerProc

I mentioned above that the *lParam* value passed to *TimerProc* is the address of the *TimerProc* function. Not exactly. It is actually the value of *lpfnTimerProc* returned from *MakeProcInstance*, if you ever need to use it.

Proper handling of call-back functions

Let's summarize the three requirements for call-back functions. This is particularly important because the Windows documentation is often hazy on these three requirements. Sometimes the documentation mentions one or two of the rules but not all three. Any function within your program that is called by Windows must be handled as follows:

- 1. The function must be defined as FAR PASCAL.
- The function must be included in the EXPORTS section of the module definition (DEF) file.
- The address of the function that you give to Windows must be the return value from a MakeProcInstance call. (This third rule does not apply to window functions that are passed to Windows as part of a windows class structure in a RegisterClass call. Windows itself handles the MakeProcInstance requirement in this case.)

As you'll discover in Chapter 8, "Memory Management," these three requirements are closely related to each other. They are part of the overhead necessary for Windows to run several instances of the same program using the same code segment where each instance must have its own data segment. Windows also requires this overhead to move the code segment and the data segments around in memory. Here are the practical results of the three requirements:

 When you define a function as FAR and you compile with the -Gw (Windows) flag, Windows inserts special prolog and epilog code in the function. In assembly language, the prolog code sets the value of the AX register equal to the DS (data segment) register by using the PUSH DS and POP AX instructions. It then saves the value of DS (with PUSH DS) and sets DS equal to AX by using a MOV DS,AX instruction. The epilog code at the end of the function pops the original value of DS off the stack.

- 2. If the FAR function is also exported (that is, if the function is listed in the EXPORTS section of the module definition file), Windows replaces the PUSH DS and POP AX instructions at the top of the function prolog with NOP (no operation) instructions when the code segment is loaded into memory. With this change the function sets DS from the value of AX. But what is the value of AX on entry to the function? Well, if you didn't do anything else, the value of AX would be indeterminate. So would the operation of your program.
- 3. MakeProcInstance creates a small piece of code elsewhere in Windows called a "thunk." The far address returned from MakeProcInstance is the address of this thunk. The thunk loads the segment address of the data segment in AX and branches to the function. The function prolog then loads DS from AX. Perfect.

Note that *MakeProcInstance* requires *hInstance* as a parameter. You must use *MakeProcInstance* to create a different thunk for each instance because each instance has its own data segment. For a particular call-back function, the thunks for each instance all branch to the same function address (because all instances use the same code segment), but each thunk sets AX to a different data segment—the data segment for that instance. When Windows moves a data segment in memory, it must change the thunk for that instance so that the thunk sets AX to the new data segment address. The thunk itself is always in an unmoveable area of memory.

(To further complicate this matter, any reference in your program to a FAR function—such as the address passed to the *MakeProcInstance* call and the address that the thunk branches to—is not even the address of the function within your program. Another small routine sits between the thunk and the actual function. This routine loads the code segment into memory if it has not yet been loaded or if it has been discarded from memory. But let's forget about this for now and come back to it in Chapter 8. The last thing I want to do is make this subject sound as complex as it actually is.)

These requirements imply that you should never call exported far functions directly from within your program. For instance, you might want to simulate a timer message with the following statement:

```
TimerProc (hWnd, WM_TIMER, 1, OL); /* WRONG !!! */
```

It looks OK, but don't do it! The prolog of *TimerProc* will set DS equal to AX, but the value of AX could be anything, and it very likely is not the address of the program's data segment. If

you need to directly call an exported function from within your program, use the far pointer returned from MakeProcInstance:

```
(*lpfnTimerProc) (hWnd, WM_TIMER, 1, OL); /* RIGHT */
```

This code calls the thunk, and the thunk sets AX equal to the correct data segment before branching to the function.

Method Three

The third method of setting the timer is similar to the second method. It requires a far pointer created from *MakeProcInstance* to a function that processes the WM_TIMER messages. However, the *hWnd* parameter to *SetTimer* is set to NULL, and the second parameter (normally the timer ID) is ignored. Instead, the function returns a timer ID:

```
nTimerID = SetTimer (NULL, 0, wMsecInterval, lpfnTimerProc);
```

The nTimerID returned from SetTimer will be NULL if no timer is available.

The first parameter to KillTimer (usually the window handle) must also be NULL. The timer ID must be the value returned from SetTimer:

```
KillTimer (NULL, nTimerID) ;
```

The hWnd parameter passed to the TimerProc timer function will also be NULL. The wParam parameter is the timer ID, and lParam is lpfnTimerProc, the same as in the second method.

This method for setting a timer is rarely used. It might come in handy if you do a lot of SetTimer calls at different times in your program and don't want to keep track of which timer IDs you've already used.

Now that you know how to use the Windows timer, you're ready for a couple of useful timer programs.

USING THE TIMER FOR A STATUS REPORT

One use of a Windows timer is to periodically update a status report displayed on the screen. The program can relinquish control until the next WM_TIMER message and thus not hog precious processing time. The FREEMEM program, shown in Figure 6-5, displays the amount of free memory available in Windows. The free memory value is updated every second and is consistent with the figure shown in the MS-DOS Executive's About box. FREEMEM can give you an idea how close Windows is to running out of memory. While testing a new Windows program, you may want to keep an eye on FREEMEM for a rough indication of how your program is allocating and freeing memory.

```
freemem.obj : freemem.c
cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp freemem.c
freemem.exe : freemem.obj freemem.def
link4 freemem, /align:16, /map, slibw, freemem
```

```
/* FREEMEM.C -- Free Memory Display Program */
#include <windows.h>
#include <stdlib.h>
#include <string.h>
long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG) ;
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
    HANDLE
              hInstance, hPrevInstance ;
                 lpszCmdLine ;
     LPSTR
     int
                nCmdShow ;
     static char szAppName [] = "FreeMem" ;
    HDC
                hDC ;
     HWND
                hWnd ;
    MSG
                 msg ;
    TEXTMETRIC tm ;
    WNDCLASS
                wndclass ;
    if (hPrevInstance)
         return FALSE ;
    wndclass.style
                           = CS HREDRAW | CS VREDRAW;
    wndclass.lpfnWndProc = WndProc ;
    wndclass.cbClsExtra
                           = 0 ;
    wndclass.cbWndExtra
                           = 0 ;
    wndclass.hInstance
                           = hInstance ;
    wndclass.hIcon
                           = NULL ;
                           = LoadCursor (NULL, IDC ARROW) ;
    wndclass.hCursor
    wndclass.hbrBackground = GetStockObject (WHITE BRUSH) ;
    wndclass.lpszMenuName = NULL ;
    wndclass.lpszClassName = szAppName ;
    if (!RegisterClass (&wndclass))
         return FALSE :
    hWnd = CreateWindow (szAppName, szAppName,
                         WS OVERLAPPEDWINDOW,
                         CW USEDEFAULT, 0,
                         CW USEDEFAULT, 0,
                         NULL, NULL, hinstance, NULL) ;
    hDC = GetDC (hWnd) ;
    GetTextMetrics (hDC, &tm) ;
    ReleaseDC (hWnd, hDC) ;
    if (4 * tm.tmAveCharWidth > GetSystemMetrics (SM CXICON) ||
              2 * tm.tmHeight > GetSystemMetrics (SM_CYICON))
```

Figure 6-5. The FREEMEM program

Figure 6-5. Continued

```
MessageBox (hWnd, "Icon size too small for display!",
                          szAppName, MB ICONEXCLAMATION | MB OK) ;
          return FALSE ;
    if (!SetTimer (hWnd, 1, 1000, NULL))
          MessageBox (hWnd, "Too many clocks or timers!",
szAppName, MB_ICONEXCLAMATION | MB_OK);
          return FALSE ;
     ShowWindow (hWnd, SW_SHOWMINNOACTIVE) ;
    UpdateWindow (hWnd) ;
    while (GetMessage (&msg, NULL, 0, 0))
          TranslateMessage (&msg) ;
          DispatchMessage (&msg) ;
     return msg.wParam ;
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
                hWnd ;
     unsigned
                 iMessage ;
                 wParam ;
     WORD
     LONG
                 1Param ;
     static RECT rect ;
     static WORD wFreeMem, wPrevMem;
char cBuffer [20];
     HDC
                 hDC :
     PAINTSTRUCT ps :
     switch (iMessage)
          case WM TIMER:
               wFreeMem = (WORD) (GlobalCompact (OL) / 1024) ;
                if (wFreeMem != wPrevMem)
                     InvalidateRect (hWnd, NULL, TRUE) ;
                wPrevMem = wFreeMem ;
                break ;
          case WM SIZE:
                GetClientRect (hWnd, &rect) ;
               break ;
          case WM PAINT:
                hDC = BeginPaint (hWnd, &ps) ;
                DrawText (hDC, cBuffer,
                     strlen (strcat (itoa (wFreeMem, cBuffer, 10), "K Free")),
                     &rect, DT WORDBREAK) ;
                EndPaint (hWnd, &ps) ;
                break ;
          case WM QUERYOPEN:
               break :
```

Figure 6-5. Continued

```
case WM_DESTROY:
    KillTimer (hWnd, 1) ;
    PostQuitMessage (0) ;
    break ;

default:
    return DefWindowProc (hWnd, iMessage, wParam, 1Param) ;

return OL ;
)
```

```
NAME
             FREEMEM
DESCRIPTION
             'Free Memory Display (C) Charles Petzold, 1987'
STUB
             'WINSTUB.EXE'
CODE
            MOVEABLE
DATA
             MOVEABLE MULTIPLE
HEAPSIZE
             1024
             4096
STACKSIZE
EXPORTS
             WndProc
```

Because FREEMEM doesn't need much display space, I've written it to appear as an icon at the bottom of the Windows screen. (See Figure 6-6.) This is about as unobtrusive a window as you can create in Windows.




Figure 6-6. The FREEMEM icon

Although FREEMEM's use of the timer is simple enough, the program illustrates some interesting tricks that admittedly have nothing to do with the timer.

Creative Use of Icons

Unlike most Windows programs, FREEMEM starts out life as an icon, displays everything it needs to display within the icon, and cannot be opened into a regular window. Most Windows applications have static pictorial icons that you specify in the windows class structure. These icons are usually created with the ICONEDIT utility supplied with the Windows Software Development Kit (as you'll see in Chapter 9). So far, we have been using predefined Windows icons in our programs. Alternatively, you can specify a NULL icon in the window class structure by the statement:

```
wndclass.hIcon = NULL ;
```

A NULL icon means that the application is responsible for drawing the icon. Windows sends the application WM_PAINT messages when the icon needs to be painted. Thus a program can change the appearance of the icon while the program is running. The CLOCK application included with Windows uses this technique to display the clock even when the window is an icon. A NULL icon is really just a tiny window that you can draw on in the same way that you draw on the client area of a normal window. If you need to know when your application is becoming an icon, you can get the information from the wParam parameter of a WM_SIZE message. For instance, when CLOCK becomes an icon, it eliminates the second hand from the clock and changes the timer from a 1-second interval to a 1-minute interval.

FREEMEM displays two lines of four-character text within its icon. This will work fine on the most common displays used for Windows, such as the CGA, EGA, and Hercules Graphics Card. However, some higher-resolution displays may have larger system fonts but a 32-by-32-pixel icon size. Because FREEMEM cannot display correctly on these video boards, it checks the size of the system font against the icon size and uses a message box to inform the user if the icon size is too small.

Forcing the Icon

Shortly before entering the message loop in WinMain, most Windows applications execute the function:

```
ShowWindow (hWnd, nCmdShow);
```

The nCmdShow variable is passed to the program as a parameter to WinMain.

If you run a program from the MS-DOS Executive (by selecting Run from the File menu, pressing Enter when the cursor is on the program name, or double-clicking the program), nCmdShow is set equal to SW_SHOWNORMAL. If you load an application as an icon (by selecting Load from the File menu or pressing Shift-Enter with the cursor on the program name), nCmdShow is set equal to SW_SHOWMINNOACTIVE. Your application usually doesn't have to figure this out but simply passes this parameter to ShowWindow.

However, you aren't required to use the nCmdShow variable with ShowWindow. Instead, FREEMEM uses the line:

```
ShowWindow (hWnd, SW_SHOWMINNOACTIVE) ;
```

This forces the window to appear as an icon regardless of the value of *nCmdShow*. The currently active program remains active.

You can perform other tricks with this technique. If you always want a particular application to appear first as a maximized full-screen display, you can use:

```
ShowWindow (hWnd, SW_SHOWMAXIMIZED) ;
```

You can even force FREEMEM to occupy a particular icon position at the bottom of the display. If you replace the existing *ShowWindow* call in FREEMEM with:

```
ShowWindow (hWnd, (int) 0xFF8F);
```

the icon will be positioned in icon slot 15. This syntax is a little obscure but is documented in the Programmer's Reference.

Keeping the Icon an Icon

FREEMEM does not allow itself to be opened into a regular window. Would you believe this trick requires merely two simple lines in the *WndProc* function? Here they are:

```
case WM_QUERYOPEN:
    break ;
```

These two lines don't seem to be doing very much, but let's take a closer look.

Windows sends a WM_QUERYOPEN message to a program when it wants to open an icon into a window. Normally, WM_QUERYOPEN is passed on to the *DefWindowProc* function, which returns a nonzero value; Windows then opens the icon. With the two lines shown above, however, *WndProc* returns a value of 0 for a WM_QUERYOPEN message. So when Windows asks, "Do you want to be opened?" *WndProc* answers "Zero," which in this case means "No thanks."

Calculating Free Memory

When Windows sends FREEMEM a WM_TIMER message, FREEMEM must determine the amount of free memory. Like the About box in the MS-DOS Executive, FREEMEM gets a free memory value by calling *GlobalCompact* with a parameter of 0. Windows applications normally use *GlobalCompact* to generate free memory from the global heap. If you pass *GlobalCompact* a parameter of 0, Windows will compact memory (that is, move blocks of memory to consolidate free memory space) and return the size of the largest block of contiguous free memory. This is memory that a Windows application can get from the global heap if it needs it. (Windows memory management is covered in detail in Chapter 8.)

If the free memory value has changed since the last GlobalCompact call, FREEMEM invalidates the client area to generate a WM_PAINT message. FREEMEM processes WM_PAINT messages by calling DrawText, a convenient function for simple word-wrapped text. Note that the line within the DrawText code that reads:

```
strlen (strcat (itoa (wFreeMem, cBuffer, 10), "K Free"))
```

accomplishes the same task as the more common construction:

```
sprintf (cBuffer, "% dK Free", wFreeMem)
```

However, *sprintf* is a big function. By using *strlen*, *strcat*, and *itoa* instead, we can reduce the size of FREEMEM.EXE by about 3 KB. (Yes, every little bit helps.)

USING THE TIMER FOR A CLOCK

A clock is the most obvious application for the timer. Although digital clocks were once in fashion, the pendulum has swung back (so to speak) to analog clocks. But you already have an analog clock with Windows. So I'm going to buck the trend and write a good old digital clock program instead. The DIGCLOCK program, shown in Figure 6-7, creates a popup window that positions itself in the lower right corner of the display in the icon area. The program displays the day of the week, the time, and the date, as shown in Figure 6-8 (on page 221).

```
digclock.obj : digclock.c
cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp digclock.c
digclock.exe : digclock.obj digclock.def
link4 digclock, /align:16, /map, slibw, digclock
```

```
/* DIGCLOCK.C -- Digital Clock Program */
#include <windows.h>
#include <stdio.h>
#include <time.h>
#define YEAR (datetime->tm year % 100)
#define MONTH (datetime->tm_mon + 1)
#define MDAY (datetime->tm mday)
#define WDAY (datetime->tm wday)
#define HOUR (datetime->tm_hour)
#define MIN
              (datetime->tm min)
#define SEC (datetime->tm sec)
long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG);
void SizeTheWindow (short *, short *, short *, short *);
char sDate [2], sTime [2], sAMPM [2][5];
     iDate, iTime ;
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
     HANDLE hInstance, hPrevInstance;
     LPSTR
                lpszCmdLine;
                nCmdShow;
     static char szAppName [] = "DigClock" ;
     HWND
                hWnd:
     MSG
                msq:
     short
                xStart, yStart, xClient, yClient ;
     WNDCLASS wndclass;
     if (!hPrevInstance)
                            = CS_HREDRAW | CS_VREDRAW;
          wndclass.style
          wndclass.lpfnWndProc = WndProc;
wndclass.cbClsExtra = 0;
```

Figure 6-7. The DIGCLOCK program

Figure 6-7. Continued

```
wndclass.cbWndExtra = 0;
          wndclass.hInstance = hInstance;
wndclass.hIcon = NULL;
wndclass.hCursor = LoadCursor (NULL, IDC_ARROW);
           wndclass.hbrBackground = GetStockObject (WHITE BRUSH) ;
           wndclass.lpszMenuName = NULL ;
           wndclass.lpszClassName = szAppName ;
           if (!RegisterClass (&wndclass))
                return FALSE;
     SizeTheWindow (&xStart, &yStart, &xClient, &yClient) ;
     hWnd = CreateWindow (szAppName, szAppName, WS_POPUP | WS_DLGFRAME | WS_SYSMENU,
                           xStart, yStart, xClient, yClient,
                            NULL, NULL, hInstance, NULL) ;
     if (!SetTimer (hWnd, 1, 1000, NULL))
           MessageBox (hWnd, "Too many clocks or timers!", szAppName,
                           MB_ICONEXCLAMATION | MB OK) ;
           return FALSE ;
     ShowWindow (hWnd, SW SHOWNOACTIVATE) ;
     UpdateWindow (hWnd);
     while (GetMessage (&msg, NULL, 0, 0))
           TranslateMessage (&msg) ;
           DispatchMessage (&msg) ;
     return msg.wParam;
void SizeTheWindow (pxStart, pyStart, pxClient, pyClient)
                 *pxStart, *pyStart, *pxClient, *pyClient;
                 hDC ;
     HDC
     TEXTMETRIC tm ;
     hDC = CreateIC ("DISPLAY", NULL, NULL, NULL) ;
     GetTextMetrics (hDC, &tm) ;
     DeleteDC (hDC) ;
     *pxClient = 2 * GetSystemMetrics (SM_CXDLGFRAME) + 16*tm.tmAveCharWidth ;
     *pxStart = GetSystemMetrics (SM CXSCREEN) - *pxClient;
*pyClient = 2 * GetSystemMetrics (SM CYDLGFRAME) + 2*tm.tmHeight;
     *pyStart =
                      GetSystemMetrics (SM CYSCREEN)
                                                             - *pyClient ;
void SetInternational ()
     static char cName [] = "intl" ;
     iDate = GetProfileInt (cName, "iDate", 0) ;
     iTime = GetProfileInt (cName, "iTime", 0) ;
```

Figure 6-7. Continued

```
GetProfileString (CName, "sDate", "/", sDate, 2);
GetProfileString (CName, "sTime", ":", sTime, 2);
GetProfileString (CName, "s1159", "AM", sAMPM [0], 5);
GetProfileString (CName, "s2359", "PM", sAMPM [1], 5);
                                                                    2);
void WndPaint (hWnd, hDC)
                    hWnd ;
      HWND
                     hDC :
      static char szWday [] = "Sun\OMon\OTue\OWed\OThu\OFri\OSat" ;
                   cBuffer [40] ;
      char
                     lTime :
      long
                     rect ;
      RECT
      short
                    nLength ;
      struct tm *datetime ;
      time (&lTime) ;
      datetime = localtime (&lTime) ;
     nLength = sprintf (cBuffer, " %s %d%s%02d%s%02d \r\n", szWday + 4 * WDAY, iDate == 1 ? MDAY : iDate == 2 ? YEAR : MONTH, sDate,
                   iDate == 1 ? MONTH : iDate == 2 ? MONTH : MDAY, sDate, iDate == 1 ? YEAR : iDate == 2 ? MDAY : YEAR) ;
      if (iTime == 1)
             nLength += sprintf (cBuffer + nLength, " %02d%s%02d%s%02d ",
                                HOUR, sTime, MIN, sTime, SEC) ;
      else
             nLength += sprintf (cBuffer + nLength, " %d%s%02d%s%02d %s ", (HOUR % 12) ? (HOUR % 12) : 12,
                                sTime, MIN, sTime, SEC, sAMPM [HOUR / 12]) ;
      GetClientRect (hWnd, &rect) ;
      DrawText (hDC, cBuffer, -1, &rect, DT CENTER | DT NOCLIP) ;
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
                     hWnd;
      HWND
      unsigned
                     iMessage;
      WORD
                      wParam;
      LONG
                      1Param;
      HDC
                     hDC :
      PAINTSTRUCT ps;
      switch (iMessage)
             case WM CREATE :
                    SetInternational () ;
                   break :
             case WM TIMER :
                    InvalidateRect (hWnd, NULL, FALSE) ;
                   break ;
```

Figure 6-7. Continued

```
case WM_PAINT :
    hDC = BeginPaint (hWnd, &ps) ;
    WndPaint (hWnd, hDC) ;
    EndPaint (hWnd, &ps) ;
    break ;

case WM_WININICHANGE :
    SetInternational () ;
    InvalidateRect (hWnd, NULL, TRUE) ;
    break ;

case WM_DESTROY :
    KillTimer (hWnd, 1) ;
    PostQuitMessage (0) ;
    break ;

default:
    return DefWindowProc (hWnd, iMessage, wParam, lParam) ;
    break;

return (OL) ;
}
```

```
NAME
              DIGCLOCK
DESCRIPTION
              'Digital Clock (C) Charles Petzold, 1987'
STUB
             'WINSTUB.EXE'
CODE
              MOVEABLE
DATA
              MOVEABLE MULTIPLE
HEAPSIZE
              1024
STACKSIZE
              4096
EXPORTS
              WndProc
```




Figure 6-8. The DIGCLOCK window

DIGCLOCK has all the peculiarities of popup windows: It remains on the display at all times unless another program is zoomed out to use the full screen or unless another popup window covers it. Watch out, though—DIGCLOCK will even cover up icons.

DIGCLOCK uses yet another variation of the ShowWindow call:

```
ShowWindow (hWnd, SW_SHOWNOACTIVATE) ;
```

Normally, a program becomes the active window when you run it. SW_SHOWNOACTIVATE tells Windows that the program that loaded DIGCLOCK (most probably the MS-DOS Executive) should remain the active window. You can make DIGCLOCK active, however, by clicking on its window with the mouse or by pressing Alt-Tab or Alt-Esc. Although DIGCLOCK has no system menu box, you can still access the system menu when DIGCLOCK is active by pressing Alt-Spacebar. If you select Move, you can move the window with the keyboard.

Positioning and Sizing the Popup

The DIGCLOCK popup window is positioned at the lower right corner of the display. The window must be large enough to accommodate two lines of text of 16 characters each. The SizeTheWindow function in DIGCLOCK.C determines the correct parameters to use in the CreateWindow call. Normally, a program cannot obtain a text size without first creating a window, because it needs the window handle to obtain a device context handle. DIGCLOCK gets around this problem by obtaining an information device context handle for the screen using CreateIC. This function is similar to CreateDC (used in the BLOWUP program in Chapter 5) but is used to obtain information from the device context. The text size in combination with information available from GetSystemMetrics is enough to derive an initial starting position and window size.

Getting the Date and Time

In its WndPaint function, DIGCLOCK uses the time and localtime C functions available in the Microsoft C Compiler library to determine the current date and time. The localtime function puts all the information we need into a structure; several macro definitions near the top of the program help make the sprintf calls more readable. You could also use the MS-DOS Interrupt 21H function calls 2AH and 2CH to obtain the date and time, either through the intdos function included in the Microsoft C Compiler library or through an assembly-language subroutine. This approach would slightly reduce the size of the DIGCLOCK.EXE file.

Going International

Windows includes international support. The WIN.INI file created during installation of Windows contains a section headed *[intl]*. This lists information concerning formats of dates, time, currency, and numbers. You can display dates in one of three different formats: month-day-year, year-month-day, or day-month-year. The separator between these three numbers can be a slash, a dash, a period, or, in fact, any character you like. You can display the time in either 12-hour or 24-hour format; a semicolon or a period is commonly used to separate hours, minutes, and seconds.

The SetInternational function in DIGCLOCK retrieves this formatting information from the WIN.INI file using the Windows GetProfileInt (for integers) and GetProfileString (for strings). These calls must include default values if Windows cannot find the values in WIN.INI. SetInternational stores the values in global variables that have the same names as the text strings that identify them in WIN.INI. The WindPaint function uses the values obtained from WIN.INI to format the date and time displays and then calls DrawText to center the two lines of text within the window.

As you would expect, whenever DIGCLOCK's window function receives a WM_TIMER message, it invalidates the window to generate a WM_PAINT message. But WndProc also invalidates the window when it receives a WM_WININICHANGE message. Any application that changes WIN.INI sends the WM_WININICHANGE message to all active Windows applications. If the [intl] section of WIN.INI is changed, DIGCLOCK will know and will obtain the new international information. To see how this works, load DIGCLOCK, load the CONTROL program included with Windows, select Country Settings from the Preferences menu, and change either the date format, the date separator, the time format, or the time separator. Now press Enter. CONTROL updates the WIN.INI file, and DIGCLOCK's display reflects that change—Windows' message magic at work.

When the window function receives a WM_WININICHANGE message, it invalidates the window using:

InvalidateRect (hWnd, NULL, TRUE) ;

When DIGCLOCK receives a WM_TIMER message, it invalidates the window using:

InvalidateRect (hWnd, NULL, FALSE) ;

A value of TRUE in the last parameter tells Windows to erase the background before drawing the window. A value of FALSE tells Windows simply to draw over the existing background. We use FALSE when processing WM_TIMER messages because this approach reduces flickering of the display. You may wonder why we need to use the TRUE value at all.

A TRUE value is necessary when processing WM_WININICHANGE messages because the length of the displayed strings can change by several characters if you switch the time format from 12 hours to 24 hours. However, the largest change that occurs as a result of a WM_TIMER is two characters—for instance, when the date advances from 12/31/87 to 1/1/88—and the formatted string that WndPaint uses for the display has a blank on each end to account for this change in length.

We could also have DIGCLOCK process WM_TIMECHANGE messages, which notify applications of changes to the system date or time. Because DIGCLOCK is updated every second by WM_TIMER messages, however, this is unnecessary. Processing WM_TIMECHANGE messages would make more sense for a clock that was updated every minute.

WINDOWS STANDARD TIME

If you've been scouting around the Programmer's Reference of the Windows Software Development Kit, you may be wondering why the Windows GetCurrentTime function is not used in DIGCLOCK. The answer is that GetCurrentTime tells you about "Windows time" rather than real time. This is the time (in milliseconds) since the beginning of the current Windows session. GetCurrentTime is used mostly for calculating a difference from the time returned from GetMessageTime. You can use these two calls while processing a message to determine how long the message was in the message queue before you retrieved it for processing.

Chapter 7

Child Window Controls

Chapter 5 introduced a program called CHECKER that displays a grid of rectangles. When you click the mouse in a rectangle, the program draws an X. When you click again, the X disappears. As you played with the program, you may have thought that the rectangle with the X inside looked vaguely familiar. If the rectangle were reduced in size, it would resemble a "check box" that Windows programs use in dialog boxes to allow the selection of options.

Although the CHECKER1 and CHECKER2 versions of this program use only one main window, the CHECKER3 version uses a child window for each rectangle. The rectangles are maintained by a separate window function called *ChildWndProc*. It we wanted to, we could add a facility to *ChildWndProc* to send a message to its parent window function (*WndProc*) whenever a rectangle is checked or unchecked.

Here's how: The child window function determines the window handle of its parent by calling GetParent:

hWndParent = GetParent (hWnd) ;

where hWnd is the window handle of the child window. It then sends a message to the parent window function:

SendMessage (hWndParent, iMessage, wParam, 1Param);

Perhaps for this message the child window could set wParam to its child window ID. The IParam could be set to a 1 if the child window were being checked and a 0 if it were being unchecked.

This in effect creates a "child window control." The child window processes mouse and keyboard messages and notifies the parent window when the child window's state has changed. In this way, the child window becomes an input device for the parent window.

Although you can create your own child window controls, you can also take advantage of several predefined window classes (and window functions) that your program can use to create child window controls. These controls take the form of buttons, check boxes, edit boxes, list boxes, text strings, and scroll bars. For instance, if you want to put a button labeled "Recalculate" in a corner of your spreadsheet program, you can create it with a single *CreateWindow* call. You don't have to worry about the mouse logic or button painting logic or about making the button "flash" when it's clicked. That's all done in Windows. All you have to do is trap WM_COMMAND messages—that's how the button informs your window function when it has been triggered.

Is it really that simple? Well, almost.

Child window controls are used most often in dialog boxes. As you'll see in Chapter 11, the position and size of the child window controls are defined in a dialog box template contained in the program's resource script. However, you can also use predefined child window controls on the surface of an overlapped or popup window's client area. You create each child window with a *CreateWindow* call and adjust the position and size of the child windows with calls to *MoveWindow*. The parent window function sends messages to the child window controls, and the child window controls send messages back to the parent window function.

When you bring up your normal window, you first define a window class and register it with windows using *RegisterClass*. You then create the window based on that class using *CreateWindow*. When you use one of the predefined controls, however, you do not register a window class for the child window. The class already exists within Windows and has one of these names: "button," "static," "scrollbar," "edit," or "listbox." You simply use the name as the window class parameter in *CreateWindow*. The window style parameter to *CreateWindow* defines more precisely the appearance and functionality of the child window control. Windows contains the window functions that process messages to the child windows based on these classes.

Using child window controls directly on the surface of your window involves tasks of a lower level than are required for using child window controls in dialog boxes, where the dialog box manager adds a layer of insulation between your program and the controls themselves. In particular, you'll discover that the child window controls you create on the surface of your window have no built-in facility to move the input focus from one control to another using the Tab or cursor movement keys. A child window control can obtain the input focus, but once it does, it won't relinquish the input focus back to the parent window. This is a problem we'll struggle with throughout this chapter.

THE BUTTON CLASS

We'll begin our exploration of the button window class with a program called BTNLOOK ("button look"), which is shown in Figure 7-1. BTNLOOK creates 11 child window button controls, one for each of the 11 styles of buttons.

```
btnlook.obj : btnlook.c
cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp btnlook.c
btnlook.exe : btnlook.obj btnlook.def
link4 btnlook, /align:16, /map, slibw, btnlook
```

```
/* BTNLOOK.C -- Button Look Program */
#include <windows.h>
#include <stdio.h>
long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG) ;
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
    HANDLE hInstance, hPrevInstance;
     LPSTR
             lpszCmdLine :
             nCmdShow ;
     int
     WNDCLASS wndclass ;
     HWND hWnd;
     MSG
     static char szAppName [] = "BtnLook" ;
     if (!hPrevInstance)
                                = CS HREDRAW | CS_VREDRAW ;
          wndclass.style
          wndclass.lpfnWndProc = WndProc ;
          wndclass.cbClsExtra
                                = 0 1
          wndclass.cbWndExtra
                              = 0 ;
          wndclass.hInstance = hInstance;
          wndclass.hCon
wndclass.hCursor
                                = Loadicon (NULL, IDI_APPLICATION) ;
                                = LoadCursor (NULL, IDC ARROW) ;
          wndclass.hbrBackground = GetStockObject (WHITE BRUSH) ;
          wndclass.lpszMenuName = NULL ;
          wndclass.lpszClassName = szAppName ;
          if (!RegisterClass (&wndclass))
              return FALSE ;
     hWnd = CreateWindow (szAppName, "Button Look",
                         WS OVERLAPPEDWINDOW,
                         CW_USEDEFAULT, 0,
                         CW_USEDEFAULT, 0,
                         NULL, NULL, hinstance, NULL) ;
```

Figure 7-1. The BTNLOOK program

Figure 7-1. Continued

```
ShowWindow (hWnd, nCmdShow) ;
     UpdateWindow (hWnd) ;
     while (GetMessage (&msg, NULL, 0, 0))
          TranslateMessage (&msg) ;
          DispatchMessage (&msq) ;
     return msg.wParam ;
struct
     long style ;
     char *text ;
     button [] =
     BS PUSHBUTTON,
                        "PUSHBUTTON",
     BS DEFPUSHBUTTON, "DEFPUSHBUTTON",
                          "CHECKBOX",
     BS CHECKBOX,
     BS_AUTOCHECKBOX,
                          "AUTOCHECKBOX",
     BS_RADIOBUTTON,
BS_3STATE,
                          "RADIOBUTTON",
                          "3STATE",
                          "AUTOSSTATE",
     BS AUTO3STATE,
     BS_GROUPBOX,
BS_USERBUTTON,
                          "GROUPBOX"
                    "USERBUTTON",
     BS AUTORADIOBUTTON, "AUTORADIO",
BS PUSHBOX, "PUSHBOX"
     ) ;
#define NUM (sizeof button / sizeof button [0])
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
                   hWnd ;
     HWND
     unsigned
                   iMessage ;
     WORD
                   wParam :
     LONG
                   lParam ;
                              = "wParam
     static char szPrm []
                                                LOWORD (1Param) HIWORD (1Param) ",
                   szTop [] = "Control ID
                                                Window Handle Notification",
                              - 11
                   szUnd []
                   szFormat [] = " %5u
szBuffer [50] ;
                                                   84X
                                                                %5u",
     static HWND hWndButton [NUM] ;
     static RECT rect;
     static short xChar, yChar ;
     HDC
                   hDC ;
     PAINTSTRUCT ps ;
                   i ;
     short
     TEXTMETRIC
                  tm ;
     switch (iMessage)
          case WM CREATE:
               hDC = GetDC (hWnd) ;
               GetTextMetrics (hDC, &tm) ;
               xChar = tm.tmAveCharWidth ;
               yChar = tm.tmHeight + tm.tmExternalLeading ;
               ReleaseDC (hWnd, hDC) ;
```

Figure 7-1. Continued

```
for (i = 0 ; i < NUM ; i++)
                 hWndButton [i] = CreateWindow ("button", button[i].text,
                              WS CHILD | WS VISIBLE | button[i].style, xChar, yChar * (1 + 2 * i),
                              16 * xChar, 2 * yChar,
                              hWnd, i,
                              ((LPCREATESTRUCT) 1Param) -> hInstance, NULL) ;
           break ;
     case WM SIZE:
           rect.left = 20 * xChar;
rect.top = 3 * yChar;
rect.right = LOWORD (lParam);
            rect.bottom = HIWORD (1Param) ;
           break :
     case WM PAINT:
            InvalidateRect (hWnd, &rect, TRUE) ;
            hDC = BeginPaint (hWnd, &ps) ;
            SetBkMode (hDC, TRANSPARENT) ;
           TextOut (hDC, 20 * xChar, 1 * yChar, szPrm, sizeof szPrm - 1);
TextOut (hDC, 20 * xChar, 2 * yChar, szTop, sizeof szTop - 1);
TextOut (hDC, 20 * xChar, 2 * yChar, szUnd, sizeof szUnd - 1);
            EndPaint (hWnd, &ps) ;
           break ;
     case WM COMMAND:
            ScrollWindow (hWnd, 0, -yChar, &rect, &rect) ;
            hDC = GetDC (hWnd) ;
            TextOut (hDC, 20 * xChar, yChar * (rect.bottom / yChar - 1),
                        szBuffer, sprintf (szBuffer, szFormat, wParam,
                              LOWORD (1Param), HIWORD (1Param)));
            ReleaseDC (hWnd, hDC) ;
            ValidateRect (hWnd, NULL) ;
            break ;
      case WM DESTROY:
            PostQuitMessage (0) ;
            break ;
            return DefWindowProc (hWnd, iMessage, wParam, lParam) ;
return OL ;
)
```

```
NAME
               BTNLOOK
               'Button Look Program (C) Charles Petzold, 1987'
DESCRIPTION
               'WINSTUB.EXE'
STUB
CODE
               MOVEABLE
               MOVEABLE MULTIPLE
DATA
               1024
HEAPSIZE
               4096
STACKSIZE
EXPORTS
               WndProc
```

As you click on each button, it sends a WM_COMMAND message to the parent window function, which is the familiar WndProc. BTNLOOK's WndProc displays the wParam and IParam parameters of this message on the right half of the client area, as shown in Figure 7-2.




Figure 7-2. The BTNLOOK display

Creating the Child Windows

BTNLOOK defines a structure called *button* that contains button window styles and descriptive text strings for each of the nine types of buttons. The button window styles all begin with the letters BS, which stand for "button style."

The nine button child windows are created in a *for* loop during WM_CREATE message processing in *WndProc*. The *CreateWindow* call uses the following parameters:

Class name	"button"
Window text	button[i].text
Window style	WS_CHILD WS_VISIBLE button[i].style
x position	xChar
y position	yChar • (1 + 2 • i)
Width	16 • xChar
Height	2 • yChar
Parent window	hWnd
Child window ID	i
Instance handle	((LPCREATESTRUCT) lParam) -> hInstance
Extra parameters	NULL

The class name parameter is the predefined name. The window style uses WS_CHILD, WS_VISIBLE, and one of the 11 button styles (BS_PUSHBUTTON, BS_DEFPUSHBUTTON, and so forth) in the *button* structure. The window text parameter (which for a normal window is the text that appears in the caption bar) is text that will be displayed with each button. I've simply used text that identifies the button style.

The x position and y position parameters indicate the placement of the upper left corner of the child window relative to the upper left corner of the parent window's client area. The width and height parameters specify the width and height of each child window.

The child window ID parameter should be unique for each child window. This ID helps your window function identify the child window when processing WM_COMMAND messages from it.

The instance handle parameter of the *CreateWindow* call looks a little strange, but we're taking advantage of the fact that during a WM_CREATE message *lParam* is actually a pointer to a structure of type CREATESTRUCT ("creation structure") that has a member *hInstance*. So we cast *lParam* into a long (or far) pointer to a CREATESTRUCT structure and get *hInstance* out.

(Some Window programs use a global variable named hInst to give window functions access to the instance handle available in WinMain. In WinMain, you need simply set:

```
hInst = hInstance ;
```

before creating the main window. In Chapter 7 we used GetWindowWord to obtain the instance handle:

```
GetWindowWord (hWnd, GWW_HINSTANCE)
```

Any of these methods is fine.)

After the *CreateWindow* call, we don't have to do anything more with these child windows. The button window function within Windows maintains them for us and handles all repainting jobs. At the program's termination, Windows destroys these child windows when the parent window is destroyed.

The Child Talks to Its Parent

When you run BTNLOOK, you see the different button types displayed on the left side of the client area. (The Bs_USERBUTTON button is not visible, for reasons I'll explain later.) As I mentioned above, when you click a button with the mouse, the child window control sends a WM_COMMAND message to its parent window. BTNLOOK traps the WM_COMMAND message and displays the values of wParam and IParam. Here's what they mean:

wParam Child window ID
LOWORD (IParam) Child window handle
HIWORD (IParam) Notification code

The child window ID is the value passed to *CreateWindow* when the child window was created. In BTNLOOK these IDs are 0 through 10 for the 11 buttons displayed in the client area. The child window handle is the value that Windows returns from the *CreateWindow* call.

The notification code is a submessage code that the child window uses to tell the parent window in more detail what the message means. The possible values of button notification codes are defined in WINDOWS.H:

Button Notification Code Identifier	Value	
BN_CLICKED	0	1 -0 - 1 -1
BN_PAINT	1	
BN_HILITE	2	
BN_UNHILITE	3	
BN_DISABLE	4	
BN_DOUBLECLICKED	5	

For all button styles except BS_USERBUTTON, this notification code is always BN_CLICKED, which simply tells the parent window that the button has been clicked. The other notification codes are used for the BS_USERBUTTON style.

You'll notice that when you click a button with the mouse, a dashed line surrounds the text of the button. This indicates that the button has the input focus. All keyboard input now goes to the child window button control rather than to the main window. However, when the button control has the input focus, it ignores all keystrokes except the Spacebar, which now has the same effect as a mouse click.

The Parent Talks to Its Child

Although BTNLOOK does not demonstrate this fact, a window function can also send messages to the child window control. Four button-specific messages are defined in WINDOWS.H, each begins with the letters "BM," which stand for "button message." These messages are defined in WINDOWS.H in terms of the WM_USER identifier:

```
#define BM_GETCHECK WM_USER+0
#define BM_SETCHECK WM_USER+1
#define BM_GETSTATE WM_USER+2
#define BM_SETSTATE WM_USER+3
#define BM_SETSTYLE WM_USER+4
```

The WM_USER identifier is available for programs to define their own messages beyond the predefined messages. Each window class can have its own separate set of messages unique to that class. The other classes of predefined child window controls also can have their own messages defined in terms of WM_USER.

The BM_GETCHECK and BM_SETCHECK messages are sent by a parent window to a child window control to get and set the check mark of check boxes and radio buttons. The

BM_GETSTATE and BM_SETSTATE messages refer to the reverse-video "flash" of a window when you click it with the mouse. We'll see how these messages work when we look at each type of button.

Push Buttons

The first two buttons shown in BTNLOOK are push buttons. A push button is a rectangle with rounded corners enclosing text specified in the window text parameter of the *CreateWindow* call. The rounded rectangle takes up the full height and width of the dimensions given in the *CreateWindow* or *MoveWindow* call. The text is centered within the rectangle.

Push button controls are used mostly to trigger an immediate action without retaining any type of on/off indication. The two types of push button controls have window styles called Bs_PUSHBUTTON and Bs_DEFPUSHBUTTON. The "DEF" in Bs_DEFPUSHBUTTON stands for "default." When used to design dialog boxes, Bs_PUSHBUTTON controls and Bs_DEFPUSHBUTTON controls function differently from one another. When used as child window controls, however, the two types of push buttons function the same, although Bs_DEFPUSHBUTTON has a heavier outline.

A push button looks best when its height is 7/4 times the height of a SYSTEM_FONT character (including external leading). BTNLOOK uses 2 times the height of a SYSTEM_FONT character. The push button's width must accommodate at least the width of the text plus two additional characters.

When the mouse cursor is inside the push button, pressing the mouse button inverts the interior of the button. Releasing the mouse button restores the original colors and sends a WM_COMMAND message to the parent window with notification code BN_CLICKED. As with the other button types, when a push button has the input focus, a dashed line surrounds the text, and pressing and releasing the Spacebar has the same effect as pressing and releasing the mouse button.

You can simulate a push button flash by sending the window a BM_SETSTATE message. This causes the button to invert:

```
SendMessage (hWndButton, BM_SETSTATE, 1, 0L);
```

This call causes the button to return to normal:

```
SendMessage (hWndButton, BM_SETSTATE, 0, 0L) ;
```

The hWndButton window handle is the value returned from the CreateWindow call.

You can also send a BM_GETSTATE message to a push button. The child window control returns the current state of the button—TRUE if the button is inverted and FALSE (or 0) if normal. Most applications do not require this information, however. And because push buttons do not retain any on/off information, the BM_SETCHECK and BM_GETCHECK messages are not used.

Check Boxes

A check box is a square box containing text that usually appears to the right. (If you include the BS_LEFTTEXT style when creating the button, the text appears to the left.) Check boxes are usually incorporated in an application to allow a user to select options. The check box commonly functions as a toggle switch: Clicking the box once causes an X to appear; clicking again toggles the X off.

The two most common styles for a check box are BS_CHECKBOX and BS_AUTOCHECKBOX. When you use the BS_CHECKBOX style, you must set the X mark yourself by sending the control a BM_SETCHECK message. The wParam parameter is set to 1 to create an X and 0 to remove it. You can obtain the current check state of the box by sending the control a BM_GETCHECK message. You might use code like this to toggle the X mark when processing a WM_COMMAND message from the control:

```
SendMessage (LOWORD (1Param), BM_SETCHECK, (WORD)
!SendMessage (LOWORD (1Param), BM_GETCHECK, 0, 0L), 0L);
```

Note the / operator in front of the second SendMessage call. The low word of IParam is the child window handle passed to your window function in the WM_COMMAND message. When you later need to know the state of the button, send it another BM_GETCHECK message. Or you can retain the current check state in a static variable in your window function. You can also initialize a BS_CHECKBOX check box with an X by sending it a BM_SETCHECK message:

```
SendMessage (hWndButton, BM_SETCHECK, 1, 0L);
```

For the BS_AUTOCHECKBOX style, the button control itself toggles the X on and off. Your window function can ignore WM_COMMAND messages. When you need the current state of the button, send the control a BM_GETCHECK message:

```
nCheck = (WORD) SendMessage (hWndButton, BM_GETCHECK, 0, 0L);
```

The value of nCheck is TRUE or nonzero if the button is checked, FALSE or zero if not.

The other two check box styles are BS_3STATE and BS_AUTO3STATE. As their names indicate, these styles can display a third state as well—a gray color within the check box—which occurs when you send the control a WM_SETCHECK message with wParam equal to 2. The gray color indicates to the user that the box cannot be checked—i.e., that it is disabled. However, the check box control continues to send messages to the parent when the box is clicked. Better methods for disabling a check box are described below.

The check box is aligned with the left edge and is centered within the top and bottom dimensions of the rectangle specified during the *CreateWindow* call. Clicking anywhere within the rectangle causes a WM_COMMAND message to be sent to the parent. The minimum height for a check box is one character height (with external leading). The minimum width is the number of characters in the text plus two.

Radio Buttons

A radio button looks very much like a check box except that it uses a circle rather than a box. A heavy dot within the circle indicates that the radio button has been checked. The radio button has the window style BS_RADIOBUTTON or BS_AUTORADIOBUTTON, but the latter is used only in dialog boxes.

In dialog boxes, groups of radio buttons are conventionally used to indicate mutually exclusive options. (For instance, look at the dialog box in TERMINAL that appears when you select Communication from the Settings menu.) Unlike check boxes, radio buttons do not work as toggles—that is, when you click a radio button a second time, its state remains unchanged.

When you receive a WM_COMMAND message from a radio button, you should display its check by sending it a BM_SETCHECK message with wParam equal to 1:

```
SendMessage (hWndButton, BM_SETCHECK, 1, 0L);
```

For all other radio buttons in the same group, you can turn off the checks by sending them BM_SETCHECK messages with wParam equal to 0:

```
SendMessage (hWndButton, BM_SETCHECK, 0, 0L) ;
```

Group Boxes

The group box, style BS_GROUPBOX, is an oddity in the button class. It neither processes mouse or keyboard input nor sends WM_COMMAND messages to its parent. The group box is a rectangular outline with its window text at the top. Group boxes are often used to enclose other button controls.

User-Defined Buttons

The user-defined button, which has the style BS_USERBUTTON, is the only button that sends WM_COMMAND messages to its parent with these notification codes:

BN_PAINT Button is normal
BN_HILITE Button is being clicked
BN_UNHILITE Clicking is finished
BN_DISABLE Button is disabled

These notification codes indicate that the window must be painted. The parent window is responsible for this painting. It can use the low word of *lParam* to obtain the window handle of the button, *GetClientRect* to determine the button's dimensions, and *GetDC* to get the button's display context in preparation for painting.

Changing the Button Text

You can change the text in a button (or in any other window) by calling SetWindowText:

```
SetWindowText (hWnd, lpszString) ;
```

where hWnd is a handle to the window whose text is being changed and lpszString is a long (or far) pointer to a null-terminated string. For a normal window, this text is the text of the caption bar. For a button control, it's the text displayed with the button.

You can also obtain the current text of a window:

```
nLength = GetWindowText (hWnd, lpszBuffer, nMaxLength);
```

The nMaxLength parameter specifies the maximum number of characters to copy into the buffer pointed to by lpszBuffer. The function returns the string length copied. You can prepare your program for a particular text length by first calling:

```
nlength = GetWindowTextLength (hWnd) ;
```

Visible and Enabled Buttons

To receive mouse and keyboard input, a child window must be both visible (displayed) and enabled. When a child window is visible but not enabled, Windows displays it in gray rather than black.

If you do not include WS_VISIBLE in the window class when creating the child window, the child window will not be displayed until you make a call to ShowWindow:

```
ShowWindow (hWndChild, SW_SHOWNORMAL) ;
```

If you include WS...VISIBLE in the window class, you do not need to call ShowWindow. However, you can hide the child window by a call to ShowWindow:

```
ShowWindow (hWndChild, SW_HIDE) ;
```

You can determine if a child window is visible by a call to:

```
IsWindowVisible (hWndChild) ;
```

You can also enable and disable a child window. By default, a window is enabled. You can disable it by calling:

```
EnableWindow (hWndChild, FALSE) ;
```

For button controls, this has the effect of graying the button and the text string. The button no longer responds to mouse or keyboard input. This is the best method for indicating that a button option is currently unavailable.

You can reenable a child window by calling:

```
EnableWindow (hWndChild, TRUE) ;
```

You can determine whether a child window is enabled by calling:

```
IsWindowEnabled (hWndChild) ;
```

Buttons and Input Focus

As I noted earlier in this chapter, push buttons, check boxes, radio buttons, and user-defined buttons receive the input focus when they are clicked with the mouse. The control indicates it has the input focus by a dashed line surrounding the text. When the child window control gets the input focus, the parent window loses it; all keyboard input then goes to the control rather than to the parent window. However, the child window control responds only to the Spacebar, which now functions like the mouse. This situation presents an obvious problem: Your program has lost control of keyboard processing. Let's see what we can do about it.

When Windows switches the input focus from one window (such as a parent) to another (such as a child window control), it first sends a WM_KILLFOCUS message to the window losing the input focus. The wParam parameter is the handle of the window that is to receive the input focus. Windows then sends a WM_SETFOCUS message to the window receiving the input focus, with wParam the handle of the window losing the input focus. (In both cases, wParam may be NULL, which indicates that no window has or is receiving the input focus.)

A parent window can prevent a child window control from getting the input focus by processing WM_KILLFOCUS messages. Assume that the array hWndChild contains window handles of all child windows. (These were saved in the array during the CreateWindow calls that created the windows.) NUM is the number of child windows:

In this code, when the parent window detects that it's losing the input focus to one of its child window controls, it calls SetFocus to restore the input focus to itself.

Here's a simpler (but less obvious) way of doing it:

```
case WM_KILLFOCUS:
   if (hWnd == GetParent (wParam))
       SetFocus (hWnd);
   break;
```

Both these methods have a shortcoming, however: They undo the button's ability to respond to the Spacebar, because the button never gets the input focus. A better approach would be to let the button get the input focus but also to include the facility for the user to move from button to button using the Tab key. At first this sounds impossible, but I'll show you how to accomplish it with a technique called "window subclassing" in the COLORSCR program shown later in this chapter.

CONTROLS AND COLORS

I deliberately put a little "gotcha" into BTNLOOK. There is something wrong with the program. It may not be immediately apparent, but here's how to see it: Run BTNLOOK and bring up the CONTROL program included with Windows. Select Screen Colors from the Preferences menu, which brings up a dialog box that lets you change system colors. Change the colors of Window Background and Window Text, and save the new settings by clicking the OK button: The background and text of each button in BTNLOOK changes to reflect the new colors, but the background color and text color of the rest of BTNLOOK's client area remains the same—black text on a white background. It looks dreadful. (When I talk about colors here, I use "white" to refer also to the solid green of green-phosphor monochrome displays and the solid amber of amber displays.)

What happened? Simple—the button colors change because they are based on the system colors you set in CONTROL, but BTNLOOK's client-area background remains white because white is specified in the window class:

```
wndclass.hbrBackground = GetStockObject (WHITE_BRUSH) ;
```

When BTNLOOK writes text to the display, it uses the text color and background color defined in the default display context. These are always black and white, regardless of the system colors set with CONTROL.

Let's fix this problem. We'll begin by exploring how Windows uses color. (Meanwhile, you can restore the Windows colors to normal by editing WIN.INI with NOTEPAD, removing the whole [colors] section, exiting Windows, and loading it again.)

Windows' Use of Color

Windows uses an unsigned long (32-bit) integer value to represent a color. The lowest three bytes specify red, green, and blue values that range from 0 through 255, as illustrated by Figure 7-3. This results in a potential 2²⁴ (or about 16 million) colors.




Figure 7-3. The 32-bit color value

This unsigned long is often referred to in the Windows documentation as *rgbColor*. The WINDOWS.H header file provides several macros for working with *rgbColor* values. The RGB macro in WINDOWS.H takes three arguments representing red, green, and blue values and combines them into an unsigned long:

Thus the value:

is really 0x00FF00FF, an *rgbColor* value for magenta. When all three arguments are set to 0, *rgbColor* is black; when the arguments are set to 255, *rgbColor* is white. The *GetRValue*, *GetGValue*, and *GetBValue* macros extract the unsigned character primary-color values from an unsigned long *rgbColor* value. These macros are sometimes handy when using Windows functions that return *rgbColor* values to your program.

The Windows display driver for the Enhanced Graphics Adapter attached to a color display uses only three of the four color planes of the EGA board, so only eight pure colors are possible. A monochrome display has only two pure colors—white and black. Windows can display additional colors by "dithering," which is creating a pixel pattern that combines pixels of different pure colors.

Not all unique combinations of red, green, and blue bytes produce different dithering patterns. For instance, on a color EGA, a red, green, or blue value must generally be incremented by 4 to produce a different dithering pattern. So for an EGA, you have 2¹⁸ (or 262,144) dithered colors. On a monochrome display (such as a CGA, an EGA connected to a monochrome display, or a Hercules Graphics Card), Windows uses 64 different patterns of white and black. The density of white is approximately equal to:

where the red, green, and blue values range from 0 to 255. (Watch out for this: If you're using a color display, you might see nothing wrong with putting a pure red object against a pure blue background. On a monochrome display, however, the pure red and pure blue "colors" appear the same.)

System Colors

Windows maintains 13 system colors for painting various parts of the display. You can obtain and set these colors using *GetSysColor* and *SetSysColor*. Identifiers defined in WINDOWS.H specify the system color. Setting a system color with *SetSysColor* changes it only for the current Windows session.

You can set system colors for future Windows sessions by including a *[colors]* section in the WIN.INI file. The *[colors]* section uses keywords for the 13 system colors (different from the *GetSysColor* and *SetSysColor* identifiers) followed by red, green, and blue values that can range from 0 to 255. You can also use the Windows CONTROL program to change system colors for future sessions. The following table shows how the 13 system colors are identified using the WINDOWS.H identifiers for *GetSysColor* and *SetSysColor*, the WIN.INI keywords, and the CONTROLEXE terms:

GetSysColor & SetSysColor	WIN.INI	CONTROLEXE
COLOR_SCROLLBAR	Scrollbar	Scroll Bars
COLOR_BACKGROUND	Background	Screen Background
COLOR_ACTIVECAPTION	ActiveTitle	Active Title Bar
COLOR_INACTIVECAPTION	InactiveTitle	Inactive Title Bar
COLOR_MENU	Menu	Menu Bar
COLOR_WINDOW	Window	Window Background
COLOR_WINDOWFRAME	WindowFrame	Window Frame
COLOR_MENUTEXT	MenuText	Menu Text
COLOR_WINDOWTEXT	WindowText	Window Text
COLOR_CAPTIONTEXT	TitleText	Title Bar Text
COLOR_ACTIVEBORDER	ActiveBorder	Active Border
COLOR_INACTIVEBORDER	InactiveBorder	Inactive Border
COLOR_APPWORKSPACE	AppWorkspace	Application Workspace

Here are a few useful notes on some of these colors:

- COLOR_SCROLLBAR is the color of the interior section of the scroll bar control, not
 of the scroll bar thumb or the arrows at each end.
- COLOR_BACKGROUND is the desktop area.
- COLOR_WINDOW is the client area of a window and is also used for the scroll bar thumb. (Many Windows programs override this color for their client area.)
- COLOR_WINDOWFRAME is used for lines drawn between many of the sections of
 the display, such as between windows. It is also used as the background to the text
 appearing in the caption bar, as the color of the scroll bar arrows, and as the colors
 of lines that appear in the size box and system menu box.
- COLOR_CAPTIONTEXT is the color of the text in the caption bar. It is also the background color of the system menu box, the size box, and scroll bar arrows.
- COLOR_ACTIVEBORDER and COLOR_INACTIVEBORDER are the colors of the sizing border that surrounds windows which can be sized.

Default values for these 13 colors are provided by the display driver. Windows uses these default values unless they are overriden by the [colors] section of WIN.INI.

The Button Colors

We began this discussion about color when we encountered a color problem with button controls. Here's the problem: Although your Windows program may not use system colors for its client area and text, the predefined child window controls do. For instance, the child window button controls use COLOR_WINDOW to color the background behind the button. (For a group box, COLOR_WINDOW is used only for the background behind the text.) The button control uses COLOR_WINDOWTEXT for all text, for the box in a check box control, and for the round button in a radio button control. The outline of push buttons and group boxes is COLOR_WINDOWFRAME.

You can use one of two methods to make your main window and the child window control consistent in their use of colors. The first method is to use system colors for your main window. To begin, you use COLOR_WINDOW for the background of your client area when defining the window class:

```
wndclass.hbrBackground = COLOR_WINDOW + 1 ;
```

(Windows requires that you add 1 when you use these identifiers in your *undclass* structure, but doing so has no profound purpose other than to prevent the value from being 0.) But that causes another problem. When you display text using *TextOut*, Windows uses values defined in the device context for the text background color (which erases the background behind the text) and the text color. The default values are white (background) and black (text) regardless of both the system colors and the *hbrBackground* field of the window class structure. So you need to use *SetTextColor* and *SetBkColor* to change your text and text background colors to the system colors. You do this after you obtain the handle to a device context:

```
SetBkColor (hDC, GetSysColor (COLOR_WINDOW));
SetTextColor (hDC, GetSysColor (COLOR_WINDOWTEXT));
```

Now the client-area background, text background, and text color are all consistent with button colors. That's the first method.

The second method is to force the child window controls to use the colors you want to use. This method is a little more involved; it requires processing WM_CTLCOLOR messages.

The WM_CTLCOLOR Messages

WM_CTLCOLOR is a message that a predefined child window control sends to its parent window function when the child window is about to paint its client area. The parent window can use this opportunity to alter the colors that the child window function will use for painting.

When the parent window function receives a WM_CTLCOLOR message, the wParam and lParam parameters have the following meaning:

wParam Handle to

Handle to child window's device context

LOWORD(IParam)

Handle to child window

HIWORD(IParam)

Type of window

The high word of <i>lParam</i> can	be one of the following:
------------------------------------	--------------------------

HIWORD (lParam)	Type of Window	
CTLCOLOR_MSGBOX	Message box	
CTLCOLOR_EDIT	Edit control	
CTLCOLOR_LISTBOX	List box control	
CTLCOLOR_BTN	Button control	
CTLCOLOR_DLG	Dialog box	
CTLCOLOR_SCROLLBAR	Scroll bar control	
CTLCOLOR_STATIC	Static control	

Right now, we're interested in CTLCOLOR_BTN, the WM_CTLCOLOR message from a button control. When the parent window function gets this message, the child window control (or the message or dialog box) has already obtained its device context. The handle to this device context is in wParam. Any GDI (Graphics Device Interface) calls you make using this device context will affect the painting that the child window does when you pass control back to the child window.

You must perform three actions when processing a WM_CTLCOLOR message:

- Set a text color using SetTextColor.
- Set a background color using SetBkColor.
- · Return a handle to a brush to the child window.

A "brush" is a GDI object that defines a bitmapped pattern of pixels. Windows uses brushes to fill areas with color. You can get a handle to a brush using GetStockObject, CreateSolid-Brush, CreateHatchBrush, or CreatePatternBrush. For processing WM_CTLCOLOR message, you'll probably use CreateSolidBrush. Before your program terminates, you must explicitly delete any brushes you create. A good time to do this is while processing the WM_DESTROY message.

For most child window controls, the color you set in SetBkColor should be the same as the color of the brush you return from the WM_CTLCOLOR message. For instance, button controls use the brush to color the background of the entire child window client area. The text background color is used only for the background behind the text. These two colors should be the same. To see how this works, let's take an example of processing a WM_CTLCOLOR message for button controls where the window function simply sets the normal default colors. During initialization (probably when processing a WM_CREATE message), you can create a brush:

hBrush = CreateSolidBrush (GetSysColor (COLOR_WINDOW)) ;

The hBrush brush handle should be stored in a static variable. Here's what the WM_CTLCOLOR processing looks like:

```
case WM_CTLCOLOR:
   if (HIWORD (lParam) == CTLCOLOR_BTN)
   {
       SetBkColor (wParam, GetSysColor (COLOR_WINDOW));
      SetTextColor (wParam, GetSysColor (COLOR_WINDOWTEXT));

      UnrealizeObject (hBrush);
      point.x = point.y = 0;
      ClientToScreen (hWnd, &point);
      SetBrushOrg (wParam, point.x, point.y);

      return ((DWORD) hBrush);
   }
   else
   return DefWindowProc (hWnd, iMessage, wParam, lParam);
```

Note that wParam is the device context handle of the button control. The four statements that culminate in the SetBrushOrg call require some further explanation:

As noted above, a brush defines a bitmapped pattern of pixels. When Windows uses this brush to fill an area with color, the pattern of the brush is repeated horizontally and vertically until the area is filled. The origin of this brush—the place where Windows assumes the repeating pattern begins—is the upper left corner of the client area associated with the device context.

But if you color both the client area of a parent window and the client area of a child window with this same brush, the pattern won't merge correctly at the edge of the child window because Windows is using two different origins for the same brush. To avoid this problem, you call *UnrealizeObject*. This function causes Windows to reset the origin of the brush the next time it is selected into a device context (which will follow the return from the WM_CTLCOLOR processing). The origin Windows will use is the one you set with SetBrushOrg; in this example, the function sets the brush origin to the screen origin of the parent window. (Don't use *UnrealizeObject* for a stock brush handle that you obtain from GetStockObject, and don't worry if this sounds a bit obscure right now. We'll cover the issues in more depth in Chapter 13.)

The brush we created above is based on the system color COLOR_WINDOW. If this color changes while the program is running, then the window function receives a WM_SYSCOLORCHANGE message. The program deletes the brush and creates a new one:

```
case WM_SYSCOLORCHANGE:
    DeleteObject (hBrush);
hBrush = CreateSolidBrush (GetSysColor (COLOR_WINDOW));
break;
```

Finally, when the program is about to terminate, the brush should be deleted:

```
case WM_DESTROY:
   DeleteObject (hBrush);
   PostQuitMessage (0);
   break;
```

I've shown here how you can reproduce the default processing of WM_CTLCOLOR messages for button controls. Using your own colors is much the same. You would not need to trap WM_SYSCOLORCHANGE messages unless you wanted to base the brush on a system color. We'll come back to WM_CTLCOLOR messages later in this chapter, when we use the COLORSCR program. For now, let's explore another class of child window controls.

THE STATIC CLASS

You create a static child window control using "static" as the window class in the Create-Window function. These are fairly benign child windows. They do not accept mouse or keyboard input, and they do not send WM_COMMAND messages back to the parent window. (When you move or click the mouse over a static child window, the child window traps the WM_NCHITTEST message and returns a value of HTTRANSPARENT to Windows. This causes Windows to send the same WM_NCHITTEST message to the underlying window, which is usually the parent. The parent usually passes the message to DefWindowProc, where it is converted into a client area mouse message.)

The first six static window styles simply draw a rectangle or frame in the client area of the child window. The three "RECT" static styles (left column below) are filled-in rectangles; the three "FRAME" styles (right column) are rectanglar outlines that are not filled in:

SS_BLACKRECT	SS_BLACKFRAME
SS_GRAYRECT	SS_GRAYFRAME
SS_WHITERECT	SS_WHITEFRAME

"BLACK," "GRAY," and "WHITE" do not mean the colors are black, gray, and white. Rather, the colors are based on system colors as shown here:

Static Control	System Color	
BLACK	COLOR_WINDOWFRAME	
GRAY	COLOR_BACKGROUND	
WHITE	COLOR_WINDOW	

Most display drivers define default settings of black for COLOR_WINDOWFRAME and white for COLOR_WINDOW. However, the driver for an Enhanced Graphics Adapter attached to an enhanced color display uses a greenish color—more precisely, RGB (0, 255, 64)—for

the desktop background. In this case, "GRAY" is actually green. (Of course, a user can change any of these colors using the CONTROL program in Windows.) The colors used in the "RECT" and "FRAME" static styles cannot be changed by trapping WM_CTLCOLOR messages. The window text field of the *CreateWindow* call is ignored for these styles. The upper left corner of the rectangle begins at the x position and y position coordinates relative to the parent window.

The static class also includes three text styles: SS_LEFT, SS_RIGHT, and SS_CENTER. These create left-justified, right-justified, and centered text. The text is given in the window text parameter of the <code>CreateWindow</code> call, and it can be changed later using <code>SetWindowText</code>. When the window function for static controls displays this text, it uses the <code>DrawText</code> function with <code>DT_WORDBREAK</code>, <code>DT_NOCLIP</code>, and <code>DT_EXPANDTABS</code> parameters. The text is wordwrapped within the rectangle of the child window. The background of these three text style child windows is normally <code>COLOR_WINDOW</code>, and the text itself is <code>COLOR_WINDOWTEXT</code>. When you intercept <code>WM_CTLCOLOR</code> messages, you can change the text color by calling <code>SetTextColor</code> and the background color by calling <code>SetBkColor</code> and by returning the handle to the background brush.

Finally, the static class also includes the window styles SS_ICON and SS_USERITEM. However, these have no meaning when used as child window controls. We'll look at them again when discussing dialog boxes.

THE SCROLLBAR CLASS

When the subject of scroll bars first came up in Chapter 3 while designing the SYSMETS program, I discussed some of the differences between "window scroll bars" and "scroll bar controls." SYSMETS uses window scroll bars, which appear at the right and bottom of the window. You add window scroll bars to a window by including the identifier WS_VSCROLL or WS_HSCROLL or both in the window style when creating the window. Now we're ready to make some scroll bar controls, which are child windows that can appear anywhere in the client area of the parent window. You create child window scroll bar controls by using the predefined window class "scrollbar" and one of the two scroll bar styles SBS_VERT and SBS_HORZ.

Unlike the button controls (and the edit and list box controls to be discussed later), scroll bar controls do not send WM_COMMAND messages to the parent window. Instead, they send WM_VSCROLL and WM_HSCROLL messages, just like window scroll bars. When processing the scroll bar messages, you can differentiate between window scroll bars and scroll bar controls by the high word of the *IParam* parameter:

Scroll Bar Type	HIWORD (lParam)	
Window scroll bar	0	
Scroll bar control	Window handle of control	

The wParam parameter and the low word of IParam have the same meaning for window scroll bars and scroll bar controls.

Although window scroll bars have a fixed width, Windows uses the full rectangle dimensions given in the *CreateWindow* call (or later in the *MoveWindow* call) to size scroll bar controls. You can make long, thin scroll bar controls or short, pudgy scroll bar controls. If you want to create scroll bar controls that have the same dimensions as window scroll bars, you can use *GetSystemMetrics* to obtain the height of a horizontal scroll bar:

```
GetSystemMetrics (SM_CYHSCROLL)
```

or the width of a vertical scroll bar:

```
GetSystemMetrics (SM_CXVSCROLL)
```

(The scroll bar window style identifiers SBS_LEFTALIGN, SBS_RIGHTALIGN, SBS_TOPALIGN, and SBS_BOTTOMALIGN are documented to give standard dimensions to scroll bars. However, these styles work only for scroll bars in dialog boxes.)

You can set the range and position of a scroll bar control with the same calls used for window scroll bars:

```
SetScrollRange (hWndScroll, SB_CTL, nMin, nMax, bRedraw) ;
SetScrollPos (hWndScroll, SB_CTL, nPos, bRedraw) ;
```

The difference is that window scroll bars use a handle to the parent window as the first parameter and SB_VERT or SB_HORZ as the second parameter.

The colors used in scroll bar controls are a little different from those used in other child window controls: The interior bar of the scroll bar is COLOR_SCROLLBAR. The thumb is COLOR_WINDOW. The frame around the scroll bar and the arrows at each end are COLOR_WINDOWFRAME. If COLOR_WINDOWFRAME is not a pure color, it is converted to one for the scroll bar arrows. The background behind the arrows is COLOR_CAPTIONTEXT. If you trap WM_CTLCOLOR messages, you can use <code>SetBkColor</code> to set the background color of the arrows and <code>SetTextColor</code> for the arrow colors. The brush returned from the message call is the interior bar of the scroll bar. You cannot change the thumb color.

The COLORSCR Program

To see some uses of scroll bars and static child windows—and also to explore color in more depth—we'll use the COLORSCR ("color scroll") program, shown in Figure 7-4. COLORSCR displays three scroll bars in the left half of the client area labeled "Red," "Green," and "Blue." As you scroll the scroll bars, the right half of the client area changes to the composite color indicated by the mix of the three primary colors. The numeric values of the three primary colors are displayed under the three scroll bars.

```
colorscr.obj : colorscr.c
    cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp colorscr.c

colorscr.exe : colorscr.obj colorscr.def
    link4 colorscr, /align:16, /map, slibw, colorscr
```

```
/* COLORSCR.C -- Color Scroll using child window controls */
#include <windows.h>
#include <stdlib.h>
long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG);
long FAR PASCAL ScrollProc (HWND, unsigned, WORD, LONG);
FARPROC lpfnOldScr[3] ;
        hChScrol[3], hChLabel[3], hChValue[3], hChRect;
short
        color[3], nFocus ;
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
     HANDLE
             hInstance, hPrevInstance;
     LPSTR
                 lpszCmdLine;
     int
                 nCmdShow:
     static char szAppName[] = "ColorScr" ;
     static char *szColorLabel[] = ( "Red", "Green", "Blue" ) ;
     FARPROC
                 lpfnScrollProc ;
     HWND
                 hWnd :
                 msg;
     MSG
     short
                 n ;
     WNDCLASS
                 wndclass ;
     if (hPrevInstance)
          return FALSE ;
     wndclass.style
                            - CS HREDRAW | CS VREDRAW ;
     wndclass.lpfnWndProc = WndProc ;
     wndclass.cbClsExtra = 0;
     wndclass.cbWndExtra
                            = 0 ;
     wndclass.hInstance
                            = hInstance ;
    wndclass.hIcon
                            = NULL ;
     wndclass.hCursor
                            = LoadCursor (NULL, IDC_ARROW) ;
     wndclass.hbrBackground = CreateSolidBrush (OL);
     wndclass.lpszMenuName = NULL ;
     wndclass.lpszClassName = szAppName ;
     if (!RegisterClass (&wndclass))
          return FALSE;
     lpfnScrollProc = MakeProcInstance ((FARPROC) ScrollProc, hInstance) ;
     hWnd = CreateWindow (szAppName, "Color Scroll"
                          WS OVERLAPPEDWINDOW | WS_CLIPCHILDREN,
                          CW_USEDEFAULT, 0,
                          CW USEDEFAULT, 0,
                          NULL, NULL, hInstance, NULL) ;
```

Figure 7-4. The COLORSCR program

```
hChRect = CreateWindow ("static", NULL,
WS_CHILD | WS_VISIBLE | SS_WHITERECT,
                               0, 0, 0, 0,
                               hWnd, 9, hInstance, NULL)
    for (n = 0 ; n < 3 ; n++)
          hChScrol(n) = CreateWindow ("scrollbar", NULL,
                               WS CHILD | WS_VISIBLE | WS_TABSTOP | SBS_VERT,
                               0, 0, 0, 0, hWnd, n, hInstance, NULL);
          hChLabel[n] = CreateWindow ("static", szColorLabel[n],
                               WS_CHILD | WS_VISIBLE | SS_CENTER,
                               0, 0, 0, 0, hWnd, n + 3, hInstance, NULL) ;
          hChValue[n] = CreateWindow ("static", "0",
                               WS_CHILD | WS_VISIBLE | SS_CENTER,
                               0, 0, 0, 0,
hWnd, n + 6, hInstance, NULL);
          lpfnOldScr[n] = (FARPROC) GetWindowLong (hChScrol[n], GWL_WNDPROC) ;
          SetWindowLong (hChScrol[n], GWL WNDPROC, (LONG) lpfnScrollProc) ;
          SetScrollRange (hChScrol[n], SB CTL, 0, 255, FALSE) ;
          SetScrollPos (hChScrol[n], SB_CTL, 0, FALSE) ;
     ShowWindow (hWnd, nCmdShow) ;
     UpdateWindow (hWnd);
     while (GetMessage (&msg, NULL, 0, 0))
          TranslateMessage (&msg) ;
          DispatchMessage (&msg) ;
     return msg.wParam ;
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
     HWND
                   hWnd;
     unsigned
                   iMessage:
     WORD
                    wParam;
                   1Param;
     LONG
     static HBRUSH hBrush [3] ;
                   szbuffer[10] ;
     char
                   hDC ;
     HDC
                   point
     POINT
                   n, xClient, yClient, yChar ;
     short
     TEXTMETRIC
                   tm ;
     switch (iMessage)
          case WM CREATE :
               hBrush[0] = CreateSolidBrush (RGB (255, 0, 0));
               hBrush[1] = CreateSolidBrush (RGB (0, 255, 0));
               hBrush[2] = CreateSolidBrush (RGB (0, 0, 255));
               break ;
```

```
case WM SIZE :
     xClient = LOWORD (1Param) ;
     yClient = HIWORD (1Param) ;
     hDC = GetDC (hWnd) ;
     GetTextMetrics (hDC, &tm) ;
     yChar = tm.tmHeight ;
     ReleaseDC (hWnd, hDC) ;
     MoveWindow (hChRect, 0, 0, xClient / 2, yClient, TRUE) ;
     for (n = 0 ; n < 3 ; n++)
           MoveWindow (hChScrol[n],
                (2 * n + 1) * xClient / 14, 2 * yChar,
xClient / 14, yClient - 4 * yChar, TRUE) ;
           MoveWindow (hChLabel[n],
                (4 * n + 1) * xClient / 28, yChar / 2,
xClient / 7, yChar, TRUE) ;
           MoveWindow (hChValue[n],
                (4 * n + 1) * xClient / 28, yClient - 3 * yChar / 2,
                xClient / 7, yChar, TRUE) ;
     SetFocus (hWnd) ;
     break ;
case WM SETFOCUS:
     SetFocus (hChScrol[nFocus]) ;
     break ;
case WM VSCROLL :
     n = GetWindowWord (HIWORD (1Param), GWW ID) ;
     switch (wParam)
           case SB PAGEDOWN :
                color[n] += 15 ;
                                       /* fall through */
           case SB LINEDOWN :
                color[n] = min (255, color[n] + 1);
                break ;
           case SB PAGEUP :
                color[n] -= 15 ;
                                          /* fall through */
           case SB LINEUP :
                color[n] = max (0, color[n] - 1);
                break :
          case SB TOP:
                color[n] = 0 ;
                break ;
          case SB BOTTOM :
               color[n] = 255 ;
                break ;
          case SB_THUMBPOSITION : case SB_THUMBTRACK :
                color[n] = LOWORD (1Param) ;
                break ;
          default :
               break ;
```

```
SetScrollPos (hChScrol[n], SB_CTL, color[n], TRUE) ;
              SetWindowText (hChValue[n], itoa (color[n], szbuffer, 10)) ;
               DeleteObject (GetClassWord (hWnd, GCW HBRBACKGROUND));
               SetClassWord (hWnd, GCW HBRBACKGROUND,
                    CreateSolidBrush (RGB (color[0], color[1], color[2]))) ;
               InvalidateRect (hWnd, NULL, TRUE) ;
               break :
          case WM CTLCOLOR:
               if (HIWORD (1Param) == CTLCOLOR SCROLLBAR)
                    SetBkColor (wParam, GetSysColor (COLOR CAPTIONTEXT)) ;
                    SetTextColor (wParam, GetSysColor (COLOR WINDOWFRAME));
                    n = GetWindowWord (LOWORD (lParam), GWW ID) ;
                    point.x = point.y = 0 ;
                    ClientToScreen (hWnd, &point) ;
                    UnrealizeObject (hBrush[n]) ;
                    SetBrushOrg (wParam, point.x, point.y) ;
                    return ((DWORD) hBrush[n]) ;
                    break ;
               else
                    return DefWindowProc (hWnd, iMessage, wParam, 1Param) ;
               break ;
          case WM DESTROY:
               DeleteObject (GetClassWord (hWnd, GCW HBRBACKGROUND)) ;
               for (n = 0 ; n < 3 ; DeleteObject (hBrush [n++])) ;
               PostQuitMessage (0) ;
               break ;
          default :
               return DefWindowProc (hWnd, iMessage, wParam, 1Param) ;
     return OL ;
long FAR PASCAL ScrollProc (hWnd, iMessage, wParam, 1Param)
             hWnd ;
     unsigned iMessage ;
             wParam :
     WORD
     LONG
             lParam ;
              n = GetWindowWord (hWnd, GWW ID) ;
     switch (iMessage)
          case WM KEYDOWN:
               if (wParam == VK TAB)
                    SetFocus (hChScrol((n +
                         (GetKeyState (VK_SHIFT) < 0 ? 2 : 1)) % 3]) ;
               break ;
          case WM SETFOCUS:
               nFocus = n ;
               break :
     return CallWindowProc (lpfnOldScr[n], hWnd, iMessage, wParam, lParam) ;
     1
```

Figure 7-4. Continued

```
NAME
               COLORSCR
DESCRIPTION
               'Color Scroll (C) Charles Petzold, 1987'
STUB
               'WINSTUB.EXE'
CODE
               MOVEABLE
DATA
               MOVEABLE MULTIPLE
HEAPSIZE
               1024
STACKSIZE
               4096
EXPORTS
               WndProc
               ScrollProc
```

COLORSCR puts its children to work. The program uses 10 child window controls: 3 scroll bars, 6 windows of static text, and 1 static rectangle. COLORSCR traps WM_CTLCOLOR messages to color the interior sections of the three scroll bars red, green, and blue. You can scroll the scroll bars using either the mouse or the keyboard. You can use COLORSCR as a development tool in experimenting with color and choosing attractive (or, if you prefer, ugly) colors for your own Windows programs. A monochrome version of the COLORSCR display is shown in Figure 7-5; obviously, to take advantage of the program's manipulation of color, you'll need to use a color monitor. A color version of the COLORSCR display is shown on the back cover of this book.




Figure 7-5. A monochrome version of the COLORSCR display

COLORSCR doesn't process WM_PAINT messages, and the program obtains a device context handle only for determining the height of a character. Most of the work in COLORSCR is done by the child windows.

The color shown at the right half of the client area is actually the background color of the parent window. A static child window with style SS_WHITERECT blocks out the left half of the client area. The three scroll bars are child window controls with the style SBS_VERT placed on top of the SS_WHITERECT child. Six more static child windows of style SS_CENTER (centered text) provide the labels and the color values. COLORSCR creates its normal overlapped window and the ten child windows within the WinMain function using Create-Window. The SS_WHITERECT and SS_CENTER static windows use the window class "static," and the three scroll bars use the window class "scrollbar."

The x position, y position, width, and height parameters of the CreateWindow call are initially set to 0 because the position and sizing depend on the size of the client area, which is not yet known. COLORSCR's window function resizes all ten child windows using Move-Window when it receives a WM_SIZE message. So whenever you resize the COLORSCR window, the size of the scroll bars changes proportionally.

When the WndProc window function receives a WM_VSCROLL message, the high word of the IParam parameter is the handle to the child window. We can use GetWindowWord to get the window ID number:

```
n = GetWindowWord (HIWORD (1Param), GWW_ID) ;
```

For the three scroll bars, we have conveniently set the ID numbers to 0, 1, and 2, so WndProc can tell which scroll bar is generating the message.

Because the handles to the child windows were saved in arrays when the windows were created, WndProc can process the scroll bar message and set the new value of the appropriate scroll bar using the SetScrollPos call:

```
SetScrollPos (hChScrol[n], SB_CTL, color[n], TRUE) ;
```

WndProc also changes the text of the child window at the bottom of the scroll bar:

```
SetWindowText (hChValue[n], itoa (color[n], szbuffer, 10));
```

The Automatic Keyboard Interface

Scroll bar controls can also process keystrokes, but only if they have the input focus. The following chart shows how keyboard cursor keys translate into scroll bar messages:

Cursor Key	Key Scroll Bar Message wParam Value	
Home	SB_TOP	
End	SB_BOTTOM	
Page Up	SB_PAGEUP	
Page Down	SB_PAGEDOWN	
Left or Up	SB_LINEUP	
Right or Down	SB_LINEDOWN	

In fact, the SB_TOP and SB_BOTTOM scroll bar messages can be generated only by using the keyboard and not the mouse. If you want a scroll bar control to obtain the input focus when the scroll bar is clicked with the mouse, you must include the WS_TABSTOP identifier in the window class parameter of the <code>CreateWindow</code> call. When a scroll bar has the input focus, a blinking gray block is displayed on the scroll bar thumb.

To provide a full keyboard interface to the scroll bars, however, some more work is necessary. First, the *WndProc* window function must specifically give a scroll bar the input focus. It does this by processing the WM_SETFOCUS message, which the parent window receives when it obtains the input focus. *WndProc* simply sets the input focus to one of the scroll bars:

```
SetFocus (hChScrol[nFocus]);
```

But you also need some way to get from one scroll bar to another by using the keyboard, preferably by using the Tab key. This is more difficult, because once a scroll bar has the input focus, it processes all keystrokes. But the scroll bar cares only about the cursor keys; it ignores the Tab key. The way out of this dilemma lies in a technique called "window subclassing." We'll use it to add a facility to COLORSCR to jump from one scroll bar to another using the Tab key.

Window Subclassing

The window function for the scroll bar controls is somewhere inside Windows. However, you can obtain the address of this window function by a call to <code>GetWindowLong</code> using the <code>GWL_WNDPROC</code> identifier as a parameter. Moreover, you can set a new window function for the scroll bars by calling <code>SetWindowLong</code>. This technique, called "window subclassing," is very powerful. It lets you hook into existing window functions, process some messages within your own program, and pass all other messages to the old window function.

The window function that does preliminary scroll bar message processing in COL-ORSCR is called *ScrollProc*; it is toward the end of the COLORSCR.C listing. Because *ScrollProc* is a function within COLORSCR that is called by Windows, it must be defined as FAR PASCAL and must be listed in the EXPORTS in the COLORSCR.DEF module definition file.

First, to ensure that ScrollProc accesses the proper data segment, COLORSCR must obtain a far address for the function using MakeProcInstance:

```
lpfnScrollProc = MakeProcInstance ((FARPROC) ScrollProc, hInstance);
```

For each of the three scroll bars, COLORSCR uses GetWindowLong to obtain and save the address of the existing scroll bar window function:

```
lpfnOldScr[n] = (FARPROC) GetWindowLong (hChScrol[n], GWL_WNDPROC) ;
```

Next, the program sets the new scroll bar window function:

```
SetWindowLong (hChScrol[n], GWL_WNDPROC, (LONG) lpfnScrolProc) ;
```

Now the function ScrollProc gets all messages that Windows sends to the scroll bar window function for the three scroll bars in COLORSCR (but not, of course, for scroll bars in other programs). The ScrollProc window function simply changes the input focus to the next (or previous) scroll bar when it receives a Tab or Shift-Tab keystroke. It calls the old scroll bar window function using CallWindowProc.

Coloring the Background

When COLORSCR defines its window class, it gives the background of its client area a solid black brush:

```
wndclass.hbrBackground = CreateSolidBrush (OL) ;
```

When you change the settings of COLORSCR's scroll bars, the program must create a new brush and put the new brush handle in the window class structure. Just as we were able to get and set the scroll bar window function using <code>GetWindowLong</code> and <code>SetWindowLong</code>, we can get and set the handle to this brush using <code>GetClassWord</code> and <code>SetClassWord</code>.

First you must delete the existing brush:

```
DeleteObject (GetClassWord (hWnd, GCW_HBRBACKGROUND))
```

Then you can create the new brush and insert the handle in the window class structure:

The next time Windows recolors the background of the window, Windows will use this new brush. To force Windows to erase the background, we invalidate the entire client area:

```
InvalidateRect (hWnd, NULL, TRUE) ;
```

The TRUE (nonzero) value as the third parameter indicates that we want the background erased before repainting.

InvalidateRect causes Windows to put a WM_PAINT message in the message queue of the window function. Because WM_PAINT messages are low priority, this message will not be processed immediately if you are still moving the scroll bar with the mouse or the cursor keys. Alternatively, if you want the window to be updated immediately after the color is changed, you can add the statement:

```
UpdateWindow (hWnd) ;
```

after the InvalidateRect call. But this slows down keyboard and mouse processing.

COLORSCR's WndProc function doesn't process the WM_PAINT message but passes it to DefWindowProc. Window's default processing of WM_PAINT messages simply involves calling BeginPaint and EndPaint to validate the window. Because we specified in the InvalidateRect call that the background should be erased, the BeginPaint call causes Windows to generate a WM_ERASEBKGND (erase background) message. WndProc ignores this message also. Windows processes it by erasing the background of the client area using the brush specified in the window class.

Normally, Windows would erase the entire client area using the window class brush. Doing so would erase the 10 child windows, however, and Windows would then have to send WM_PAINT messages to all the child windows so they could repaint themselves—very annoying. We avoid the problem by using the WS_CLIPCHILDREN style value when first creating the parent window using <code>CreateWindow</code>; this style prevents the parent window from painting over its children. Take the WS_CLIPCHILDREN style out of <code>CreateWindow</code>, and you'll see a big difference in how COLORSCR works.

Like all GDI objects, the brushes created by a program using *CreateSolidBrush* are not automatically deleted by Windows when the program terminates. We've been good about deleting each brush before creating a new one, but when the program is about to terminate, one last brush in the window class still should be discarded. Thus during processing of the WM_DESTROY message, *DeleteObject* is called once more:

```
DeleteObject (GetClassWord (hWnd, GCW_HBRBACKGROUND));
```

Coloring the Scroll Bars

On a color display, the interiors of the three scroll bars in COLORSCR are red, green, and blue. This coloring is accomplished by processing WM_CTLCOLOR messages.

In WndProc we define a static array of three handles to brushes:

```
static HBRUSH hBrush [3] ;
```

During processing of WM_CREATE, we create the three brushes:

```
hBrush[0] = CreateSolidBrush (RGB (255, 0, 0));
hBrush[1] = CreateSolidBrush (RGB (0, 255, 0));
hBrush[2] = CreateSolidBrush (RGB (0, 0, 255));
```

During the WM_CTLCOLOR processing, the text and text background colors are set to the normal values for scroll bars. The brush that's returned from this message is one of the three brushes created earlier:

These brushes must be destroyed during processing of the WM_DESTROY message:

```
for (n = 0 ; n < 3 ; DeleteObject (hBrush [n++])) ;
```

Dealing with Multiple Instances

Normally, Windows programs reuse the same window class when you load multiple instances of the program. The window class is registered only if the previous instance is NULL:

But COLORSCR can't do this, because the background color is specified in the window class. If all instances of COLORSCR used the same window class, then each instance would use (and change) the same background color. We can avoid this problem entirely by allowing only one instance of COLORSCR to run:

```
if (hPrevInstnace)
return FALSE
```

COLORSCR as an Icon

When you make COLORSCR into an icon, the entire surface of the icon—rather than only the right half—is the color of the parent window's background. Yet COLORSCR doesn't seem to have any separate icon logic.

You'll note that COLORSCR specifies a NULL icon in the window class:

```
wndclass.hIcon = NULL ;
```

This indicates that COLORSCR is responsible for painting its icon. The entire icon appears as the background color because Windows hides child windows when a program becomes an icon, and thus the colored background is completely uncovered.

THE EDIT CLASS

The edit class is in some ways the simplest predefined window class and in other ways the most complex. When you create a child window using the class name "edit," you define a rectangle based on the x position, y position, width, and height parameters of the CreateWindow call. This rectangle contains editable text. When the child window control has the input focus, you can type text, move the cursor around, select portions of text using either the mouse or the Shift key and a cursor key, delete selected text to the clipboard by pressing Shift-Del, or insert text from the clipboard by pressing Shift-Ins.

One of the simplest uses of edit controls is for single-line entry fields. For instance, the PIFEDIT program included with Windows uses edit controls in this way on its main window. But edit controls are not limited to single lines. For example, the NOTEPAD program included with Windows uses a multiline edit control. The size of the NOTEPAD.EXE program is surprisingly small—less than 20 KB. Most of the editing logic is not in NOTEPAD at all; it's in the edit control logic within Windows.

To give you an idea of the power of edit controls, we'll write a "NOTEPAD clone" program called POPPAD. We'll begin the program in this chapter and continue it in Chapters 10 (when we'll add a menu) and 11 (when we'll use dialog boxes to load and save files). The first version of POPPAD is shown in Figure 7-6.

```
poppad.obj : poppad.c
    cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp poppad.c

poppad.exe : poppad.obj poppad.def
    link4 poppad, /align:16, /map, slibw, poppad.def
    echo /* no resources */ >poppad.rc
    rc poppad
```

Figure 7-6. The POPPAD program

```
/* POPPAD.C -- Popup Editor using child window edit box */
#include <windows.h>
long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG);
char szAppName [] = "PopPad" ;
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
     HANDLE
               hInstance, hPrevInstance;
               lpszCmdLine:
     LPSTR
               nCmdShow;
     int
     MSG
               msq;
     HWND
               hWnd ;
     WNDCLASS wndclass ;
     if (!hPrevInstance)
          wndclass.style
                                  = CS_HREDRAW | CS_VREDRAW ;
          wndclass.lpfnWndProc = WndProc;
          wndclass.cbClsExtra = 0;
wndclass.cbWndExtra = 0;
          wndclass.hInstance = hInstance;
                            = LoadIcon (NULL, IDI_APPLICATION) ;
= LoadCursor (NULL, IDC_ARROW) ;
          wndclass.hIcon
          wndclass.hCursor
          wndclass.hbrBackground = GetStockObject (WHITE_BRUSH) ;
          wndclass.lpszMenuName = NULL ;
          wndclass.lpszClassName = szAppName ;
          if (!RegisterClass (&wndclass))
               return FALSE;
     hWnd = CreateWindow (szAppName, szAppName,
                          WS OVERLAPPEDWINDOW,
                          CW USEDEFAULT, 0,
                          GetSystemMetrics (SM CXSCREEN) / 2,
                          GetSystemMetrics (SM_CYSCREEN) / 2,
                          NULL, NULL, hInstance, NULL) ;
     ShowWindow (hWnd, nCmdShow) ;
     UpdateWindow (hWnd);
     while (GetMessage (&msg, NULL, 0, 0))
          TranslateMessage (&msg) ;
          DispatchMessage (&msq) ;
     return msq.wParam ;
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
     HWND
                 hWnd;
     unsigned
                 iMessage;
     WORD
                 wParam;
     LONG
                 lParam;
     static HWND hWndEdit ;
```

Figure 7-6. Continued

```
switch (iMessage)
     case WM CREATE:
           hWndEdit = CreateWindow ("edit", NULL,
                      WS_CHILD | WS_VISIBLE | WS_HSCROLL | WS_VSCROLL |
WS_BORDER | ES_LEFT | ES_MULTILINE |
ES_AUTOHSCROLL | ES_AUTOVSCROLL,
                       0, 0, 0, 0,
                       hWnd, 1,
                       ((LPCREATESTRUCT) 1Param) -> hInstance, NULL) :
           break ;
     case WM SETFOCUS:
           SetFocus (hWndEdit) ;
           break ;
     case WM SIZE:
           MoveWindow (hWndEdit, 0, 0, LOWORD (1Param),
                                           HIWORD (1Param), TRUE) ;
           break :
     case WM COMMAND :
           if (wParam == 1 && HIWORD (1Param) == EN ERRSPACE)
                 MessageBox (hWnd, "Edit control out of space.",
                            szAppName, MB OK | MB ICONHAND) ;
           break :
     case WM DESTROY :
           PostQuitMessage (0) ;
           break ;
     default :
           return DefWindowProc (hWnd, iMessage, wParam, 1Param) ;
return OL ;
```

```
NAME
              POPPAD
            'Popup Editor (C) Charles Petzold, 1987'
DESCRIPTION
              'WINSTUB.EXE'
STUB
CODE
              MOVEABLE
DATA
              MOVEABLE MULTIPLE
HEAPSIZE
              1024
STACKSIZE
              4096
EXPORTS
              WndProc
```

POPPAD is a multiline editor (without any file I/O just yet) in less than 100 lines of C. As you can see, POPPAD itself doesn't do very much. The predefined edit control is doing quite a lot. In this form, the program lets you explore what edit controls can do without any help from a program.

The Edit Class Styles

As noted above, you create an edit control using "edit" as the window class in the *Create-Window* call. The window style is WS_CHILD plus several options. As in static child window controls, the text in edit controls can be either left-justified, right-justified, or centered. You specify this formatting with the window styles ES_LEFT, ES_RIGHT, and ES_CENTER.

By default, an edit control has a single line. You can create a multiline edit control with the window style ES_MULTILINE. For a single-line edit control, you can normally enter text only to the end of the edit control rectangle. To create an edit control that automatically scrolls horizontally, you use the style ES_AUTOHSCROLL. For a multiline edit control, text wordwraps unless you use the ES_AUTOHSCROLL style, in which case you must press the Enter key to start a new line. You can also include vertical scrolling in a multiline edit control by using the style ES_AUTOVSCROLL.

When you include these scrolling styles in multiline edit controls, you might also want to add scroll bars to the edit control. You do so using the same window style identifiers as for nonchild windows: WS_HSCROLL and WS_VSCROLL.

By default, an edit control has no border. You can add one using the style WS_BORDER.

When you select text in an edit control, Windows displays it in reverse video. When the edit control loses the input focus, however, the selected text is no longer highlighted. If you want the selection to be highlighted even when the edit control does not have the input focus, you can use the style ES... NOHIDESEL.

When POPPAD creates its edit control, the style is given in the CreateWindow call as:

```
WS_CHILD | WS_VISIBLE | WS_HSCROLL | WS_VSCROLL |
WS_BORDER | ES_LEFT | ES_MULTILINE |
ES_AUTOHSCROLL | ES_AUTOVSCROLL
```

In POPPAD the dimensions of the edit control are later defined by a call to *MoveWindow* when *WndProc* receives a WM_SIZE message. The size of the edit control is simply set to the size of the main window:

```
MoveWindow (hWndEdit, 0, 0, LOWORD (1Param),
HIWORD (1Param), TRUE);
```

For a single-line edit control, the height of the control must accommodate the height of a character. If the edit control has a border (as most do), then use 1½ times the height of a character (including external leading).

Edit Control Notification

Edit controls send WM_COMMAND messages to the parent window function. The meanings of the wParam and lParam variables are the same as for button controls:

Parameter	Description	
wParam	Child window ID	
LOWORD(IParam)	Child window handle	
HIWORD(lParam)	Notification code	

The notification codes are shown below:

EN_CHANGE	Edit control's contents have changed
EN_VSCROLL	Edit control's vertical scroll bar has been clicked
EN_HSCROLL	Edit control's horizontal scroll bar has been clicked
EN_SETFOCUS	Edit control has gained the input focus
EN_KILLFOCUS	Edit control has lost the input focus
EN_ERRSPACE	Edit control has run out of space

The current version of POPPAD traps only EN_ERRSPACE notification codes and displays a message box.

The edit control stores text in the local heap of its parent window's program. The contents of an edit control are limited to 32 KB. You'll note that POPPAD reserves only 1 KB of space for its local heap in the module definition file. As we'll see in Chapter 8, this is not a problem. Windows will expand the program's local heap if an edit control needs more space.

Using the Edit Controls

If you use several single-line edit controls on the surface of your main window (as PIFEDIT does), you'll need to use window subclassing to move the input focus from one to another. You can accomplish this much as COLORSCR does, by intercepting Tab and Shift-Tab keystrokes. (Another example of window subclassing is shown later in this chapter in the HEAD program.) How you handle the Enter key is up to you. You can use it the same way as the Tab key or as a signal to your program that all the edit fields are ready.

If you want to insert text into an edit field, you can do so using SetWindowText. Getting text out of an edit control involves GetWindowTextLength and GetWindowText. We'll see examples of these facilities in our later revisions to the POPPAD program.

Messages to an Edit Control

We won't cover all the messages you can send to an edit control using *SendMessage*, because there are quite a few of them, and several will be used in the later POPPAD revisions. Here's a broad overview.

These messages let you cut, copy, or clear the current selection. A user selects the text to be acted upon by using the mouse or the Shift key and a cursor key, thus highlighting the selected text in the edit control.

```
SendMessage (hWndEdit, WM_CUT, 0, 0L);
SendMessage (hWndEdit, WM_COPY, 0, 0L);
SendMessage (hWndEdit, WM_CLEAR, 0, 0L);
```

WM_CUT removes the current selection from the edit control and sends it to the clipboard.

WM_COPY copies the selection to the clipboard but leaves it intact in the edit control.

WM_CLEAR deletes the selection from the edit control without passing it to the clipboard.

You can also insert clipboard text into the edit control at the cursor position:

```
SendMessage (hWndEdit, WM_PASTE, 0, 0L);
```

You can obtain the starting and ending positions of the current selection:

```
1Select = SendMessage (hWndEdit, EM_GETSEL, 0, 0L) ;
```

The low word of *lSelect* has the starting position. The high word has the end position plus 1. You can select text:

```
SendMessage (hWndEdit, EM_SETSEL, 0,
MAKELONG (wBegin, wEnd));
```

You can also replace a current selection with other text:

```
SendMessage (hWndEdit, EM_REPLACESEL, 0, (LONG) lpszString);
```

For multiline edit controls, you can obtain the number of lines:

```
nCount = SendMessage (hWndEdit, EM_GETLINECOUNT, 0, 0L);
```

For any particular line, you can obtain an offset from the beginning of the edit buffer text:

```
nOffset = SendMessage (hWndEdit, EM_LINEINDEX, wLine, OL) ;
```

Lines are numbered starting at 0. A wLine value of -1 returns the offset of the line containing the cursor. You obtain the length of the line from:

```
nOffset = SendMessage (hWndEdit, EM_LINELENGTH, wLine, 01);
and copy the line itself into a buffer using:

nLength = SendMessage (hWndEdit, EM_GETLINE, wLine, lpszBuffer);
```

THE LISTBOX CLASS

The final predefined child window control is the list box, which is a collection of text strings displayed as a scrollable columnar list within a rectangle. A program can add or remove strings in the list by sending messages to the list box window function. The list box control sends WM_COMMAND messages to its parent window when an item in the list is selected. The parent window can then determine which item has been selected.

List boxes are most commonly used in dialog boxes called up by selecting Open from the File menu. The list box displays files in the current directory and can also display other subdirectories and disk drives. List boxes are also used in the CONTROL program for changing colors and in WRITE for selecting fonts. A list box can be either single selection or multiple selection. The latter allows the user to select more than one item from the list box. When a list box has the input focus, it displays a dashed line surrounding an item in the list box. This cursor does *not* indicate the selected item in the list box. The selected item is indicated by highlighting, which displays the item in reverse video.

In a single-selection list box, the user can select the item that the cursor is positioned on by pressing the Spacebar. The arrow keys move both the cursor and the current selection and can scroll contents of the list box. The Page Up and Page Down keys also scroll the list box by moving the cursor but not the selection. Pressing a letter key moves the cursor and the selection to the first (or next) item that begins with that letter. An item can also be selected by clicking or double-clicking the mouse on the item.

In a multiple-selection list box, the Spacebar toggles the selection state of the item where the cursor is positioned. (If the item is already selected, it is deselected.) The arrow keys deselect all previously selected items and move the cursor and selection just as in single-selection list boxes. However, the Ctrl key and the arrow keys can move the cursor without moving the selection. The Shift key and arrow keys can extend a selection.

Clicking or double-clicking an item in a multiple-selection list box deselects all previously selected items and selects the clicked item. However, clicking an item while pressing the Shift key toggles the selection state of the item without changing the selection state of any other item.

List Box Styles

You create a list box child window control with *CreateWindow* using "listbox" as the window class and WS_CHILD as the window style. However, this default list box style does not send WM_COMMAND messages to its parent, meaning that a program would have to interrogate the list box (via messages to the list box controls) regarding the selection of items within the list box. Therefore, list box controls almost always include the list box style identifier

LBS_NOTIFY, which allows the parent window to receive WM_COMMAND messages from the list box. If you want the list box control to sort the items in the list box, you can also use LBS_SORT, another common style.

By default, list boxes are single selection. Multiple-selection list boxes are relatively rare. If you want to create one, you use the style LBS_MULTIPLESEL.

Normally, a list box updates itself when a new item is added to the scroll box list. You can prevent this by including the style LBS_NOREDRAW. You will probably not want to use this style, however. Instead, you can temporarily prevent repainting of a list box control by using the WM_SETREDRAW message that I'll describe a little later.

By default, the list box window function displays only the list of items without any border around the box. You can add a border with the window style identifier WS_BORDER. And to add a vertical scroll bar for scrolling through the list with the mouse, you use the window style identifier WS_VSCROLL.

WINDOWS.H defines a list box style called LBS_STANDARD that includes the most commonly used styles. It is defined as:

```
(LBS_NOTIFY | LBS_SORT | WS_VSCROLL | WS_BORDER)
```

You can also use the WS_SIZEBOX and WS_CAPTION identifiers, but these will allow the user to resize the list box and to move it around its parent's client area.

The width of a list box should accommodate the width of the longest string plus the width of the scroll bar. You can get the width of the vertical scroll bar using:

```
GetSystemMetrics (SM_CXVSCROLL)
```

You can calculate the height of the list box by multiplying the height of a character by the number of items you want to appear in view. A list box does not use *tmExternalLeading* when spacing lines of text.

Putting Strings in the List Box

After you've created the list box, the next step is to put text strings in it. You do this by sending messages to the list box window function using the <code>SendMessage</code> call. The text strings are generally referenced by an index number that starts at 0 for the topmost item. In the examples that follow, <code>hWndList</code> is the handle to the child window list box control, and <code>wIndex</code> is the index value.

In cases where you pass a text string in the SendMessage call, the IParam parameter is a far pointer to a null-terminated string. To avoid error messages during compilation, cast this pointer into a LONG. Note that when you cast a near pointer to a LONG, the C compiler will first cast the near pointer to a far pointer.

In most of these examples, the SendMessage call returns LB_ERRSPACE (defined as -2) if the window function runs out of available memory space to store the contents of the list box. SendMessage returns LB_ERR (-1) if an error occurs for other reasons and LB_OKAY (0) if the operation is successful. You can test *SendMessage* for a nonzero value to detect either of the two errors. The list box allocates global memory (outside your program's data segment) for the list box contents.

If you use the LBS_SORT style (or if you are placing strings in the list box in the order that you want them to appear), the easiest way to fill up a list box is with the LB_ADDSTRING message:

```
SendMessage (hWndList, LB_ADDSTRING, 0, (LONG) szString);
```

If you do not use LBS_SORT, you can insert strings into your list box by specifying an index value with LB_INSERTSTRING:

```
SendMessage (hWndList, LB_INSERTSTRING, wIndex, (LONG) szString);
```

For instance, if wIndex is equal to 4, then szString becomes the new string with an index value of 4—the fifth string from the top because counting starts at 0. Any strings below this point are pushed down. A wIndex value of -1 adds the string to the bottom. You can use LB_INSERTSTRING with list boxes that have the LBS_SORT style, but the list box contents will not be resorted. (You can also insert strings into a list box using the LB_DIR message, which is discussed in detail toward the end of this chapter.)

You can delete a string from the list box by specifying the index value with the LB_DELETESTRING message:

```
SendMessage (hWndList, LB_DELETESTRING, wIndex, OL) ;
```

You can clear out the listbox using LB_RESETCONTENT:

```
SendMessage (hWndList, LB_RESETCONTENT, 0, 0L) ;
```

The list box window function updates the display when an item is added to or deleted from the list box. If you have a number of strings to add or delete, you may want to temporarily inhibit this action by turning off the control's redraw flag:

```
SendMessage (hWndList, WM_SETREDRAW, FALSE, OL);
```

After you've finished, you can turn the redraw flag back on:

```
SendMessage (hWndList, WM_SETREDRAW, TRUE, OL) ;
```

A list box created with the LBS_NOREDRAW style begins with the redraw flag turned off.

Selecting and Extracting Entries

The SendMessage calls that carry out the tasks shown below usually return a value. If an error occurs, this value is set to LB_ERR (defined as -1). Note that the return value from SendMessage is normally a signed long (LONG), but the values are unsigned integers (WORD), so some casting is necessary.

After you've put some items into a list box, you can find out how many items are in the list box:

```
nCount = (WORD) SendMessage (hWndList, LB_GETCOUNT, 0, 0L) ;
```

Some of the other calls are different for single-selection and multiple-selection list boxes. Let's first look at single-selection list boxes:

Normally, you'll let a user select from a list box. But if you want to highlight a default selection, you can use:

```
SendMessage (hWndList, LB_SETCURSEL, nIndex, OL) ;
```

Setting IParam to -1 in this call deselects all items.

You can also select an item based on its initial characters:

```
nIndex = (WORD) SendMessage (hWndList, LB_SELECTSTRING, wIndex, (LONG) szSearchString);
```

The wIndex given as the wParam parameter to the SendMessage call is the index following which the search begins for an item with initial characters that match szSearchString. A wIndex value of -1 starts the search from the top. SendMessage returns the index of the selected item or LB_ERR if no initial characters match szSearchString.

When you get a WM_COMMAND message from the list box (or at any other time), you can determine the index of the current selection using LB_GETCURSEL:

```
nIndex = (WORD) SendMessage (hWndList, LB_GETCURSEL, 0, 0L) ;
```

The nIndex value returned from the call is LB_ERR if no item is selected.

You can determine the length of any string in the list box:

```
nLength = (WORD) SendMessage (hWndList, LB_GETTEXTLEN, nIndex, 0L);
and copy the item into the text buffer:
```

In both cases, the *nLength* value returned from the call is the length of the string. The *szBuffer* array must be large enough for the length of the string and a terminating NULL. You may want to use LB_GETTEXTLEN to first allocate some local memory to hold the string (which you'll learn how to do in Chapter 8).

For a multiple-selection list box, you cannot use LB_SETCURSEL, LB_GETCURSEL, or LB_SELECTSTRING. Instead, you use LB_SETSEL to set the selection state of a particular item without affecting other items that may also be selected:

```
SendMessage (hWndList, LB_SETSEL, wParam, (LONG) wIndex) ;
```

The wParam parameter is nonzero to select and highlight the item and 0 to deselect it. If the IParam parameter is -1, all items are either selected or deselected. You can also determine the selection state of a particular item using:

```
wSelect = (WORD) SendMessage (hWndList, LB_GETSEL, wIndex, OL) ;
```

where wSelect is set to nonzero if the item indexed by wIndex is selected and 0 if it is not.

Receiving Messages from List Boxes

When a user clicks on a list box with the mouse, the list box receives the input focus. A parent window can give the input focus to a list box control by using:

```
SetFocus (hWndList) ;
```

When a list box has the input focus, the cursor movement keys, letter keys, and Spacebar can also be used to select items from the list box.

A list box control sends WM_COMMAND messages to its parent. The meanings of the wParam and IParam variables are the same as for the button and edit controls:

wParam Child window ID
LOWORD (*IParam*) Child window handle
HIWORD (*IParam*) Notification code

The notification codes and their values are as follows:

LBN_ERRSPACE -2 LBN_SELCHANGE 1 LBN_DBLCLK 2

The list box control sends the parent window LBN_SELCHANGE and LBN_DBLCLK codes only if the list box window style includes LBS_NOTIFY.

The LBN_ERRSPACE code indicates that the list box control has run out of space. The LBN_SELCHANGE code indicates that the current selection has changed; these messages occur as the user moves the highlight through the list box, toggles the selection state with the Spacebar, or clicks an item with the mouse. The LBN_DBLCLK code indicates that a list box item has been double-clicked with the mouse. (The notification code values for LBN_SELCHANGE and LBN_DBLCLK refer to the number of mouse clicks.)

Depending on your application, you may want to use either LBN_SELCHANGE or LBN_DBLCLK messages or both. Your program will get many LBN_SELCHANGE messages, but LBN_DBLCLK messages occur only when the user double-clicks with the mouse. If your program uses double-clicks, you'll need to provide a keyboard interface that duplicates LBN_DBLCLK.

A Simple List Box Application

Now that you know how to create a list box, fill it with text items, receive messages from the list box, and extract strings, it's time to program an application. The ENVIRON program, shown in Figure 7-7, uses a list box in its client area to display the name of your current MS-DOS environment variables (such as PATH, COMSPEC, and PROMPT). As you select a variable, the name and the environment string is displayed across the top of the client area.

```
environ.obj : environ.c

cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp environ.c

environ.exe : environ.obj environ.def

link4 environ, /align:16, /map, slibw, environ
```

```
/* ENVIRON.C -- Environment List Box */
#include <windows.h>
#include <stdlib.h>
#include <string.h>
#define MAXENV 256
long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG) ;
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
    HANDLE hInstance, hPrevInstance;
    LPSTR lpszCmdLine ;
           nCmdShow ;
    int
             char szAppName [] = "Environ" ;
    static
    HWND
             hWnd ;
    MSG
             msg ;
    WNDCLASS wndclass ;
    if (!hPrevInstance)
                              = CS HREDRAW | CS VREDRAW ;
         wndclass.style
         wndclass.lpfnWndProc = WndProc ;
         wndclass.cbClsExtra = 0 ;
         wndclass.cbWndExtra = 0;
wndclass.hInstance = hInstance;
         wndclass.hbrBackground = COLOR WINDOW + 1 ;
         wndclass.lpszMenuName = NULL ;
         wndclass.lpszClassName = szAppName ;
         if (!RegisterClass (&wndclass))
              return FALSE ;
     hWnd = CreateWindow (szAppName, "Environment List Box",
                        WS OVERLAPPEDWINDOW,
                        CW USEDEFAULT, 0,
```

Figure 7-7. The ENVIRON program

```
CW USEDEFAULT, 0, NULL, NULL, hInstance, NULL) ;
     ShowWindow (hWnd, nCmdShow) ;
     UpdateWindow (hWnd) ;
     while (GetMessage (&msg, NULL, 0, 0))
           TranslateMessage (&msg) ;
           DispatchMessage (&msg) ;
     return msg.wParam ;
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
     HWND
                   hWnd ;
     unsigned
                   iMessage ;
     WORD
                   wParam ;
     LONG
                   lParam ;
     static HWND hWndList, hWndText;
                   szBuffer [MAXENV + 1] ;
                   hDC ;
     TEXTMETRIC tm ;
     WORD
                   n ;
     switch (iMessage)
           case WM CREATE:
                 hDC = GetDC (hWnd) ;
                 GetTextMetrics (hDC, &tm) ;
                 ReleaseDC (hWnd, hDC) ;
                 hWndList = CreateWindow ("listbox", NULL,
                                  WS_CHILD | WS_VISIBLE | LBS_STANDARD,
                                  tm.tmAveCharWidth, tm.tmHeight * 3,
tm.tmAveCharWidth * 16 +
                                        GetSystemMetrics (SM_CXVSCROLL),
                                  tm.tmHeight * 5.
                                  hWnd, 1,
                                  GetWindowWord (hWnd, GWW HINSTANCE), NULL) ;
                hWndText = CreateWindow ("static", NULL,
WS_CHILD | WS_VISIBLE | SS_LEFT,
                                  tm.tmAveCharWidth, tm.tmHeight,
tm.tmAveCharWidth * MAXENV, tm.tmHeight,
                                  hWnd, 2,
                                  GetWindowWord (hWnd, GWW HINSTANCE), NULL) ;
                 for (n = 0 ; environ[n] ; n++)
                      if (strlen (environ [n]) > MAXENV)
                            continue ;
                      *strchr (strcpy (szBuffer, environ [n]), '=') = '\0';
SendMessage (hWndList, LB_ADDSTRING, 0, (LONG) szBuffer);
                break ;
           case WM SETFOCUS:
                SetFocus (hWndList) ;
                break :
```

Figure 7-7. Continued

```
NAME ENVIRON
DESCRIPTION 'Environment List Box Program (C) Charles Petzold, 1987'
STUB 'WINSTUB.EXE'
CODE MOVEABLE
DATA MOVEABLE MULTIPLE
HEAPSIZE 1024
STACKSIZE 4096
EXPORTS WndProc
```

ENVIRON creates two child windows: a list box with the style LBS_STANDARD and a static window with the style SS_LEFT (left-justified text). ENVIRON uses the *environ* variable (declared external in STDLIB.H) to obtain the list of environment strings, and it uses the message LB_ADDSTRING to direct the list box window function to place each string in the list box.

When you run ENVIRON, you can select an environment variable using the mouse or the keyboard. Each time you change the selection, the list box sends a WM_COMMAND message to the parent window, which is WndProc. When WndProc receives a WM_COMMAND message, it checks to see if wParam is 1 (the child ID of the list box) and if the high word of IParam (the notification code) is equal to LBN_SELCHANGE. If so, it obtains the index of the selection using the LB_GETCURSEL message and the text itself—the environment variable name—using LB_GETTEXT. ENVIRON uses the C function getenv to obtain the environment string corresponding to that variable and SetWindowText to pass this string to the static child window control, which displays the text.

Note that ENVIRON cannot use the index returned from LB_GETCURSEL to index the environ variable and obtain the environment string. Because the list box has an LBS_SORT style (included in LBS_STANDARD), the indices no longer match.

Listing Files

I've been saving the best for last: LB_DIR, the most powerful list box message. This fills the list box with a file directory list, optionally including subdirectories and valid disk drives:

SendMessage (hWndList, LB_DIR, wAttr, (LONG) lpszFileSpec);

Using file attribute codes

The wAttr parameter is a file attribute code. The least significant byte is the normal file attribute code when making MS-DOS function calls:

wAttr	Attribute	
0x0000	Normal file	
0x0001	Read-only file	
0x0002	Hidden file	
0x0004	System file	
0x0010	Subdirectory	
0x0020	File with archive bit set	55

The high byte provides some additional control over the items desired:

wAttr	Option	
0x4000	Include drive letters	
0x8000	Exclusive search only	

When the wAttr value of the LB_DIR message is 0x0000, the list box lists normal files, read-only files, and files with the archive bit set. This is consistent with the logic used by MS-DOS function calls to find files. When the value is 0x0010, the list includes child subdirectories in addition to these files; this list is the equivalent of that displayed by the Directory command or by Windows' MS-DOS Executive. A value of 0x4010 expands the 0x0010 list to include all valid drives; for many Windows programs, this is the list in the dialog box called up by selecting Open from the program's File menu. To list all files, child subdirectories, and drives, you set the wAttr value to 0x4037.

Setting the topmost bit of wAttr lists the files with the indicated flag while excluding normal files. For a Windows file backup program, for instance, you might want to list only files that have been modified since the last backup. Such files have their archive bits set, so you would use 0x8020. A value of 0x8010 lists only subdirectories; 0xC000, only valid disk drives; and 0xC010, subdirectories and valid disk drives but no files.

Ordering file lists

The *IParam* parameter is a far pointer to a file specification string such as "*.*". This file specification does not affect the subdirectories that the list box includes.

You'll want to use the LBS_SORT message for list boxes with file lists. The list box will first list files satisfying the file specification and then (optionally) list valid disk drives in the form:

[-A-]

and (also optionally) subdirectory names. The first subdirectory listing will take the form:

1..1

This "double-dot" subdirectory entry lets the user back up one level toward the root directory. (The entry will not appear if you're listing files in the root directory.) Finally, the specific subdirectory names are listed in the form:

[SUBDIR]

If you do not use LBS_SORT, the filenames and subdirectory names are intermixed and the drive letters appear at the bottom.

As you may know, Microsoft C 4.0 does not include functions corresponding to the "find first" and "find next" MS-DOS function calls. However, you can duplicate these functions by creating a child window list box that does not include the WS_VISIBLE style. Such a window is not displayed on the screen, but you can still send it an LB_DIR message and extract the filename and directory strings. When you're done, you can destroy the child window with a DestroyWindow call.

A head for Windows

A well-known UNIX utility called *head* displays the beginning lines of a file. Let's use a list box to write a similar program for Windows. HEAD, shown in Figure 7-8, lists all files and child subdirectories in the list box. You can choose a file to display by double-clicking on the filename with the mouse or by pressing the Enter key when the filename is selected. You can also change the subdirectory using either of these methods. The program displays up to 2 KB of the beginning of the file in the right side of the client area of HEAD's window.

HEAD

```
head.obj : head.c
cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp head.c
head.exe : head.obj head.def
link4 head, /align:16, /map, slibw, head
```

Figure 7-8. The HEAD program

```
/* HEAD.C -- Displays beginning (head) of file */
#include <windows.h>
#include <io.h>
#include <string.h>
#include <direct.h>
#define MAXPATH
                       100
#define MAXREAD
                      2048
long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG);
long FAR PASCAL ListProc (HWND, unsigned, WORD, LONG);
       sReadBuffer [MAXREAD] ;
char
FARPROC lpfnoldList ;
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
     HANDLE hInstance, hPrevInstance;
     LPSTR
                  lpszCmdLine ;
     int
                  nCmdShow ;
     static char szAppName [] = "Head" ;
     HWND hWnd;
     MSG
                  msq ;
     WNDCLASS wndclass;
     if (!hPrevInstance)
          wndclass.style
                                   = CS HREDRAW | CS VREDRAW ;
          wndclass.lpfnWndProc = WndProc;
          wndclass.cbClsExtra = 0;
wndclass.cbWndExtra = 0;
wndclass.hInstance = hInstance;
          wndclass.hCon = LoadCon (NULL, IDI APPLICATION);
wndclass.hCursor = LoadCursor (NULL, IDC_ARROW);
          wndclass.hbrBackground = COLOR WINDOW + 1 ;
          wndclass.lpszMenuName = NULL ;
          wndclass.lpszClassName = szAppName ;
          if (!RegisterClass (&wndclass))
                return FALSE ;
     hWnd = CreateWindow (szAppName, "File Head",
                           WS_OVERLAPPEDWINDOW | WS_CLIPCHILDREN,
                           CW USEDEFAULT, 0,
                           CW USEDEFAULT, O.
                           NULL, NULL, hinstance, NULL) ;
     ShowWindow (hWnd, nCmdShow) ;
     UpdateWindow (hWnd) ;
     while (GetMessage (&msg, NULL, 0, 0))
          TranslateMessage (&msg) ;
          DispatchMessage (&msg) ;
     return msg.wParam ;
```

```
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
                  hWnd ;
     HWND
                        iMessage ;
     unsigned
     WORD
                       wParam ;
      LONG
                        lParam ;
     static BOOL bValidFile ;
static char szFile [16] ;
static HWND hWndList, hWndText ;
      static OFSTRUCT ofs ;
      static RECT
                       rect ;
                        szBuffer [MAXPATH + 1] ;
      char
      HDC
                      hDC ;
                       iHandle, i, iCount ;
      int
      PAINTSTRUCT
                    ps ;
      TEXTMETRIC
                        tm :
      switch (iMessage)
           case WM CREATE:
                 hDC = GetDC (hWnd) ;
                 GetTextMetrics (hDC, &tm) ;
                 ReleaseDC (hWnd, hDC) ;
                 rect.left = 20 * tm.tmAveCharWidth ;
                 rect.top = 3 * tm.tmHeight;
                 hwndList = CreateWindow ("listbox", NULL,
WS_CHILDWINDOW | WS_VISIBLE | LBS_STANDARD,
                                   tm.tmAveCharWidth, tm.tmHeight * 3,
tm.tmAveCharWidth * 13 +
                                        GetSystemMetrics (SM CXVSCROLL),
                                   tm.tmHeight * 10,
                                   GetWindowWord (hWnd, GWW_HINSTANCE), NULL) ;
                 hWndText = CreateWindow ("static", getcwd (szBuffer, MAXPATH),

WS_CHILDWINDOW | WS_VISIBLE | SS_LEFT,
                                                                    tm.tmHeight,
                                   tm.tmAveCharWidth,
                                   tm.tmAveCharWidth * MAXPATH, tm.tmHeight,
                                   hWnd, 2,
                                   GetWindowWord (hWnd, GWW_HINSTANCE), NULL) ;
                  lpfnOldList = (FARPROC) GetWindowLong (hWndList, GWL_WNDPROC) ;
                  SetWindowLong (hWndList, GWL WNDPROC,
                              (LONG) MakeProcInstance ((FARPROC) ListProc,
GetWindowWord (hWnd, GWW_HINSTANCE)));
                  SendMessage (hWndList, LB_DIR, 0x37, (LONG) "*.*");
                  break ;
           case WM SIZE:
                  rect.right = LOWORD (1Param) ;
                  rect.bottom = HIWORD (1Param) ;
                  break ;
            case WM SETFOCUS:
                  SetFocus (hWndList) ;
                  break ;
```

```
case WM COMMAND:
           if (wParam == 1 && HIWORD (1Param) == LBN DBLCLK)
                if (LB ERR == (i = (WORD) SendMessage (hWndList,
                                                LB GETCURSEL, 0, 0L)))
                      break ;
                SendMessage (hWndList, LB_GETTEXT, i,
                                      (LONG) (char far *) szBuffer) ;
                if (-1 != OpenFile (szBuffer, &ofs, OF EXIST | OF READ))
                      bValidFile = TRUE ;
                      strcpy (szFile, szBuffer) ;
                      getcwd (szBuffer, MAXPATH) ;
                      if (szBuffer [strlen (szBuffer) - 1] != '\\')
                     strcat (szBuffer, "\");
SetWindowText (hWndText, strcat (szBuffer, szFile));
                else
                      bValidFile = FALSE ;
                      szBuffer [strlen (szBuffer) - 1] = '\0';
                     chdir (szBuffer + 1) ;
                     getcwd (szBuffer, MAXPATH) ;
                      SetWindowText (hWndText, szBuffer) ;
                     SendMessage (hWndList, LB_RESETCONTENT, 0, 0L) ;
                     SendMessage (hWndList, LB_DIR, 0x37, (LONG) "*.*");
                InvalidateRect (hWnd, NULL, TRUE) ;
          break ;
     case WM PAINT:
          hDC = BeginPaint (hWnd, &ps) ;
          if (bValidFile && -1 != (iHandle =
                     OpenFile (szFile, &ofs, OF_REOPEN | OF_READ)))
                i = read (iHandle, sReadBuffer, MAXREAD) ;
                close (iHandle) ;
                DrawText (hDC, sReadBuffer, i, &rect, DT_WORDBREAK | DT_EXPANDTABS | DT_NOCLIP | DT_NOPREFIX);
          else
                bValidFile = FALSE ;
          EndPaint (hWnd, &ps) ;
          break ;
     case WM DESTROY:
          PostQuitMessage (0) ;
          break ;
          return DefWindowProc (hWnd, iMessage, wParam, 1Param) ;
return OL ;
```

```
NAME HEAD
DESCRIPTION 'File Head Program (C) Charles Petzold, 1987'
STUB 'WINSTUB.EXE'
CODE MOVEABLE
DATA MOVEABLE MULTIPLE
HEAPSIZE 1024
STACKSIZE 4096
EXPORTS Windproc
ListProc
```

In ENVIRON, when we selected an environment variable—either with a mouse click or with the keyboard—the program displayed an environment string. If we used this select-display approach in HEAD, however, the program would be too slow because it would continually need to open and close files as you moved the selection through the list box. Instead, HEAD requires that the file or subdirectory be double-clicked. This presents a bit of a problem because list box controls have no automatic keyboard interface that corresponds to a mouse double-click. As we know, we shouldn't write Windows programs that require a mouse.

The solution? Window subclassing, of course. The list box subclass function in HEAD is called *ListProc*. It simply looks for a WM_KEYDOWN message with *wParam* equal to VK_RETURN and sends a WM_COMMAND message with an LBN_DBLCLK notification code back to the parent. The WM_COMMAND processing in *WndProc* uses the Window function *OpenFile* to check for the selection from the list. If *OpenFile* returns an error, the selection is not a file, so it's probably a subdirectory. HEAD then uses *chdir* to change the subdirectory. It sends a LB_RESETCONTENT message to the list box to clear out the contents and a LB_DIR message to fill it with files from the new subdirectory.

The WM_PAINT message processing in *WndProc* opens the file using the Windows *OpenFile* function. This returns an MS-DOS handle to the file that can be passed to the normal C functions *read* and *close*. The contents of the file are displayed using *DrawText*.

2 KB of Wasted Space

HEAD includes a 2 KB array called *sReadBuffer* that is needed only briefly, when the contents of the file are read and passed to *DrawText*. But this array remains in the program's data segment during the entire time this program is running. Wouldn't it make more sense to allocate that memory before the *read* call and free it up after *DrawText*?

Yes, it would. For that reason we can no longer avoid the subject of Windows memory management. It's not an easy subject, but let's begin.

SECTION III

USING RESOURCES



Chapter 8

Memory Management

Multitasking without memory management is like having a party in a closet: You may be able to accommodate some of the earlier arrivals, but once everybody starts mingling, some toes are going to get smashed. Windows includes a sophisticated memory management scheme that implements in software some of the memory management features you might expect to find in an operating system based on the "protected-mode" operation of the 80286 microprocessor. Here are some examples of Windows' memory management:

- When Windows runs multiple instances of a program, it uses the same code segment and the same resources for each instance. (Resources include icons, cursors, menu templates, and dialog box templates, all of which are covered in the next three chapters.) In most cases, Windows requires only that data segments be unique for each instance of a program.
- Much of the memory allocated within Windows is moveable, including (in most cases) the memory allocated for a program's code segments, data segments, and resources.
- Code segments and resources are often "demand-loaded": Windows does not load them into memory until a program specifically needs them.
- Code segments and resources are often discardable: When Windows needs to free some memory, it discards the segments from memory and later reloads them from the program's EXE file as the program requires.

These memory management features allow Windows to run several large programs in a memory space that might not be large enough for even one of the programs under a less ambitious memory management scheme. If you initially feel a little queasy when thinking about Windows moving your program around in memory, that's good. It means that you're already aware that this is not an easy feat. You must keep this fact in mind in order to write programs that run without problems. You must cooperate with Windows' memory management. That's what we'll look at in this chapter.

SEGMENTED MEMORY, INTEL STYLE

When Windows runs on the IBM PC and compatibles, it organizes memory in "segments." So before we proceed, let's quickly review the segmented memory architecture of the Intel 8086 family of microprocessors. This family includes the 8088 found in the PC and XT, the 8086 and the 80186 found in some compatibles, the 80286 found in the PC-AT, and the 80386. (Current versions of MS-DOS run the 80286 and 80386 microprocessors in "real mode," making them essentially compatible with the 8086.)

When an 8086-family microprocessor accesses memory, the address consists of two parts, a 16-bit segment address and a 16-bit offset address. The 16-bit segment address is shifted 4 bits to the left and added to the offset address. The resultant 20-bit physical address can access 1 MB (megabyte) of data:

Four internal registers of the microprocessor hold segment addresses. These segment registers are called CS (code segment), DS (data segment), SS (stack segment), and ES (extra segment).

Software for the 8086 family runs most efficiently when the segment addresses are held constant and all addressing is done by varying the offset addresses. The offset addresses generated by the microprocessor include the instruction pointer (IP), which accesses code in combination with the CS register; the stack pointer (SP) and base pointer (BP), which access the stack in combination with the SS register; and the BX (base), SI (source index), and DI (destination index) registers, which access data, most often in combination with the DS or ES register. An address that uses only the offset address with an implied segment address (the current segment address) is called a "near pointer" or sometimes a "short pointer." An address that uses both the segment and offset addresses is called a "far pointer" or a "long pointer."

For any particular segment address, the offset address can vary over a 64 KB range from 0000H through FFFFH. A block of memory that is based on a particular segment address is called (appropriately enough) a "segment." People used to think of segments as 64 KB blocks of memory, but this definition is becoming less common. Now we say that segments can be any size up to 64 KB. Sometimes the size of a segment (or the size of an area of memory larger than 64 KB) is given in terms of "paragraphs." A paragraph is 16 bytes. Memory allocated for a segment is often a multiple of 16 bytes, because a segment must begin on a 16-byte boundary of physical memory. (When the segment register is shifted left four bits, the bottom four bits are 0.)

The use of segments is central to Windows' memory organization. The entire memory space controlled by Windows is divided into segments of various lengths. Some of these segments contain code, and others contain data.

MEMORY ORGANIZATION IN WINDOWS

The entire memory area that Windows controls is called "global memory" or the "global heap." This area begins at the location where MS-DOS first loads Windows into memory and ends at the top of available memory, which most often is the top of physical memory. (In C programming, the word *global* usually refers to variables or functions in one source code file that can be referenced from functions in another source code file of the same program. That is *not* the meaning of *global* here. In this discussion of Windows' memory organization, the word *global* instead means "everything.") Every block of memory allocated from the global heap is a segment. Global memory not currently allocated is called "free memory."

A Windows program can have one or more code segments and one or more data segments. (The example programs shown so far have only one of each.) When Windows loads a program into memory, it allocates at least one segment from the global heap for code and one segment for data. When the program begins to execute, the microprocessor's CS register is set to the segment address of the code segment that contains the entry point of the program. The DS and SS registers are set to the segment address of the program's automatic, or default, data segment, which is the data segment that contains the stack. (The combination of the data and the stack into one segment referenced by both DS and SS is normal for C compilers. DS is used to reference data declared as static; SS is used to reference data on the stack, which includes local nonstatic data and arguments passed to functions. This approach allows near pointers to be used for function parameters. The function doesn't have to know whether it's dealing with static data or stack data. Problems related to unequal DS and SS segment registers are discussed in Chapter 18, "Dynamic Link Libraries.")

When loading a program, Windows also allocates two other segments from the global heap for program overhead. One of these segments contains the header portion of the program's .EXE file. This segment is used for all instances of a program, so it is allocated only for the first instance. The other segment contains information unique to each instance, such as the program's command line string and the program's current subdirectory. When a program loads resources (such as icons, cursors, or menu templates) into memory, each resource gets its own segment in the global heap. A program may itself also allocate some memory from the global heap.

If a program has only one code segment, then any calls it makes to functions within the program are compiled as near calls. The CS code segment register remains the same. However, when a program calls a Windows function, the Windows function is in a different code segment. This situation requires that the program generate a far call, which is the reason that all Windows functions (and all functions within your program that are called by Windows) must be declared as far.

A Windows program that has one data segment can use near pointers to access memory within that data segment. However, when a Windows program passes a pointer to a Windows function, the pointer must be a far (or long) pointer; otherwise, the code that contains the Windows function will use its own data segment. The far pointer is required for the Windows function to access the data within your program's data segment.

Fixed and Moveable Segments

Every segment in Windows' total memory space is marked with certain attributes that tell Windows how to manage the segment. First and foremost, segments are marked as either "fixed" or "moveable." Windows can move moveable segments in memory if necessary to make room for other memory allocations. When Windows moves a segment in memory, all existing near pointers to that segment continue to be valid, because near pointers reference an offset from the beginning of a segment. However, far pointers become invalid when the segment they reference is moved. A fixed segment cannot be moved in memory. Segments must be marked as fixed if Windows is incapable of modifying an existing far pointer to the segment.

Most segments—including the segments allocated for your program's code and data—
are moveable, but some exceptions exist. Whenever Windows gives your program a far
pointer, the pointer references a fixed data segment. For instance, when your Windows program begins executing, Windows passes a parameter to WinMain that we call lpszCmdLine.
This is a far pointer to an area of memory that contains a command line argument for the program. I mentioned above that this command line string is stored in a program overhead

segment that Windows creates for each instance of a program. This program overhead segment must be fixed. If Windows moves it, the command line pointer passed to your program becomes invalid.

Here's one way Windows deals with moveable segments: You've seen how Windows and your programs use numbers called "handles." In many cases, the handles are really near pointers. Windows maintains a segment called BURGERMASTER (no kidding) that contains a master handle-to-memory table. The handle points to a small area of memory within BURGERMASTER that contains the segment address of the item that the handle references. When Windows moves the segment that contains the item, it can adjust the address in BURGERMASTER without invalidating the handle. BURGERMASTER is itself a moveable segment.

All non-Windows MS-DOS programs are assigned fixed segments when they run under Windows. Windows cannot determine how these programs reference memory, so Windows has no choice but to make them fixed. However, you should try very hard to ensure that the code and data segments of your Windows programs (as well as any additional segments your programs allocate) are moveable segments. Fixed segments stand like brick walls in memory space and clog up Windows' memory management. Users quickly learn which programs seem to use little memory (because they use moveable segments) and which programs seem to use a lot of memory (because they use fixed segments). Users have a name for programs that use a lot of memory. They say, "This program is a real pig." Your goal should be to write programs that are not pigs.

Discardable Memory

Moveable segments can also be marked as discardable. This means that when Windows needs additional memory space, it can free up the area occupied by the segment. Windows uses a "least recently used" (LRU) algorithm to determine which segments to discard when attempting to free up memory.

Discardable segments are almost always those that do not change after they are loaded. Code segments of Windows programs are discardable because (in most cases) programs do not modify their code segments. When Windows discards a code segment, it can later reload the code segment by accessing the .EXE file. Most of Windows' own code in the USER and GDI modules and various driver libraries is also discardable. (The KERNEL module is fixed. This is the module responsible for Windows' memory management.) Resources (such as dialog box templates, cursors, and icons) also are often marked as discardable. Again, Windows can simply reload the resource into memory by accessing the .EXE file that contains the resource.

Sometimes you'll see that a disk is being accessed when you move the mouse from the client area of one program to the client area of another. Why is this? Windows has to send mouse movement messages to the second application. If the program's code to process this message is not currently in memory, Windows must reload it from the disk file. If you have several large Windows programs loaded simultaneously, you will probably witness some "thrashing" (an inordinate amount of disk activity) as you move from program to program. Windows is reloading previously discarded segments.

Discardable segments must also be moveable segments, because discardable segments can be reloaded in a different area of memory than the area they occupied earlier. However, moveable segments are not always discardable segments. This is usually the case with data segments. Windows definitely cannot discard a program's automatic data segment, because the segment always contains read-write data and the stack.

Many people are under the impression that Windows also swaps memory—that is, that when Windows needs additional memory, it saves some portion of memory on the disk and reloads it at a later time. This is not so. Windows swaps memory to disk only when running non-Windows programs (otherwise known as "old applications"). When Windows loads these old applications from disk back into memory, it must load them at the same memory address they occupied previously. This fact explains the common recommendation that you load the largest program first when running old applications. Doing so reserves a block of fixed memory that Windows can use for all old applications. If you later load in an old application larger than this block, Windows must allocate another fixed segment for it.

The Global Memory Layout

As I noted before, global memory ranges from the spot where MS-DOS first loads Windows to the top of available memory. At the bottom of global memory (the area with the lowest memory address), Windows allocates fixed segments. Fixed segments are allocated from the bottom up. At the top of global memory, Windows allocates discardable segments such as program code segments. (Remember that discardable segments are also moveable segments.) Discardable segments are allocated from the top down.

Between fixed segments and discardable segments, Windows allocates moveable but nondiscardable segments such as program data segments. The largest block of free memory is usually located below the discardable segments. The memory layout looks something like that shown in Figure 8-1, with arrows indicating the direction in which the areas expand. When Windows needs to allocate a fixed segment, it starts searching from the bottom up for a sufficiently large free block below the area of moveable segments. If it can't find one, it starts moving moveable segments up in memory to make room. If that doesn't work, Windows begins discarding discardable segments, based on an LRU (least recently used)




Figure 8-1. The organization of global memory

algorithm, again moving moveable segments. To allocate moveable but nondiscardable segments, Windows searches the free memory area below the discardable segments. If it doesn't find enough room, Windows moves other moveable segments down in memory and eventually starts discarding discardable segments.

Within the area of discardable memory, Windows maintains a space large enough to accommodate the largest code segment of every currently running program. Windows never runs out of memory space when reloading code segments. However, Windows can run out of memory space when a program attempts to allocate global memory or load a resource. Sometimes it can be a little tricky to deal with this problem—you may need a text string or icon not currently in memory to display an error message. If your program needs to report that it is low on memory, you can use a message box. Windows keeps in memory all the code necessary to create a message box. You'll want to use the MB_SYSTEMMODAL flag to prevent the user from switching to another application. The IDI_HANDICON (which is supposed to accompany messages of severe problems) is also always in memory. The text message in the message box should either be in your default data segment or be a string resource that has previously been copied into your data segment.

Local Memory

Every Windows program has at least one data segment called the default, or automatic, data segment. A program's DS and SS segment registers both point to this segment. In contrast to the "global memory" that Windows manages, this automatic data segment is called your program's "local memory." Within Windows' global memory organization, your program's automatic data segment is most often a moveable but nondiscardable segment.

If you look at the .MAP file that LINK4 produces for any of the sample programs presented so far, you'll see that all data are in a group called DGROUP. Although there seem to be more than 15 segments in this group, DGROUP defines a physical segment that encompasses all these separate segments. The separate segments are no longer treated as segments when the linker combines them in a group. The offset addresses are adjusted to be offsets from the beginning of the group. In both regular MS-DOS C programs and Windows programs, the memory within DGROUP is organized into four areas, as shown in Figure 8-2. These four areas are described below:

- Initialized static data—This area contains initialized variables defined outside of functions, initialized static variables within functions, and explicit strings and floating-point numbers.
- Uninitialized static data—This area has uninitialized variables that are defined
 outside of functions and uninitialized variables defined as static within functions.
 In accordance with C standards, all uninitialized static variables are initialized to 0
 when the data segment is created in memory.
- Stack—This area is used for "automatic" data items defined within functions (variables not defined as static), for data passed to functions, and for return addresses during function calls.
- Local heap—This is free memory available for dynamic allocation by the program.



Figure 8-2. The organization of memory in DGROUP

The module definition (.DEF) file specifies your program's stack and local heap size:

HEAPSIZE 1024 STACKSIZE 4096

If you do not include these statements in your module definition file, the defaults are 0 for each. A STACKSIZE of at least 40% bytes is recommended for Windows programs.

In a regular C program, you can allocate memory from the local heap using the *malloc* and *calloc* functions. In Windows programs, you can also allocate memory from the local heap, but you'll want to use the Windows memory allocation functions rather than the C functions. When you use Windows functions to allocate local memory, Windows organizes the local heap just like global memory, as shown in Figure 8-3. Although the stack is fixed in

size, Windows can dynamically expand the local heap if you attempt to allocate more local memory than is specified in your module definition file. Windows can even move your data segment if that is necessary to expand the local heap.




Figure 8-3. The organization of the local heap

CODE AND DATA SEGMENTS

All the Windows programs shown so far have one code segment and one data segment. Windows programs can also have multiple code and data segments. For larger programs, using multiple code segments is highly recommended because it helps relieve memory congestion in Windows. Using multiple data segments, on the other hand, is a real problem. Let's take a look at this interesting subject.

Small, Medium, Compact, Large, and Huge

When we speak about a program having one code or data segment or multiple code or data segments, we're referring to "memory models." Microsoft C 4.0 supports five memory models:

Model	Code Segments	Data Segments	
Small	1	1	
Medium	Multiple	1	
Compact	1	Multiple	
Large	Multiple	Multiple	
Huge	Multiple	Multiple	

Command line switches of the compiler determine the memory model you use. The small memory model is the default, but programs that have more than 64 KB of code must contain two or more code segments, and programs that have more than 64 KB of data must

contain two or more data segments. In medium-model and large-model programs, all functions (unless explicitly declared as near) are far, and the compiler generates far calls for them. In compact-model and large-model programs, all data references use far pointers.

The small, compact, medium, and large models each have their own C libraries. The medium-model and large-model libraries contain functions that assume they have been called from another segment. The functions in the compact-model and large-model libraries always assume they have been passed long pointers to data. The huge model is essentially the same as the large model, except that individual data items may be greater than 64 KB. The huge model has no library support. (For instance, you can create a 128 KB character string in the huge model, but you cannot use *strlen* to find the length of it.)

Most small Windows programs are compiled as small model, with one code segment and one data segment. Strictly speaking, however, Windows programs are really "mixed-model" programs, because they extensively use the *near* and *far* keywords. Windows programs make far calls to Windows functions, and Windows makes far calls to functions within a program, such as window functions or call-back functions. All data pointers passed between a program and Windows are far pointers.

Windows programs can also be compiled as medium-model programs. You can try this out on any of the programs shown so far. You need to make two changes to the make file:

- Add the -AM switch to the compile step. This compiles for the medium model.
- Change SLIBW to MLIBW in the link step. This is the library that contains the Windows-specific start-up code and import references to resolve calls to Window functions.

Delete the .OBJ file and run MAKE. You'll find that the .EXE file is somewhat larger than before because all the functions within your program—not only the window function and callback functions—now require far calls.

Multiple Code Segments

The medium model doesn't make sense for a small program, and it comes into play only when you have more than one source code module. But then it starts making a lot of sense. In the medium model, each source code module becomes a different code segment. Each of these code segments can be moveable and discardable. The amount of space required to fit your code into memory is the size of the largest code segment.

For instance, the approximately 160 KB of code in Windows WRITE is distributed among 78 separate moveable and discardable code segments. The largest code segment in WRITE is about 8 KB. Thus, when memory is limited, WRITE can continue to run with only an

8 KB code space. As program logic within WRITE moves from segment to segment, the code segment currently in memory can be discarded and a new one loaded in.

If you like, you can think of the medium model as a simplified overlay manager: You split your program into multiple source code modules and compile for the medium model. Windows does the rest. In order to work efficiently, the medium-model approach requires some planning. The functions in each of your source modules should be organized in functional groups. When your program is dealing with such routine matters as processing mouse messages, for example, it should not have to load several code segments to get from the top of the window function to the bottom.

While using the medium model is certainly the easiest approach to take with a large program, it is not the most efficient. As you'll see shortly, when you run the Microsoft C Compiler with the -Gw switch (the Windows switch), the compiler adds some extra prolog code to all far functions. Only those functions actually called by Windows (such as window functions or call-back functions) need this prolog code, however. When all the functions in your program are far functions (as they are in the medium model), this extra code can add up to a significant waste of space.

One approach to reduce wasted space in a medium-model program is to define all functions used only within a module as near functions. Another solution is to use a mixed model with a small model as a base. Let's assume you have five source code modules:

- Module 1 contains WinMain, the message loop, your window function, and most message processing.
- Module 2 contains one function that has all initialization code. This function is called by WinMain from Module 1 before entering the message loop.
- Module 3 contains one function called from your window function and several other functions called only within this module.
- Module 4 also contains a function called from your window function and several other functions called only within this module. This module also calls a function in Module 5.
- Module 5 contains a function called from Module 4 and several other functions called only within this module.

You can organize this program into four segments, with Modules 4 and 5 in a single segment. Within each module, you explicitly define as far any function called from outside the segment. This involves one function each in Modules 2, 3, and 4. In the modules that call these

functions, the functions must be declared as far using the function name prefaced by FAR near the top of the program.

You compile each module for the small model, except that you assign one code segment name to Module 2, another to Module 3, and yet another to Modules 4 and 5. These names are assigned by including the -NT ("name the text segment") switch when compiling. Each module with the same code segment name is in the same segment. Now you have far functions only where you need them—for functions that are called from another segment. For a full-scale example of this technique, look at the CARDFILE program included with the Windows Software Development Kit.

As you can see, this mixed-model approach is more of a headache than the mediummodel approach. It requires that you figure out which functions must be declared far and which can be near. It also has an additional problem: You can call normal C library routines from only one segment—the segment that gets the default segment name _TEXT when you compile without the -NT switch.

What About the Compact and Large Models?

Windows programmers who require more than 64 KB of data in their programs might be feeling a little nervous at this point. They have a right to be, because the compact and large models are not recommended for Windows programs. This doesn't mean they can't be used, however. The Windows Software Development Kit includes libraries called CLIBW.LIB and LLIBW.LIB, so obviously the compact and large models are legal. However, compact-model and large-model programs are subject to a very strict penalty: The data segments must be fixed in memory. They cannot be flagged as moveable.

Why this restriction? There are various reasons; here's an easy example that illustrates one of them. Suppose that somewhere within your program you define a static pointer that looks like this:

char *pointer ;

Because you're compiling for a compact or large model, this is a far pointer. During your program's execution, you assign a value to that pointer. If the pointer references a moveable data segment, then the value of the pointer must be adjusted when Windows moves the data segment it references. But the compiler and linker will not even generate a relocation address for that pointer because it's not initialized.

Program developers who cry "but I need the large model" should consider the alternatives made evident by existing Windows applications. For instance, the 480 KB PM.EXE file for Aldus's PageMaker version 1.00 contains 99 segments—98 code segments and 1 data segment. If PageMaker doesn't need the large model, then you probably don't either. If your program needs more than 64 KB of data, you have alternatives to using the compact or large model. Here they are:

- If your program uses large blocks of uninitialized data, do not define these data as variables within the program. Instead, use the Windows GlobalAlloc function (discussed later in this chapter) to allocate a block of moveable memory outside your program.
- If your program uses large blocks of initialized read-only data (the most obvious example is "help" text), make the data a discardable "user-defined resource" (discussed in Chapter 9) to be loaded from the disk only when necessary. This keeps the data out of memory when not needed.
- If your program uses large blocks of initialized read-write data, put the initialized data in a discardable "user-defined resource" and transfer the data to a global memory block allocated with GlobalAlloc.

Avoiding Movement Problems

We have been creating small Windows programs for several chapters now and have not run into problems when Windows has moved the code and data segments in memory. Here are some general rules for continuing to avoid problems:

- Use the small model or medium model.
- Don't store any far pointers to data except those that Windows gives you. The
 lpszCmdLine parameter passed to *WinMain* is OK. The far addresses returned
 from *GlobalLock* (discussed later in this chapter) and *LockResource* (discussed in
 Chapter 9) point to fixed data until you specifically unlock the data, so these are
 legitimate also. Some window messages (WM_CREATE, for instance) have *lParam* values that are far pointers. Use these pointers only for the duration of the message.
- When you call Windows functions, you must often pass far pointers to data that are
 within your data segment. But don't declare far pointers and assign them far
 addresses to local data items and then later use the far pointers when calling
 Windows functions. Instead, cast the near pointers into far pointers when you call
 the functions, or let the compiler do this casting for you.

- Don't store or use any far pointers to code, except for pointers to functions that are specifically declared as far or far pointers returned from MakeProcInstance.
 (Pointers to functions in medium-model programs are also OK.)
- When you need to give Windows a far pointer to a function for a call-back function
 (as discussed in Chapter 6), a window subclassing function (as discussed in Chapter
 7), or a dialog box function (as discussed in Chapter 11), obtain the pointer from
 MakeProcInstance. The function must be declared as FAR PASCAL and included in
 the EXPORTS section of your module definition file.

Although these rules are numerous and important, don't let them drive you to paranoia. Keep in mind that Windows is nonpreemptive. Windows will not pull the rug out from under you by interrupting your code. Windows will move or discard your code segments only when you make a Windows call. Windows will not move your data segment except when you make a few select Windows calls. If you have a long stretch of code between two Windows calls, you can be as carefree as you like in that code without worrying about sudden movements.

Program Segment Attributes

I have been talking about program segments that are fixed, moveable, and discardable. These characteristics are called "segment attributes." To tell Windows the attributes you desire of your program segments, you use the CODE, DATA, and SEGMENTS statements in the module definition file. During linking, LINK4 encodes the attributes for each program segment into a 16-bit flag and stores this flag in the segment table of the .EXE file. Windows has access to these segment attributes when loading your code and data segments. The sample programs presented so far contain these two lines in their module definition files:

CODE MOVEABLE DATA MOVEABLE MULTIPLE

We have not yet encountered the SEGMENTS statement.

The CODE statement applies to all code segments within your program that are not explicitly listed in the SEGMENTS statement. Similarly, the DATA statement applies to all data segments except those listed in the SEGMENTS statement. The format of the CODE and DATA statements is somewhat confusing, because there are different default attribute types, depending on whether the CODE or DATA statement is actually present in the module definition file. These are the CODE statement segment attributes that Windows recognizes:

Attribute	Default if CODE Statement	Default if No CODE Statement	Option
Load	LOADONCALL	PRELOAD	
Memory	FIXED	MOVEABLE	
Discardable			DISCARDABLE

The "load" attribute tells Windows when to load the segment. PRELOAD means that the code segment (or segments) should be loaded at the time the program begins execution. A LOADONCALL segment will be loaded into memory the first time it is needed. By default we have been using LOADONCALL in the sample programs. For a program with a single code module, it really doesn't matter which you use. For programs with multiple code modules, you should use PRELOAD for segments that are required when the program first starts up (for instance, those that do initialization from *WinMain*) and LOADONCALL for the other code segments. To specify different attributes for multiple code segments, you must use the SEGMENTS statement discussed later.

The "memory" attribute determines whether the code segments are fixed or moveable. If you're writing normal Windows programs, you should have no problem specifying MOVEABLE. (Device drivers that must process hardware interrupts are another matter. These usually require one fixed code segment.) Despite the presence of the DISCARDABLE keyword, code segments flagged as MOVEABLE are always discardable, whether DISCARDABLE is used or not.

The DATA statement segment attributes that Windows recognizes are shown below:

Attribute	Default if DATA Statement	Default if No DATA Statement	Option
Load	LOADONCALL	PRELOAD	
Memory	FIXED	MOVEABLE	
Discardable			DISCARDABLE
Instance	MULTIPLE	MULTIPLE	NONE
			INSTANCE (or SINGLE)

When your program has only one data segment and you follow the rules that allow the segment to be moved (such as not storing far pointers to itself), you should flag the data segment as MOVEABLE. You should not make this segment DISCARDABLE, because it contains your program's stack. Programs with more than one data segment must be marked as fixed. For Windows programs, you must use the MULTIPLE instance option. The NONE and INSTANCE options are for Windows libraries (discussed in Chapter 18), because Windows libraries can have only one instance. If the Windows library has a data segment, INSTANCE (or SINGLE) is used. If not, NONE is used.

The SEGMENTS statement lets you assign different segment attributes to other code and data segments within your program. The general form of the SEGMENTS statement is:

```
SEGMENTS segment-name [CLASS 'class-name'] [allocate] [attributes]
```

You'll probably use this statement most often if you create a medium-model program or a small-model program with multiple code segments. For a medium-model program, the C library functions and start-up code are in a code segment named _TEXT. Each source code module is assigned a different code segment name that by default is the filename of the source code

file followed by _TEXT. For instance, if you have three source code modules called PRO-GRAM.C, MODULEI.C, and MODULE2.C, the PROGRAM.EXE file has four code segments: _TEXT, PROGRAM_TEXT, MODULE1_TEXT, and MODULE2_TEXT.

If you do not include a SEGMENTS statement, all four code modules take on the attributes from the CODE statements. If you do include a SEGMENTS statement, however, your results might look something like this:

CODE MOVEABLE PRELOAD
SEGMENTS MODULE1_TEXT MOVEABLE LOADONCALL
MODULE2_TEXT MOVEABLE LOADONCALL

Now the _TEXT and PROGRAM_TEXT segments are PRELOAD and are loaded when the program first begins execution. MODULE1_TEXT and MODULE2_TEXT are LOADONCALL. Windows loads them only when they are needed.

If you use the SEGMENTS statement for data segments, you must include:

CLASS 'DATA'

By default, the class is CODE. You can also add a minimum allocation size to increase the size of the data segment when it's loaded into memory. Here are the attributes that Windows recognizes for the SEGMEN'TS statement:

Attribute	Default	Option	
Load	LOADONCALL	PRELOAD	
Memory	FIXED	MOVEABLE	
Discardable		DISCARDABLE	

HOW WINDOWS MOVES AND RELOADS PROGRAM SEGMENTS

In this section, I want to give you some insights into how Windows is able to move your program's code and data segments and (in the case of code segments) discard and later reload the segments. If you'd rather not know (or if the assembly language in the pages ahead looks like Greek to you), that's fine. But you're likely to see some of this code when debugging Windows programs, so it's better that you see it here first and understand what's going on. I'll be discussing the most general recommended case—a program that contains multiple moveable and discardable code segments and a single moveable data segment. Everything works a little differently (and more simply) when the segments are fixed and nondiscardable.

When a program has a single data segment, neither the code nor the data have to contain any explicit references to the segment address of the data. When a Windows program begins running, Windows has already set the DS and SS registers to the data segment. All pointers are near pointers. When the program needs the data segment address (for instance, for casting near pointers into far pointers when calling Windows functions), it simply uses the value of DS. (In contrast to this, when you run a regular .EXE program outside Windows, MS-DOS does not set DS to the program's data segment on entry to the program. The program must begin by executing code like this:

MOV AX, DGROUP MOV DS, AX

You'll never see code like this in a compiled Windows program.) If you cast a near data pointer into a far pointer and store the far pointer in a variable, you're storing the current value of the data segment address. If Windows moves the data segment, that far pointer will no longer be valid. That's why it is recommended that you not do this.

Windows moves a program's data segment only during certain Windows calls. Most often, movement of a data segment occurs during a *GetMessage* or *PeekMessage* call. Windows always returns the new values of DS and SS to the program when it returns from one of these calls.

Windows programs use the same segment for data and the stack. However, Windows libraries (including the USER, KERNEL, and GDI modules, as well as the drivers) have their own data segments but not their own stacks. They use the stack of the program calling the Windows function. Thus the stack segment address is always that of the currently running program, even if the program is calling a Windows function. When switching from one program to another, Windows must also switch the stack.

When Windows calls a function in your program (such as a window function, a window subclassing function, a call-back function, or a dialog box function), the stack segment address is set to your program's stack segment, but the data segment address is still the one used by the Windows library calling your function. For this reason, Windows must also include a facility so that programs retrieve their own data segments during one of these calls.

All these aspects of Windows' memory management—supporting multiple instances, moving code and data segments, and discarding and reloading code segments—are tied in together.

Special Treatment of Far Functions

When you compile a C program, the compiler inserts prolog and epilog code in each function. This code sets up a "stack frame" for the function. The function uses the stack frame to retrieve

parameters passed to the function on the stack and to temporarily store the function's own local variables. For a normal MS-DOS program, the prolog and epilog can be as simple as this:

```
PUSH BP
MOV BP,SP
SUB SP,x
[other program lines]
MOV SP,BP
POP BP
RET y
```

The value of x that the prolog subtracts from SP is the total size of the function's local nonstatic data (increased to the next even number).

After the three prolog instructions have been executed, the stack is organized as shown in Figure 8-4 (from higher addresses to lower). The function uses the BP register to reference both data passed to the function on the stack (which have positive offsets to BP) and local data declared within the function (which have negative offsets to BP). Function prologs can also include a call to the Windows function *chkstk* to check for stack overflow. If the function uses the SI and DI registers, these registers will also be saved on the stack because they can be used by the caller for *register* variables. The DS register must also be preserved during a function call.




Figure 8-4. The stack after execution of the three prolog instructions

For a function declared as near, the return address is only one word—the offset address. For far functions, the return address is two words. Functions declared as near and far normally have the same prolog and epilog, but the compiled function must take into account the size of the return address—one word or two—when accessing the parameters passed to the function.

At the end of the function, the value of SP is set equal to BP, and BP is popped off the stack to restore it to its original value. The function is now ready to return to the caller. This involves a near RET, or a far RET, depending on whether the function is near or far. If the function is also declared as *pascal*, the *y* value in the code above is the total size of parameters passed to the

function. Otherwise, y is not used, and the caller adjusts the stack pointer when the function returns.

That's a normal compilation. When you compile a Windows program with the -Gw switch (the Windows switch), every far function gets special prolog and epilog code that looks like this:

```
PUSH DS
POP AX
              ; set AX to DS
NOP
INC BP
PUSH BP
              ; save incremented BP on stack
MOV BP, SP
PUSH DS
             ; save DS on stack
MOV DS, AX
             ; set DS to AX
SUB SP,x
(other program lines)
SUB BP. 2
MOV SP,BP ; reset SP to point to DS on stack
POP DS
           ; get back DS
POP BP
              ; get back incremented BP
DEC BP
              ; restore BP to normal
RET V
```

Functions that are declared as near get the normal prolog and epilog even with the -Gw switch. Notice two points here: First, the prolog sets the value of AX equal to DS, saves the DS register on the stack, and then sets DS from AX. On exiting, DS is retrieved from the stack. That code is not doing anything (or anything harmful) except taking up unnecessary space. Second, the previous value of the BP register is incremented before being saved on the stack and decremented after it is retrieved from the stack. This certainly looks mystifying right now. Figure 8-5 shows what the stack frame looks like for far functions compiled with the -Gw compiler switch after the prolog code is executed.




Figure 8-5. The stack after execution of the special Windows prolog

When LINK4 creates the program's .EXE file, it treats every far function in a moveable code segment as a "moveable entry point." In the .EXE header, LINK4 builds an entry table that contains 6 bytes of information for every moveable entry point in the program. This information includes the segment ordinal number of the function—simply a sequential numbering of the program's segments—and the offset of the function within that segment. The entry table also includes the 2 bytes 0CDH and 3FH for every moveable entry point. These 2 bytes are actually the instruction INT 3FH. This same software interrupt shows up in non-Windows programs, where it is used for overlay management. In Windows, the interrupt performs a similar function in that it loads a program's code segment from disk into memory.

A flag in the entry table indicates if the far function was listed in the EXPORTS section of the module definition (.DEF) file. As I've discussed, the EXPORTS section of the .DEF file must list all far functions in your program that are called by Windows. These include window functions (such as the function I've been calling *WndProc*), call-back functions, window subclassing functions, and dialog box functions.

When your program's code contains references to the addresses of far functions, LINK4 has to leave the instruction incomplete. For example, if you call a far function, the compiler generates a far CALL instruction, but the address is not yet known because LINK4 doesn't know where the segment containing the function will be loaded in memory. LINK4 builds a relocation table in the .EXE file at the end of each code segment. This table lists all the references to far functions within your program as well as all references to Window functions.

Now that the compiler and LINK4 have done all these strange things to your program, it's ready for Windows to run the program and do its magic.

Windows Runs the Program

When Windows runs the first instance of a program, it loads the data segment and one or more code segments. Windows also builds two fixed segments for program overhead. One segment contains information unique to each instance of the program, such as the command line argument passed to the program and the program's current subdirectory. The other overhead segment, which is used for all instances of the program, contains a large chunk of the program's EXE file header, including the entry table. The entry table already has 6 bytes of data for every far function in your program. Windows expands each entry into 8 bytes. These entries, called "reload thunks," are small pieces of code that handle segment loading.

If the segment containing the far function has not yet been loaded into memory, the reload thunk for that far function looks like this:

```
SAR BY CS:[xxxx],1
INT 3F 01 yyyy
```

The first statement is part of Window's mechanism to determine if a segment is a candidate for discarding. The second statement calls Interrupt 3FH, the software interrupt that loads into memory the appropriate segment containing the function.

If the segment containing the far function is present in memory, the reload thunk looks like this:

```
SAR BY CS:[xxxx],1
JMP ssss:0000
```

The second instruction is a far jump instruction. The ssss:0000 segment and offset address points to the beginning of the far function in the loaded code segment.

The references in your program's code to far functions are listed in the segment's relocation table. Windows must insert the addresses of the far functions into your code. However, the addresses that Windows uses for this are not the actual addresses of the far functions but rather the addresses of the reload thunks for the far functions. Because the reload thunk is in fixed memory, Windows does not need to make any other changes to the code when moving the code segment that contains the far call or moving the code segment that the far call references. Windows needs to change only the ssss:0000 address in the reload thunk.

When the program calls a far function, it's actually calling the reload thunk. If the segment containing the far function is not currently in memory, the reload thunk executes the Interrupt 3FH loader that loads the segment into memory. Windows then alters the reload thunk to contain a JMP instruction to the function. Windows jumps back to the reload thunk, which then jumps to the actual function. When Windows discards a segment from memory, it changes the reload thunk from the JMP instruction back to the INT 3FH instruction. The next time a function in that segment is needed, the segment is reloaded.

The calls in your program to Windows functions are translated into far CALL instructions and are also listed in the segment's relocation tables. When Windows loads your code segment into memory, it also resolves the calls to Windows functions. For Windows functions in fixed code segments, Windows simply inserts the address of the Windows function into your code. Windows functions in moveable segments have their own reload thunks, and Windows inserts the addresses of these thunks into your code.

Windows also does something special with functions that have been listed in the EX-PORTS section of the program's module definition file. Windows modifies the function prolog of these functions when loading the segment into memory. It replaces the first 2 bytes of every exported far function with NOP (no operation) instructions. The prolog now looks like this in memory:

```
NOP
NOP
NOP
INC BP
PUSH BP ; save incremented BP on stack
MOV BP,SP
PUSH DS ; save DS on stack
MOV DS,AX ; set DS to AX
SUB SP,X
```

Those two NOPs make a big difference. Now the prolog saves the original value of DS and sets DS to AX. When this function is called, AX must already be set to the data segment that the function must use. This change makes the exported function unusable for normal calls to the function. This is why you cannot call your window function (or any other exported function) directly from within your program.

What MakeProcInstance Does

You've just seen that far functions listed in the EXPORTS section of your .DEF file become unsuitable for normal use when Windows loads them into memory. These functions require that the value of AX on entry be the program's data segment. This data segment is different for every instance of your program. You can do only one of two things with an exported far function:

 If the function is a window function, you can give Windows the address of the function in the window class structure when registering the window class with RegisterClass:

```
wndclass.lpfnWndProc = WndProc ;
```

 If the function is a call-back function, a window subclassing function, or a dialog box function, you must give Windows an address returned from MakeProcInstance.
 For instance, if CallBackProc is the name of a call-back function, you must first make a call like this:

IpfnCallBack = MakeProcInstance (CallBackProc, hInstance)
Because CallBackProc is a far function, the address you pass to MakeProcInstance is actually the address of the reload thunk. The IpfnCallBack address you get back from MakeProcInstance can now be used as a parameter to a Windows function such as SetTimer.

MakeProcInstance and the RegisterClass call both deal with the exported far function in the same way. They create an "instance thunk" for the function. The address that MakeProcInstance returns is the address of the instance thunk. Instance thunks are in a fixed area of memory, and they look like this:

```
MOV AX,xxxx
JMP ssss:0000
```

The xxxx value is the data segment address for this instance of your program. The instance thunks are different for each instance because each instance uses a different data segment. The ssss:0000 address in the instance thunk is the segment and offset address of the reload thunk

that reloads (or jumps to) the function. The same reload thunks are used for all instances of a program because they jump to the same shareable code.

When Windows needs to call a function in your program (such as a window function), it actually calls the instance thunk. The instance thunk sets AX equal to the data segment address for that instance and jumps to the reload thunk. The reload thunk loads the segment if it is not currently present in memory and branches to the function. The function then saves the previous value of DS and sets DS from the value of AX—the data segment address for the instance. When the function ends, it retrieves the original value of DS from the stack and returns control to Windows. When Windows moves the data segment for a particular instance, Windows must also change the xxxx values in all the instance thunks for that instance.

The Difference for Dynamic Libraries

You've seen that the far function prolog inserted by the compiler is modified by Windows if the function is exported. When far functions are in memory, they can have one of three possible prologs. If the prolog starts off like this:

```
MOV AX, DS
NOP
```

then the far function is called only from within the same program and is not called by Windows. If the prolog starts off like this:

```
NOP
NOP
```

then the far function has been exported. It is not called from within the program but instead is called only by Windows. A program's window function starts off like this.

What's the purpose of the extra NOP that shows up in both prologs? The extra NOP disappears in the third form of the prolog:

```
MOV AX, xxxx
```

You'll find this form at the beginning of many Windows functions in the Windows library modules (USER, KERNEL, and GDI) and drivers (DISPLAY, KEYBOARD, SYSTEM, and so forth). Unlike Windows programs, Windows libraries cannot have multiple instances, so they do not need instance thunks. The far function itself can contain code that sets AX equal to the segment address of the library's data segment (the value xxxx). The rest of the prolog then saves DS and sets DS equal to AX.

When Windows moves a library's data segment in memory, it must change the prologs of the library functions that use that data segment. And when your program calls a Windows function, the address it calls is either the address of the function's reload thunk (if the function is in a moveable segment) or the function itself (if the function is in a fixed segment).

Note that Windows library functions use their own data segments but continue to use the stack of the caller. If the library function were to use its own stack, it would need to copy function parameters from the caller's stack. Windows switches the stack only when switching between tasks; calling a library function does not constitute a task switch.

Walking the Stack

One little mystery remains. You'll recall that the far function prolog includes the statements:

```
INC BP
PUSH BP
```

The epilog then returns BP to normal:

```
POP BP
DEC BP
```

What is this for?

Think about this problem: Free memory is very low. A function in one of your program's code segments calls a far function in another of your program's code segments. This function then calls a Windows function. The code segment containing this Windows function is not currently present in memory. To load it into memory, Windows has to move your data segment and discard both your code segments. This sounds like a serious problem, because when the Windows function returns to your program, your program will be gone.

When Windows must discard code segments, it first goes through a little exercise called "walking the stack." Within any function, the value of SS{BP} is the value of BP from the previous function. If this previous value of BP is even, the previous function is a near function; if it's odd, then the previous function is a far function. By using successive values of BP stored on the stack, Windows can trace through the stack until it reaches the top, which is the stack pointer address originally given to your program when the program began executing. Windows can determine the segment addresses and the saved DS register values of all the functions involved in making the current Windows function call.

If Windows has to move your program's data segment (which also requires moving the stack), it can adjust the DS register on the stack to the new segment address. If Windows has to move a code segment containing functions that have been involved in the current Windows

function call, it changes the return address on the stack. If Windows has to discard a code segment, it replaces the return address with an address that points to code which reloads the segment and then branches to the appropriate return address.

As I mentioned at the onset of this discussion, you may prefer not to think about all this activity going on in the innards of Windows.

ALLOCATING MEMORY WITHIN A PROGRAM

Programs often need to dynamically allocate blocks of memory for internal use. Windows programs can allocate memory either from the program's private local heap or from Windows' global heap. Windows includes two sets of memory allocation functions, one set for using the local heap and one for the global heap.

There are certain trade-offs between local and global memory allocations. Local memory allocations are generally faster and require less overhead, but the memory in the local heap is limited to 64 KB less the combined size of the program's initialized static variables, the program's uninitialized static variables, and the stack. Global memory allocations are not limited to 64 KB, either in the size of single blocks or in the total memory you can allocate. However, pointers to global memory blocks are far pointers, which can be awkward to work with in your program. (You cannot pass a far pointer to small-model and medium-model C library functions, for instance.)

This chart summarizes the differences between memory allocations from the local heap and the global heap:

	Local Heap	Global Heap
Size of block	Less than 64 KB	Any size
Total memory	Less than 64 KB	Free global memory
Pointer	Near	Par

You'll probably find local heap allocations convenient for small, short-lived blocks of memory and global heap allocations for large, long-lived blocks.

The memory blocks you allocate can be fixed, moveable, or discardable. You specify the attributes you want when you allocate the memory block. When you write polite, well-mannered Windows programs, you'll probably want to use moveable blocks when allocating global memory, but you can use either fixed or moveable blocks for local memory. How do you deal with a moveable memory block in your program? Very carefully.

Lock Your Blocks

At first, it seems impossible for Windows to support moveable memory blocks. When a program allocates some local or global memory, Windows has to give the program a pointer so that the program can access the memory. If Windows later moves the memory block, then that pointer will be invalid. It will no longer point to the right place.

How does Windows do it? The catch here is that the memory allocation functions do not directly return pointers that the program may use. Instead, these functions return—as you can probably guess by now—handles. WINDOWS.H defines two data types called LOCALHANDLE and GLOBALHANDLE. These are defined as type HANDLE (which is a WORD, or unsigned 16-bit short integer). Before your program can use the allocated memory block, it must pass that handle back to Windows in another function that locks the memory block and returns a pointer. When a memory block is locked, Windows will not move it. The pointer will continue to be valid until you call another function to unlock the block. After that, Windows is free to move the memory again.

More precisely, the functions that lock a block of memory increment a "lock count" for the memory block. The unlocking functions decrement the lock count. When you first allocate moveable memory, the lock count is 0, meaning that Windows can move it if necessary. When the lock count is positive, Windows cannot move the block. (A lock count is preferable to a simple flag that denotes whether a block is locked, because different parts of your program can independently lock a block, use it, and unlock it. If Windows used a flag instead of a lock count, the memory block may become unlocked when another section of the program still needed it.)

When you use moveable memory in your Windows program, you should keep it locked only when your program has control. You should unlock it before you leave your window function. When you are entirely done with the memory block, you can then free the block.

A Quick Example

Before going into details, let's look at a quick example to get the feel of this process. Let's say that your program needs a 48 KB chunk of global memory during the entire time the program is running. During initialization (for instance, when processing the WM_CREATE message), the program uses *GlobalAlloc* to allocate a 48 KB segment of moveable memory:

```
hGlobalMemory = GlobalAlloc (GMEM_MOVEABLE, 0xC000L) ;
```

The value returned from *GlobalAlloc* is a handle to a 48 KB global memory segment. Store the handle in a static variable (here called *hGlobalMemory*).

While processing other messages, you might need to read from or write to this memory segment. At that time you lock the block of memory using GlobalLock and save the far pointer returned from that function:

```
lpGlobalMemory = GlobalLock (hMemory) ;
```

You can now use the *lpGlobalMemory* pointer as a normal far pointer. When you are finished using the memory or processing the message, unlock the segment so that Windows can move it around in memory again:

```
GlobalUnlock (hGlobalMemory) ;
```

When your program cleans up in preparing to terminate (probably when processing the WM_DESTROY message), it can free up the memory segment by:

```
GlobalFree (hGlobalMemory) ;
```

This procedure shows how a polite, well-behaved Windows program uses global memory. (I've ignored some details for now but will cover them shortly.) Good Windows programmers keep in mind that their programs share resources with other Windows programs. Good Windows programmers structure their programs to allow Windows to move the global segments around in memory if necessary. Good Windows programmers lock their segments only when they need to use the memory and unlock the segments when they are done.

An impolite, bad Windows program uses initialization code like this:

```
lpGlobalMemory = GlobalLock (GlobalAlloc (GMEM_FIXED, 0xC000L)) ;
```

The GMEM_FIXED flag in *GlobalAlloc* specifies that the segment is fixed in memory. Windows can't move it; therefore the *lpGlobalMemory* value returned from *GlobalLock* will be valid until the segment is freed up. More convenient, yes. But don't do it.

Global Memory Functions

Now for the details. This is the general syntax of the GlobalAlloc call:

```
hGlobalMemory = GlobalAlloc (wFlags, dwBytes) ;
```

The *dwBytes* parameter is a double word (unsigned long). This value can be greater than 65,536, but there are special considerations in using global memory blocks greater than 64 KB. (These will be discussed later.)

The wFlags parameter can be a combination of several identifiers that are combined with the C bitwise OR operator. You first have a choice of three identifiers to define the attribute of the allocated memory block:

- GMEM_FIXED—Memory is fixed. (This is the default if wFlags is 0.)
- GMEM_MOVEABLE—Memory is moveable.
- GMEM_DISCARDABLE—Memory is discardable. This option should be used only
 with GMEM_MOVEABLE. You will probably use this flag infrequently for global
 memory that you allocate from within a program, because Windows has no built-in
 procedure for automatically restoring a discarded memory block when you need to
 use it again. You must implement your own facility for restoring discarded memory.

With any of the above three flags, you can use the GMEM_ZEROINIT flag for convenience; this flag tells Windows to initialize memory contents to 0.

You can use two more flags to tell Windows what to do if not enough free memory exists in the global heap. When Windows attempts to allocate the block requested by *GlobalAlloc*, it first searches to see if a large enough free block exists already. If not, Windows begins moving blocks of memory that are moveable and not currently locked. If that still doesn't generate enough space, Windows begins discarding blocks that are marked as discardable and not currently locked, again moving moveable unlocked segments. You can inhibit this action by using one of two flags:

- GMEM_NOCOMPACT—Windows will neither compact memory nor discard memory when attempting to allocate the block.
- GMEM_NODISCARD—Windows will not discard discardable global memory when attempting to allocate the block. Windows may still compact memory by moving moveable blocks.

When your program terminates, Windows automatically frees global memory blocks if you do not. However, you may want to share global memory blocks among several instances of the same program. To do so, include the GMEM_SHARE flag. Then Windows will not automatically free the allocated memory block until all instances of the program that allocated the block have terminated.

GMEM_SHARE allows multiple instances to share the same memory block. If a program determines that it is not the first instance (that is, hPrevInstance is 0), it must allocate the necessary memory block using GMEM_SHARE and store the handle in a global variable in the program. (The term global variable here uses the word global in its usual C programming sense.) If the program is not the first instance, then it uses GetInstanceData to retrieve the handle from the previous instance.

WINDOWS.H includes two shorthand flags for the most common global memory allocations. The flag GHND (which stands for "global handle") is defined as:

```
GMEM_MOVEABLE | GMEM_ZEROINIT
```

The flag GPTR ("global pointer") is defined as:

```
GMEM_FIXED | GMEM_ZEROINIT
```

The name of this flag seems odd. Why is a fixed global block referred to as a "global pointer"? The answer is given later in this chapter, in the section entitled "Memory Allocation Shortcuts."

The hGlobalMemory value returned from GlobalAlloc is a handle to the global memory block. It is NULL if GlobalAlloc could not allocate the requested memory. You should definitely check the return value from GlobalAlloc when allocating global memory.

The function GlobalLock locks the segment in memory by incrementing the lock count and returns a far pointer to type character. You should have a variable declared for this pointer:

```
LPSTR lpGlobalMemory;

[other program lines]

lpGlobalMemory = GlobalLock (hGlobalMemory);
```

If hGlobalMemory is valid, GlobalLock can return NULL only if you flagged the memory block with GMEM_DISCARDABLE. The NULL return value indicates that the block has been discarded.

Because GlobalLock is declared as returning a far pointer to type character, you should use casting if you need something different:

The far pointer returned from *GlobalLock* points to the beginning of a segment. The offset address is 0. If you need to save pointers to areas within a moveable block, do not save them as far pointers. These far pointers may be invalid the next time you lock the segment. Instead, store an offset from the beginning of the block. For a global block less than 64 KB, for instance, you need save only the offset address (the lower 16 bits) of the pointer.

The GlobalUnlock function decrements the lock count for the hGlobalMemory handle:

```
GlobalUnlock (hGlobalMemory) ;
```

Calling GlobalUnlock invalidates the lpGlobalMemory pointer returned from GlobalLock. When the lock count is 0, Windows can move the block in memory.

GlobalLock and GlobalUnlock are fairly fast, so you don't suffer a real performance penalty if you use the two functions liberally. You should definitely not keep a block locked from one message to another. Remember that Windows performs best when memory is moveable. When you make a call to a Windows function, Windows may need to load code into memory. If you have a locked memory block sitting around, Windows may have to discard other segments to make room.

When you are entirely finished with the memory block, you can call:

```
GlobalFree (hGlobalMemory) ;
```

Following this call, the hGlobalMemory handle is no longer valid, and the block is freed.

More Global Memory Functions

Although the four global memory functions shown above are the ones you'll use most often, Windows also provides several others. Before using *GlobalAlloc*, you may want to determine the amount of global memory currently available:

```
dwAvailable = GlobalCompact (dwRequested) ;
```

If dwRequested is 0, GlobalCompact simply returns the amount of free memory available. (This facility is used in the FREEMEM program in Chapter 6.) If dwRequested is not 0, GlobalCompact causes Windows to move moveable blocks and to calculate the area of free memory that could be obtained by also discarding discardable blocks. If the function cannot generate dw-Requested bytes, it returns the largest block of free memory available. Discarding doesn't take place until you call GlobalAlloc using the size returned from GlobalCompact.

After you allocate a memory block, you can determine its size using:

```
dwBytes = GlobalSize (hGlobalMemory) ;
```

You can also change the size of the memory block or change its attributes using GlobalReAlloc. This function is a little tricky, because it can be used in one of three ways. Here's the general syntax:

```
hGlobalMemory = GlobalReAlloc (hGlobalMemory, dwBytes, wFlags) ;
```

First, you can change the size of a global memory block (either increasing or decreasing it) using:

```
GlobalReAlloc (hGlobalMemory, dwNewBytes, wFlags);
```

The data already stored in the block are preserved. The function returns NULL if it cannot increase the block to the requested size.

The wflags parameter is used the same way as the wFlags parameter for GlobalAlloc. GMEM_NODISCARD and GMEM_NOCOMPACT place restrictions on what Windows will do to satisfy the allocation request. GMEM_ZEROINIT zeroes out additional bytes if you are expanding the block. When calling GlobalReAlloc, you don't have to include the GMEM_FIXED, GMEM_MOVEABLE, or GMEM_DISCARDABLE flags. Windows preserves the attribute specified when the block was allocated. However, you may want to use the GMEM_MOVEABLE flag for reallocating a fixed block. Doing so gives Windows permission to move the block in memory to satisfy the allocation request. In this case, GlobalReAlloc returns a new global memory handle to the fixed block:

```
hGlobalMemoryNew = GlobalReAlloc (hGlobalMemoryOld, dwNewBytes,
GMEM_MOVEABLE);
```

If GlobalReAlloc returns NULL, the request for memory was refused, and the original hGlobalMemoryOld value passed to GlobalReAlloc is still valid for the fixed block.

The second way to use GlobalReAlloc is to change the discardable attribute of moveable blocks. The dwNewBytes value is ignored. You can change a moveable block to a discardable one:

```
GlobalReAlloc (hGlobalMemory, OL, GMEM_MODIFY | GMEM_DISCARDABLE); or change a discardable block to a moveable (but nondiscardable) one:
```

```
GlobalReAlloc (hGlobalMemory, OL, GMEM_MODIFY | GMEM_MOVEABLE) ;
```

The third use of GlobalReAlloc is to discard a discardable memory block. This requires dwNewBytes to be 0 and the wFlags parameter to be GMEM_MOVEABLE:

```
GlobalReAlloc (hGlobalMemory, OL, GMEM_MOVEABLE) ;
```

You can do the same thing using:

```
GlobalDiscard (hGlobalMemory) ;
```

In fact, GlobalDiscard is a macro defined in terms of GlobalReAlloc.

Using Discardable Global Memory

Given that Windows has no built-in facility to save the contents of discardable memory blocks, you may be wondering what such blocks are good for. Let's say you decide to use a separate file for "help" text that your program displays when the user requests it. You could allocate a moveable block, lock it, read some data from the file, display it to the screen, unlock the block, and

free it. However, this approach requires that your program allocate a new block of memory and access this file every time help information is requested.

Alternatively, you could keep a moveable block for this file buffer in memory all the time. When the user requests some help information, you check to see that the information is already in the buffer, and then you use that information rather than access the disk again. The performance of your program improves, but it does so at the cost of having a block of global memory allocated for the duration of your program.

How about using a discardable block instead? This keeps the buffer in memory but also gives Windows permission to discard it if necessary. When you lock the block:

```
1pGlobalMemory = GlobalLock (hGlobalMemory) ;
```

the *lpGlobalMemory* return value will be NULL if the block has been discarded. In that case, you can free the handle:

```
GlobalFree (hGlobalMemory) ;
```

and allocate a new discardable block using *GlobalAlloc*. Lock it, read in the file, display it to the screen, and unlock the block. This approach involves a little more work, but that's part of being a polite Windows program.

Windows never discards a discardable block when the lock count is nonzero. If you have obtained a valid far pointer from *GlobalLock*, that pointer is valid until you call *GlobalUnlock*. Even after the block is discarded, the handle is still valid. (This avoids problems when you pass the handle to *GlobalLock*.) When you get a NULL value from *GlobalLock*, you should free the handle. It has no further purpose.

You can also determine that a block is discardable or has been discarded by using the GlobalFlags function:

```
wFlags = GlobalFlags (hGlobalMemory);
```

WINDOWS.H has identifiers you can use in combination with wFlags. This value is nonzero if the block is discardable:

```
(GMEM_DISCARDABLE & wFlags)
```

This value is nonzero if the block has been discarded:

```
(GMEM_DISCARDED & wFlags)
```

You can also obtain the lock count using the GMEM_LOCKCOUNT mask:

```
(GMEM_LOCKCOUNT & wFlags)
```

Huge Global Memory Blocks

The dwSize parameter in GlobalAlloc is a 32-bit DWORD (double word), large enough in theory to allocate a 4-gigabyte block of memory. Although you obviously won't be able to get a block quite that large, it appears that you can still allocate a block of memory larger than 64 KB. Yes, you can, but you have to be careful. Beginning with version 4.0 of the Microsoft C Compiler, the huge keyword was implemented for defining variables that are larger than 64 KB. A huge pointer is 32 bits, just like a far pointer. However, the Microsoft C Compiler assumes that a far pointer addresses only a 64 KB range and will never run past the end of the segment. With a huge pointer, the compiler generates code that checks for segment overrun and does appropriate segment arithmetic on the pointer.

When you use GlobalAlloc to allocate memory greater than 64 KB, you must cast the pointer returned from GlobalLock into a huge pointer and save it as a huge pointer. For instance, this code allocates a 128 KB memory block and locks it:

```
GLOBALHANDLE hGlobalMemory;
char huge *lpGlobalMemory;
[other program lines]
hGlobalMemory = GlobalAlloc (GMEM_MOVEABLE, 0x20000L);
[other program lines]
lpGlobalMemory = (char huge *) GlobalLock (hGlobalMemory);
```

Every function that manipulates this huge pointer must be aware that the pointer is huge. If a function that is passed a huge pointer believes that the pointer is a simple far pointer, the Microsoft C Compiler will not generate any segment arithmetic when you manipulate the pointer. For this reason, you should not pass a huge pointer to any of the standard C functions or to any of the Windows functions unless you know that the function will not be referencing the pointer past the end of a segment.

That's one problem with huge pointers. Another problem is the possibility that a single data item referenced by the pointer may straddle two segments. With a huge pointer to character data, this is never a problem, because each character is a byte. The offset address that GlobalLock returns is always 0, so the huge pointer can also safely reference arrays of all the standard data types (char, short, int, long, float, and double).

If you use a huge pointer to an array of structures, you will have no problems if the size of the structure is a power of 2 (such as 2, 4, 8, 16, and so forth). That guarantees that no single structure will straddle two segments. If the size of the structure is not a power of 2, then you are bound by two restrictions:

- The data block allocated with GlobalAlloc cannot be larger than 128 KB.
- The offset address returned from GlobalLock must be adjusted so that a structure does not straddle two segments.

The first rule is actually implied by the second rule. If the initial offset address is adjusted so that an element of the structure does not straddle the first and second segments, it will straddle the second and third segments.

This explanation requires an example. Let's say you want a huge memory block to hold an array of 15,000 structures where each structure requires 6 bytes. You can use *typedef* statements for this structure and a far pointer to the structure:

In your program you can define a variable for the far pointer to the structure:

```
GLOBALHANDLE hGlobalMemory;

LPMYSTRUCT lpMyStruct;

[other program lines]

hGlobalMemory = GlobalAlloc (GHND, 15001 * sizeof (MYSTRUCT));

lpMyStruct = (LPMYSTRUCT) ((65536L * sizeof (MYSTRUCT)) +

GlobalLock (hMem);
```

The pointer returned from *GlobalLock* will have an offset address of 0. You must increase that so that a single structure does not straddle the two segments. The adjustment value is the remainder of 65,536 divided by the size of the structure. (In this case, the adjustment value is 4.) Because you have a little waste here, *GlobalAlloc* allocates one more structure than is really needed.

Also keep in mind that even 64 KB is a substantial part of Windows global heap space. If you think you need a 64 KB block of global memory, you should probably also be thinking of alternatives that won't require keeping all that data in memory.

Allocating Local Memory

I've been stressing the importance of using moveable (and, if possible, discardable) global memory blocks. With local memory you have the same options, but the guidelines are more relaxed. Whether you use fixed or moveable memory blocks within your local heap is up to you. Because your entire data segment is moveable (as it will be if you use the small or medium model), what you do inside your data segment doesn't affect other applications.

In fact, Windows makes it easier to use local memory if the blocks are fixed. The question you have to ask yourself is this: Can my local heap be smaller if I use moveable blocks instead of fixed blocks? If you use local memory a lot, and the life spans of the memory blocks overlap each other, then the answer to that question may be yes. If you use local memory allocations solely for short-lived memory, however, there's no reason to make the blocks moveable.

The local memory functions are similar to the global memory functions. Instead of GlobalAlloc, GlobalLock, GlobalUnlock, and GlobalFree, you use LocalAlloc, LocalLock, LocalUnlock, and LocalFree. Instead of identifiers that begin with GMEM, you use identifiers that begin with LMEM. The only real differences are these: The memory size passed to LocalAlloc is a WORD (unsigned integer) rather than a DWORD, and the pointer returned from LocalLock is a near pointer rather than a far pointer.

This is the syntax of LocalAlloc.

```
hLocalMemory = LocalAlloc (wFlags, wSize) ;
```

The wSize parameter is large enough to accommodate a requested size of 65,536 bytes, but you won't get a local block that large, because the data segment also includes your program's stack and static variables.

The wFlags parameter can first specify the attributes of the block:

- LMEM_FIXED—Memory is fixed. (This is the default if wFlags is 0.)
- LMEM_MOVEABLE—Memory is moveable.
- LMEM_DISCARDABLE—Memory is discardable. This option should be used only with LMEM_MOVEABLE.

The LMEM_ZEROINIT flag zeros out the memory block.

These two flags are equivalent to the similar flags for GlobalAlloc.

- LMEM_NOCOMPACT—Windows will neither compact nor discard memory in the local heap when attempting to allocate the block.
- LMEM_NODISCARD—Windows will not discard discardable memory in the local heap when attempting to allocate the block. Windows may still compact memory by moving moveable blocks.

WINDOWS.H also includes two shorthand flags for local memory allocations. The flag LHND (which stands for "local handle") is defined as:

```
LMEM_MOVEABLE | LMEM_ZEROINIT
```

The flag LPTR ("local pointer") is defined as:

```
LMEM_FIXED | LMEM_ZEROINIT
```

If Windows cannot find enough memory in the local heap to allocate the block, it will attempt to expand the local heap by enlarging the size of the entire data segment. (Remember that the local heap is always at the top of the automatic data segment.) Windows may even move the data segment to another location in memory if that will provide the space it needs to expand the local heap. When LocalAlloc returns, your data segment may have been moved. (If this makes you nervous, check the section below entitled "Locking Your Own Data Segment.") The HEAPSIZE specification in the module definition (.DEF) file is really a minimum value for the heap.

If after all this, Windows still cannot find enough memory in the local heap to allocate the memory block, the handle returned from *LocalAlloc* will be NULL. If you use local memory allocation only for small, short-lived memory blocks, you probably don't need to check the handle for a NULL value. (Alternatively, you might want to check the value during program development but not in the final version of the program.) If you do a lot of random local memory allocation with blocks of various sizes and different life spans, then you'll have to implement some kind of error processing.

LocalLock turns the local memory handle into a near pointer and then locks the block.
LocalUnlock unlocks the block and invalidates the pointer. LocalFree frees the memory block and invalidates the handle.

Here's an example of using local memory to define the window class structure during program initialization:

```
LOCALHANDLE
               hLocalMemory ;
NPWNDCLASS
               npwndclass ;
     [other program lines]
if (!hPrevInstance)
     hLocalMemory = LocalAlloc (LHND, sizeof (WNDCLASS));
     npwndclass = (NPWNDCLASS) LocalLock (hLocalMemory) ;
                               = CS_HREDRAW | CS_VREDRAW;
     npwndclass->style
     npwndclass->lpfnWndProc = WndProc;
     npwndclass->cbClsExtra = 0 ;
     npwndclass->cbWndExtra = 0;
     npwndclass->hInstance = hInstance;
                               = Loadicon (NULL, IDI_APPLICATION) ;
     npwndclass->hIcon = LoadIcon (NULL, IDI_APPLICATIOnpwndclass->hCursor = LoadCursor (NULL, IDC_ARROW);
     npwndclass->hbrBackground = GetStockObject (WHITE_BRUSH) ;
     npwndclass->lpszMenuName = NULL ;
     npwndclass->lpszClassName = szAppName ;
     if (!RegisterClass (npwndclass))
          return FALSE ;
     LocalUnlock (hLocalMemory);
     LocalFree (hLocalMemory);
     1
```

The size of the memory block passed to LocalAlloc is the size of the WNDCLASS structure. LocalLock always returns a near pointer regardless of the memory model, because it allocates memory from the local heap in the program's automatic data segment. In this example, the pointer to type character that LocalLock returns is cast into a pointer to a WNDCLASS structure. The -> notation is used to reference the elements of a structure based on a pointer to the structure. In the RegisterClass call, we don't use the address (©) operator because npundclass is already a pointer. Note also that the use of LHND initializes the block of memory to 0. All variables in the structure that take a 0 or NULL value need not be explicitly assigned.

Other Local Memory Functions

Some other local memory functions parallel those for global memory allocations except that sizes are in terms of wBytes rather than dwBytes. You can get the current size of a local memory block by calling:

```
wBytes = LocalSize (hLocalMemory) ;
```

The function LocalReAlloc can change the size of an allocated memory block, change a moveable block to discardable, change a discardable block to nondiscardable, and discard a discardable block, just like GlobalReAlloc. During a LocalReAlloc call, Windows may expand the size of the local heap by expanding the size of the entire data segment, possibly moving it to another location in memory. LocalCompact can determine the amount of free local memory available in the heap, LocalDiscard discards a discardable memory block, and LocalFlags provides the current status of discardable blocks.

Two other local memory functions do not have counterparts in the global memory functions. You can prevent your local heap from being compacted by calling:

```
LocalFreeze (0) ;
```

When you later want to allow compacting, you can call:

```
LocalMelt (0) ;
```

Locking Your Own Data Segment

Now that you are thoroughly paranoid about locking and unlocking memory blocks, you may start to wonder about the automatic data segment of the program itself. When the program begins executing, your automatic data segment has a lock count of 1, and the data segment cannot be moved in memory. Windows decrements that lock count when the program makes one of the following calls: GetMessage, PeekMessage, WaitMessage, LocalAlloc, or LocalReAlloc.

The GetMessage, PeekMessage, and WaitMessage calls can cause a switch from your program to another program. When your program gets control again, your data segment may have been moved. A LocalAlloc or LocalReAlloc call can cause Windows to expand the size of your local heap, in the process moving the data segment to another location in memory. Windows increments the lock count when it returns from these calls to your program. So in most cases, your program's data segment is locked when your program has control. This means that you can construct (through casting) far pointers to data in your data segment, and they will remain valid until you make one of these five calls or exit the window function.

If you want to prevent the movement of your data segment during a LocalAlloc or LocalReAlloc call, you can increase the lock count by 1 before calling the function:

```
LockData (0) ;
```

Following the *LockData* call, the lock count of your data segment will be 2. When Windows decrements the count during a *LocalAlloc* or *LocalReAlloc* call, it will still be positive and your data segment will still be locked. You can decrement the lock count by calling:

```
UnlockData (0) ;
```

If you're brave, you might also want to take the opposite approach. You might be willing to keep your data segment unlocked while making Windows calls. You would do this by calling *UnlockData* to decrement the lock count to 0 and then *LockData* to increment it to 1 again before exiting the window function. When your data segment is unlocked, Windows has more flexibility in moving segments in memory because Windows can move your data segment as well. However, when your data segment is unlocked, you should not make *any* Windows calls that require a far pointer to your data segment. Depending on what happens during that call, the pointer may become invalid by the time Windows needs to use it.

Memory Allocation Shortcuts

We have been treating handles as abstract numbers. But sometimes handles are actually pointers. If you use LMEM_FIXED in *LocalAlloc*, the handle returned from the call is a near pointer that you can use directly. You do not need to call *LocalLock*. (If you do, it simply returns the same value you pass as a parameter—the handle that is actually a valid near pointer.) In fact, WINDOWS.H defines a special flag for calling *LocalAlloc* with an LMEM_FIXED parameter. The flag is LPTR ("local pointer") and is defined as:

LMEM_FIXED | LMEM_ZEROINIT

When you use this flag, you need only cast the return value from LocalAlloc into a near pointer of the type you want:

```
npString = (char NEAR *) LocalAlloc (LPTR, wSize) ;
```

You free it up by casting the near pointer back to a handle and calling LocalFree:

```
LocalFree ((LOCALHANDLE) npString) ;
```

This technique is handy for allocating small chunks of local memory. For instance, here's the example shown above for allocating memory for the window class structure. It now uses a fixed block of local memory:

```
NPWNDCLASS
             npwndclass ;
    [other program lines]
if (!hPrevInstance)
    npwndclass = (NPWNDCLASS) LocalAlloc (LPTR, sizeof (WNDCLASS));
    npwndclass->style
                         = CS_HREDRAW | CS_VREDRAW ;
    npwndclass->lpfnWndProc = WndProc;
    npwndclass->cbClsExtra = 0;
    npwndclass->cbWndExtra = 0;
    npwndclass->hInstance = hInstance;
    npwndclass->hbrBackground = GetStockObject (WHITE_BRUSH) ;
    npwndclass->lpszMenuName = NULL ;
    npwndclass->lpszClassName = szAppName ;
    if (!RegisterClass (npwndclass))
         return FALSE ;
    LocalFree ((LOCALHANDLE) npwndclass);
```

We've eliminated two lines of code (the LocalLock and LocalUnlock) and one variable (the local memory handle). Note the casting in the LocalAlloc and LocalFree calls.

The same technique is even applicable for GlobalAlloc when the GMEM_FIXED (or GPTR) flag is used. The "handle" returned from GlobalAlloc is the segment address of the segment. It's a little more clumsy to convert that into a far pointer, but here's how to do it:

```
1pString = (LPSTR) MAKELONG (0, GlobalAlloc (GPTR, dwSize)) ;
```

The MAKELONG macro combines the segment address returned from GlobalAlloc and an offset address of 0 to make a long integer, which is then cast into a long pointer to type character. To free this block, you have to extract the segment address from the pointer and pass it to GlobalFree:

```
GlobalFree ((GLOBALHANDLE) LOWORD ((LONG) lpString)));
```

Handles Are Not Pointers

In all honesty, I don't like the memory allocation shortcuts, and I don't think they should be used. I've included them only because many sample Windows programs use them, particularly when allocating local memory.

Section 5.6 of the classic *C Programming Language* by Brian Kernighan and Dennis Ritchie is entitled "Pointers Are Not Integers." The fact that pointers very often *are* integers is irrelevant. Good C programming practice requires that you treat them differently. All that C guarantees is that the *difference* between two pointers can be represented by an integer. When using C with the 8086 family of microprocessors, far pointers are certainly not integers. If you've done C programming using the compact or large model, where far pointers are used for all data, you are probably well aware of this.

In Windows, we can assert with equal confidence that "handles are not pointers." As you'll note in the above example using *GlobalAlloc*, this is literally true: The handle is not a pointer; it's only part of the pointer.

Using C Memory Allocation Functions

The start-up code that LINK4 attaches to C programs running under Windows contains functions for many of the memory allocation functions in Microsoft C 4.0, such as *calloc*, *malloc*, *realloc*, and *free*. The routines in the start-up code convert the normal C memory allocation functions into equivalent Windows memory allocation functions. For instance, the function:

```
malloc (wSize)
```

is translated into:

```
LocalAlloc (LMEM_FIXED | LMEM_NOCOMPACT, min (1, wSize));
```

These functions are included in the Windows start-up code not for your benefit, but because several other C functions from the standard library make calls to these C memory allocation functions. These other C functions cannot work properly without using the Windows memory allocation calls. Although it's not intended that you use these functions, you can use

them. Be aware, however, that in compact-memory and large-memory models (which you shouldn't be using for Windows programs anyway), the Windows *malloc* returns a far pointer to your program's automatic data segment—as opposed to the non-Windows *malloc*, which returns a far pointer to a block of memory outside the automatic data segment. Also be aware that _fmalloc and halloc are translated into GlobalAlloc calls with a flag that is equal to (GMEM_FIXED| GMEM_NODISCARD), and as you know, you should not use fixed global memory blocks. Moreover, the pointer returned from the Windows halloc is not properly aligned for an array of elements that are not multiples of 2, and the memory is not initialized to 0. The point is clear: Unless you feel deprived doing C programming without malloc, use the Windows functions for all memory allocations.

Chapter 9

Icons, Cursors, Bitmaps, and Strings

Most Windows programs include a customized icon that Windows displays when the program is minimized. Some Windows programs (such as PAINT) also use customized cursors to represent different operations of the program. Most Windows programs also use menus and dialog boxes.

Icons, cursors, menus, and dialog boxes are all examples of "resources." Resources are data and are included in a program's .EXE file, but they do not reside in a program's normal data segment. When Windows loads a program into memory for execution, it usually leaves the resources on disk. Only when Windows needs a particular resource does it load the resource into memory. (You've probably noticed dynamic loading of resources when working with Windows programs. When you invoke a program's dialog box for the first time, Windows usually accesses the disk to copy the dialog box resource from the program's .EXE file into memory.)

Most resources are read-only data and are marked as discardable. When Windows needs more memory, segments occupied by discardable resources can be freed up. If the resource is required again later, Windows reloads it from the .EXE file. Just as multiple instances of the same program share the same code, multiple instances also usually share resources. Windows programs can use nine types of resources:

- · Icons
- Cursors
- Bitmaps
- Character strings

- User-defined resources
- Menus
- Keyboard accelerators
- Dialog boxes
- Fonts

The first five resources in the list are discussed in this chapter. Menus and keyboard accelerators are covered in Chapter 10, dialog boxes in Chapter 11, and fonts in Chapter 15.

COMPILING RESOURCES

During program development, resources are defined in a "resource script," which is an ASCII text file with the extension .RC. The resource script can also reference other files (either ASCII or binary files) that also contain resources. A resource compiler compiles the resource script into a binary form, adds the resources to the end of the .EXE file that LINK4 generates, and creates a "resource table" in the .EXE header.

The resource compiler included with the Windows Software Development Kit is called RC.EXE. You can use this resource compiler in one of two ways:

 You can compile resources and add them to the linked .EXE file in one step by executing the command:

RC filename

where filename.RC is the name of the resource script (the .RC extension is assumed) and filename.EXE is the name of the linked .EXE file. You can also use:

RC resource-name exe-name

if the name of your .RC resource script and the name of your .EXE executable are different. (This is usually not the case.)

 You can compile a .RC resource script into a binary compiled form with the extension .RES by executing:

RC -r filename

This uses the ASCII *filename*.RC file to create a binary file called *filename*.RES. You can then add the resources to the linked file by executing:

RC filename.RES

The .RES extension is required here to differentiate this command from the command shown earlier that both compiles the resource script and adds the resources to the .EXE file.

This second method is the one most commonly used. Although it requires that the RC.EXE resource compiler be run twice—once to compile the resource script and again to add the resources to the .EXE file—it actually results in a faster edit-make-run cycle when developing Windows programs. The reason is that compiling the resources generally takes much longer than adding them to the .EXE file. During program development, you will probably modify your C source code much more frequently than the resource script, so you have no need to recompile the resources each time.

The procedure of compiling resources is reflected in a different make file. Up until now we have been using a make file that looks something like this:

```
progname.obj : progname.c
     cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp progname.c
progname.exe : progname.obj progname.def
     link4 progname, /align:16, /map, slibw, progname
```

When we start using resources, we require an expanded make file that looks like this:

```
progname.obj : progname.c [progname.h]
    cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp progname.c

progname.res : progname.rc [progname.h] [and other files]
    rc -r progname.rc

progname.exe : progname.obj progname.def progname.res
    link4 progname, /align:16, /map, slibw, progname
    rc progname.res
```

The first step compiles the C source code. The second step compiles the .RC resource script into a binary .RES file. The third step is executed if either the .OBJ, .DEF, or .RES file has changed since the last .EXE file was created. This final step links the program and runs .RC again to add the resources to the .EXE file. If you change only the .RC resource script file, you still need to relink to produce a new .EXE file without the previous resources. The resource compiler cannot remove old resources from a .EXE file when adding new ones.

In the first and second steps I've indicated that a .H header file can be used in both the C source code and the resource script. This header file usually defines identifiers used by the program to reference resources. I've also indicated in the second step that the dependent file list possibly includes "other files." These are files referenced from within the resource script. Generally they are binary files that contain icons, cursors, or bitmaps.

The RC.EXE resource compiler uses a preprocessor called RCPP.EXE. This preprocessor folds added or subtracted constants, recognizes /* and */ as comment delimiters, and recognizes the C preprocessor directives #define, #undef, #ifdef, #ifndef, #include, #if, #elif, #else, and #endif. The #include directive works a little differently than in normal C programs. We'll examine this more in Chapter 11.

ICONS AND CURSORS

Let's begin by looking at a sample program that uses two resources—an icon and a cursor. RESOURC1, shown in Figure 9-1, displays a customized icon when the program is minimized and uses a customized cursor when the mouse is in RESOURC1's client area. RESOURC1 also draws its icon in several rows and columns within the client area.

```
resourch.obj : resourch.c
    cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp resourch.c

resourch.res : resourch.rc resourch.ico resourch.cur
    rc -r resourch.rc

resourch.exe : resourch.obj resourch.def resourch.res
    link4 resourch, /align:16, /map, slibw, resourch
    rc resourch.res
```

```
/* RESOURCI.C -- Icon and Cursor Demonstration Program No. 1 */
#include <windows.h>
long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG) ;
char szAppName [] = "Resourcl" ;
HANDLE hinst ;
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
      HANDLE hInstance, hPrevInstance;
      LPSTR
                lpszCmdLine ;
      int
                nCmdShow :
      HWND
               hWnd ;
      MSG
                msg ;
      WNDCLASS wndclass ;
      if (!hPrevInstance)
           windclass.lpfnWndProc = WndProc;
wndclass.cbClsExtra = 0;
wndclass.cbWndExtra = 0;
wndclass.hInstance = hInstance
wndclass.hIcon
                                       = CS HREDRAW | CS VREDRAW ;
                                      = hInstance ;
            wndclass.hIcon = LoadIcon (hInstance, szAppName);
wndclass.hCursor = LoadCursor (hInstance, szAppName);
            wndclass.hbrBackground = COLOR WINDOW + 1 ;
            wndclass.lpszMenuName = NULL ;
            wndclass.lpszClassName = szAppName ;
```

Figure 9-1. The RESOURC1 program, including an icon and a cursor

Figure 9-1. Continued

```
if (!RegisterClass (&wndclass))
               return FALSE ;
    hInst = hInstance :
    hWnd = CreateWindow (szAppName, "Icon and Cursor Demo",
                         WS OVERLAPPEDWINDOW,
                         CW_USEDEFAULT, 0,
CW_USEDEFAULT, 0,
                         NULL, NULL, hInstance, NULL) ;
     ShowWindow (hWnd, nCmdShow) ;
    UpdateWindow (hWnd) ;
    while (GetMessage (&msg, NULL, 0, 0))
          TranslateMessage (&msg) ;
          DispatchMessage (&msg) ;
    return msg.wParam ;
long FAR PASCAL WndProc (hWnd, iMessage, wParam, lParam)
               hWnd ;
iMessage ;
    unsigned
     WORD
                 wParam ;
                 1Param ;
     LONG
    HDC
                hDC ;
     RECT
                 rect :
     PAINTSTRUCT ps ;
     static HICON hIcon ;
    static short xIcon, yIcon, xClient, yClient;
    short
                 x, y :
     switch (iMessage)
          case WM CREATE:
               hIcon = LoadIcon (hInst, szAppName) ;
               xIcon = GetSystemMetrics (SM CXICON) ;
               yIcon = GetSystemMetrics (SM_CYICON) ;
               break :
          case WM SIZE:
               xClient = LOWORD (1Param) ;
               yClient = HIWORD (1Param) ;
               break :
          case WM PAINT:
               hDC = BeginPaint (hWnd, &ps) ;
               for (y = yIcon ; y < yClient ; y += 2 * yIcon)
                    for (x = xIcon ; x < xClient ; x += 2 * xIcon)
                         Drawlcon (hDC, x, y, hIcon) ;
               EndPaint (hWnd, &ps) ;
               break ;
          case WM DESTROY:
               PostQuitMessage (0) ;
               break :
```

Figure 9-1. Continued

```
default:
    return DefWindowProc (hWnd, iMessage, wParam, lParam) ;
return 0L;
}
```

resourcl ICON resourcl.ico resourcl CURSOR resourcl.cur






Figure 9-1. Continued

NAME RESOURC1 'Icon and Cursor Demo Program No. 1 (C) Charles Petzold, 1987' DESCRIPTION STUB 'WINSTUB.EXE' MOVEABLE CODE MOVEABLE MULTIPLE DATA HEAPSIZE 1024 STACKSIZE 4096 EXPORTS WndProc

Both the icon and the cursor were created using the ICONEDIT program supplied with the Windows Software Development Kit. They are shown in Figure 9-1 against a light gray background. ICONEDIT is a Windows application, and it requires a mouse. Icons are saved from ICONEDIT with a .ICO extension; cursors have a .CUR extension. These files are referred to in the RESOURCLRC resource script. ICONEDIT is a deceptively easy program to use, but it also leaves you open to some pratfalls if you don't have a good grasp of how icons and cursors are constructed. That's what we'll examine now.

Monochrome Bitmaps

Icons and cursors are very similar. Both objects are defined by two monochrome bitmaps. A monochrome bitmap is a collection of bits where each bit corresponds to one display pixel. A bitmap may have any number of rows and columns.

The sequence of bytes that defines the bitmap begins with the top row and the 8 leftmost bits. The most significant bits correspond to the leftmost pixels. The sequence of bytes continues across the top row and then works down through the bitmaps. For example, a 16-pixel-wide by 8-pixel-high bitmap to draw a V-shape has the following bit pattern:

1	.0	0	0	0	0	0	0	0	0	0	0	0	0	0	1	80	01
0	1	0	0	0	0	0	0	0	0	0	0	0	0	1	0	40	02
0	0	1	0	0	0	0	0	0	0	0	0	0	1	0	0	20	04
0	0	0	1	0	0	0	0	0	0	0	0	1	0	0	0	10	0.8
0	0	0	0	1	0	0	0	0	0	0	1	0	0	0	0	08	10
0	0	0	0	0	1	0	0	0	0	1	0	0	0	0	0	04	20
0	0	0	0	0	0	1	0	0	1	0	0	0	0	0	0	02	40
0	0	0	0	0	0	0	1	1	0	0	0	0	0	0	0	0.1	80

The bytes (in hexadecimal) at the right show how this bitmap is encoded as a sequence of bytes (80, 01, 40, 02, and so forth).

Windows requires that a bitmap stored in a file or in memory have an even number of bytes (or a multiple of 16 bits) per bitmap row. Windows ignores the extra bits if the bitmap row dimension is not a multiple of 16. In simple terms, a 0 bit is black and a 1 bit is white. As we'll see, however, bitmaps are often used in logical operations rather than merely to create simple drawings. For instance, if the bitmap shown above were combined with a 16-by-8-pixel area of the display using a bitwise exclusive OR operation, then the 0 bits would leave existing display pixels intact, and the 1 bits would invert the colors of existing display pixels.

Bitmaps in Icons and Cursors

When you create an icon in ICONEDIT, you work with a 64-by-64-bit grid, which seemingly corresponds to a 64 by 64 monochrome bitmap. However, when ICONEDIT saves your work in a ICO file, it actually saves *two* 64 by 64 monochrome bitmaps. (Cursors are the same except that you create and save two 32 by 32 bitmaps.)

Why two bitmaps for cursors and icons instead of one? The use of two bitmaps relates to the way in which icons and cursors use color. The Color command from ICONEDIT's menu lets you select colors of "White," "Black," "Screen," and "Inverse screen." Areas of the icon or cursor that are colored using "Screen" are transparent when the object is viewed on the display. Bits colored as "Inverse screen" cause colors beneath the displayed object to be inverted: Black turns to white, white turns to black, and green turns to magenta.

When you select New from ICONEDIT's File menu, the entire work surface is colored as "Screen." This creates an entirely transparent icon. You can paint bits using the color selected from the menu by pressing the left mouse button. If the bit is already that color, the left mouse button inverts it. Use the right mouse button for the other two colors.

The cursor and icon shown in Figure 9-1 use all four possible colors. The figures are shown against a light gray background, so that the "Screen" sections appear in light gray and the "Inverse screen" sections in dark gray. If you run RESOURC1 on a color display and minimize the program, the "Screen" areas of the icon display the color of the desktop, and the "Inverse screen" areas invert the color of the desktop. This results from the way in which Windows uses the two bitmaps in the icon and cursor files. The following table shows the possible combinations of bits in the two bitmaps and the color that results from each:

Bitmap 1:	0	0	1	1
Bitmap 2:	0	1	0	1
Resultant color:	Black	White	Screen	Inverse screen

Still confused? Then think in terms of logical operations of bits.

First, Windows uses a bitwise AND operation of the display and the first bitmap. The display pixels corresponding to 0 bits from the first bitmap all become a 0, which is black. The display pixels corresponding to 1 bits remain the same. This is shown in the following logic table.

Bitmap 1 Bit	Displa	y Pixel	
Participation of the Control of the	0	1	
0	0	0	
1	0	1	

Next, Windows performs a bitwise Exclusive OR operation of the second bitmap and the display. A 0 in the second bitmap leaves the display pixel the same; a 1 in the second bitmap inverts the display pixel. Here's the logic table:

Using C notation for the operations, the display is altered by the following formula:

Display = (Display & Bitmap1) ^ Bitmap2

Earlier I said that 0 does not necessarily mean black, and 1 does not necessarily mean white. As you can see here, it depends on how Windows uses the bitmaps.

The inversion also works with color: Blue is inverted to yellow, green to magenta, and red to cyan. In RESOURC1, I've defined the window class to make the background of the client area be COLOR_WINDOW. You may want to bring up the CONTROL program and change the window color to see how the icon and cursor invert colors.

Some Color Design Rules

Icons and cursors often look a little different depending on the color of the display background. With ICONEDIT you can change the viewing background color to black, white, gray (blue on a color display), or light gray (cyan on a color display), thus letting you see how your icon appears against these backgrounds. On a monochrome display, the gray background causes "Screen" and "Inverse screen" bits to appear the same; the light gray background turns "Inverse screen" bits to dark gray.

This choice of background color in ICONEDIT is for viewing purposes only. When your program is running, you have no control over the background. Let's take some examples:

- When an icon is viewed against a gray background (like the default desktop color on a monochrome display), "Screen" and "Inverse screen" colors are identical.
- When an icon is viewed against a white background, "White" and "Screen" colors are identical, and "Black" and "Inverse screen" colors are identical.

 When an icon is viewed against a black background, "Black" and "Screen" colors are identical, and "White" and "Inverse screen" colors are identical.

With these examples in mind, here are some general rules:

- If your icon is mostly white (such as the NOTEPAD icon), surround it with a black border and use black for internal detail.
- If your icon is mostly black (such as the MS-DOS Executive icon), surround it with a
 white border and use white for internal detail.
- Use "Screen" if you want to make the icon nonrectangular (CARDFILE) or smaller than a normal icon (NOTEPAD) or to make a "hole" in the icon (MS-DOS Executive).
- Use "Inverse screen" to add a dash of color to the icon, but don't rely on "Inverse screen" to be different from "Screen" for the desktop background on a monochrome display.

More Problems with Icons and Cursors

Aside from considerations of color when designing icons and cursors, you may also encounter problems related to the way in which Windows reduces the icon or cursor in size. In ICONEDIT, you design an icon based on a 64 by 64 grid. However, on an IBM Color/Graphics Adapter (or an Enhanced Graphics Adapter using the 200-scan-line mode), icons are displayed 32 pixels wide by 16 pixels high. On an EGA using the 350-scan-line mode or on a Hercules Graphics Card, the icons are 32 by 32 pixels. Although a full 64 by 64 icon might be appropriate for a high-resolution display (for instance, 1024 by 1024), most of the existing Windows drivers developed for high-resolution graphics adapters and large displays use icon dimensions of 32 by 32.

Cursors designed in ICONEDIT are saved in a 32 by 32 format. This size is maintained on a Hercules Graphics Card and on an EGA using the 350-scan-line mode, but it is reduced to 32 pixels wide by 16 pixels high on a CGA. If your Windows program needs to determine the size of icons and cursors, the information is available through GetSystemMetrics. RESOURCI.C uses GetSystemMetrics with the SM_CXICON and SM_CYICON indices to obtain the dimensions of the icon.

When Windows is running on a 350-scan-line EGA display and loads your icon from the .EXE file into memory, it reduces the 64 by 64 icon stored in the .EXE file to a 32 by 32 icon in memory and then displays this 32 by 32 icon. Windows does *not* reduce an icon in size simply by deleting every other column and row, however. Instead, Windows uses a technique similar to the "black-on-white" stretching mode of the *StretchBlt* function (described in Chapter 14).

This involves reducing a bitmap in size by using a bitwise AND operation to combine adjacent bits, thus causing 0 bits to have precedence over 1 bits.

Let's take the example of a 64 by 64 icon in your .EXE file reduced to a 32 by 32 icon in memory. Each 2 by 2 group of adjacent bits in the original bitmap is reduced to a single bit. The four bits are combined in a bitwise AND operation: A bit in the reduced bitmap is set to 1 only if all four bits in the original bitmap are 1. This causes some strange things to happen. For instance, the 64 by 64 icon shown in Figure 9-2 has three times as many white pixels as black pixels. Yet when the icon is reduced in size to 32 by 32, all the white pixels disappear and the resultant icon is black. It just so happens that each group of four pixels in the 64 by 64 icon has three white pixels and one black pixel. The "black-on-white" stretching mode turns each group to black.




Figure 9-2. An icon that appears black when reduced in size

If you think the example shown in Figure 9-2 is trivial and intuitively obvious, take a look at Figure 9-3. This icon has alternating 2-pixel-wide "Screen" stripes and 2-pixel-wide "White" stripes. Yet once again the reduced icon is entirely black.



Figure 9-3. Another icon that appears black when reduced in size

This is often the result when an icon with adjacent "White" and "Screen" pixels is reduced. Windows reduces each of the two bitmaps in the icon file separately. This table shows what happens to adjacent "White" and "Screen" pixels:

	Adjacent Pixels		Pixels 1 and 2		
	Pixel 1	Pixel 2	Combined with AND Operation		
Bitmap 1:	1	0	0		
Bitmap 2:	0	1	0		
Resultant color:	"Screen"	"White"	Black		

In creating icons, the final rule is this: Recognize the limitations of the worst-case 32 by 16 matrix and make your icons simple. You probably can't draw an icon that evocatively portrays the sea on a moonlit night, so don't even try.

The .ICO and .CUR File Formats

Although your programs don't directly access icon and cursor files, you may be interested in their formats. The JCO and JCUR files contain a short 14-byte header record followed by the two bitmaps. This is the JCO icon file:

Offset	Size	Value
0	Byte	1
1	Byte	0 for device-independent format (normal)
6	Word	Width in pixels (normally 40H)
8	Word	Height in pixels (normally 40H)
10	Word	Width in bytes (must be even; normally 08H)
14	512	Bitmap 1
526	512	Bitmap 2

The .CUR cursor file is similar but includes a pixel position that represents the cursor's "hot spot":

Offset	Size	Value
0	Byte	3
1	Byte	0 for device-independent format (normal)
2	Word	Hot-spot horizontal position
4	Word	Hot-spot vertical position
6	Word	Width in pixels (normally 20H)
8	Word	Height in pixels (normally 20H)
10	Word	Width in bytes (must be even, normally 04H)
14	128	Bitmap 1
142	128	Bitmap 2

Getting a Handle on Icons

A resource script references the icon file with a statement that looks like this:

```
myicon ICON iconfile.ico
```

where ICONFILE.ICO is the name of the icon file. This statement assigns the name "myicon" to the icon. In your C program, you use the *LoadIcon* function to obtain a handle to the icon. *LoadIcon* requires two parameters. The first is the instance handle of your program, generally called *hInstance* in *WinMain*. Windows needs this handle to determine which .EXE file contains the icon resource. The second parameter is the icon name from the resource script in the form of a pointer to a null-terminated string. *LoadIcon* returns a value of type HICON, which is defined in WINDOWS.H.

This diagram shows the relationship between the icon name in the resource script and the *LoadIcon* statement in your C program:

Resource script:

myicon ICON iconfile.ico

Program source:

hlcon = Loadlcon (hInstance, "myicon");

Don't worry about uppercase and lowercase here. The resource compiler converts the name in the resource script file to uppercase and inserts the name in the resource table of the program's .EXE file header. The first time you call *LoadIcon*, Windows converts the string from the second parameter to uppercase and searches the resource table of the .EXE file for a matching name.

You can speed up this search by using a number (an unsigned integer) instead of a name. This number is called an ID number for the icon. Here's how it's done:

Resource script:

125 ICON iconfile.ico

Program source:

hicon = Loadicon (hinstance, MAKEINTRESOURCE (125)):

MAKEINTRESOURCE ("make an integer into a resource string") is a macro defined in WIN-DOWS.H that converts a number into a far pointer. The offset address is set to the number, and the segment address is set to 0. Here's how MAKINTRESOURCE is defined in WINDOWS.H:

```
#define MAKEINTRESOURCE(i) (LPSTR)((DWORD)((WORD)i))
```

Windows knows that the second parameter is a number rather than a pointer to a character string because the segment address is 0.

Sample programs presented earlier in this book use predefined icons:

LoadIcon (NULL, IDI_EXCLAMATION)

Windows knows that this is a predefined icon because the *hInstance* parameter is set to NULL_IDI_EXCLAMATION happens also to be defined in WINDOWS.H in terms of MAKEINTRESOURCE:

```
#define IDI_EXCLAMATION MAKEINTRESOURCE(32515)
```

The predefined icons and cursors are part of the display driver file.

You can also reference the icon name using a third method that combines the string method and the number method:

Resource script:

125 ICON iconfile.ico

Program source:

hIcon = Loadicon (hinstance, "#125");

Windows recognizes the initial # character as prefacing a number in ASCII form.

How about a fourth method? This one uses a macro definition in a header file that is included (using the #include directive) in both the resource script and your program:

Header file:

#define myicon 125

Resource script:

myicon ICON iconfile.ico

Program source:

hlcon = LoadIcon (hInstance, MAKEINTRESOURCE (myicon));

Be careful when you use this method! Although case doesn't matter when the icon name is a character string, case *does* make a difference for identifiers that are generated from #define statements.

Using ID numbers rather than names for icons reduces the .EXE file size and speeds up the *LoadIcon* call. Moreover, if your program uses many icons, you'll find it easier to store the ID numbers in an array.

Using Icons in Your Program

Icons have only a couple of purposes. Most Windows programs use an icon only for displaying the program in the icon area. This is accomplished when defining the window class:

```
wndclass.hIcon = LoadIcon (hInstance, "myicon") ;
```

If you later want to change the program's icon, you can do so using SetClassWord. Let's assume you had a second icon in your resource script:

```
anothericon ICON iconfil2.ico
```

You can substitute this icon for "myicon" with the statement:

```
SetClassWord (hWnd, GCW_HICON, LoadIcon (hInstance, "anothericon"));
```

If you save the icon handle from a *LoadIcon* call, you can also draw the icon on the client area of your window:

```
Drawlcon (hDC, x, y, hIcon) ;
```

Windows itself uses the *Drawlcon* function when displaying your program's icon in the icon area. Windows obtains the handle to the icon from the window class structure. You can obtain the handle in the same way:

```
Drawlcon (hDC, x, y, GetClassWord (hWnd, GGW_HICON));
```

The RESOURC1 sample program uses the same icon for the window class and for displaying in its client area. In the resource script the icon is given the same name as the program:

```
resourc1 ICON resourc1.ico
```

Because the text string "Resourc1" is stored in the array szAppName and is already used in the program for the window class name, the LoadIcon call is simply:

```
LoadIcon (hInstance, szAppName)
```

You'll notice that *Loadicon* is called twice in RESOURC1 for the same icon, once when defining the window class in *WinMain* and again when obtaining a handle to the icon while processing the WM_CREATE message in *WindProc*. Calling *Loadicon* twice presents no problem: Both calls return the same handle. Windows actually loads the icon only once from the .EXE file and then uses it for all instances of the RESOURC1 program.

Using Alternate Cursors

The statements that you use to specify a cursor in your resource script and to obtain a handle to a cursor in your program are very similar to the icon statements shown above:

Resource script: mvcursor CURSOR cursfile.cur

Program source: hCursor = LoadCursor (hInstance, "mycursor");

The other methods shown for icons (using ID numbers and MAKEINTRESOURCE) work with cursors also. WINDOWS.H includes a *typedef* definition for HCURSOR that you can use for storing the cursor handle. (Both HICON and HCURSOR are defined as HANDLE.)

You can use the cursor handle obtained from LoadCursor when setting the hCursor member of the window class structure:

```
wndclass.hCursor = LoadCursor (hInstance, "mycursor");
```

This causes the mouse cursor to be displayed as your customized cursor when the mouse is within the client area of your window.

If you use child windows, you may want the cursor to appear differently depending on the child window below the cursor. If your program defines the window class for these child windows, you can use different cursors for each class by appropriately setting the *hCursor* field in each window class. And if you use predefined child window controls, you can alter the *hCursor* field of the window class using:

```
SetClassWord (hWndChild, GCW_HCURSOR,
LoadCursor (hInstance, "childcursor");
```

If you separate your client area into smaller logical areas without using child windows, you can use SetCursor to change the mouse cursor:

```
SetCursor (hCursor) ;
```

You should call *SetCursor* during processing of the WM_MOUSEMOVE message. Otherwise, Windows uses the cursor specified in the window class to redraw the cursor when it is moved. RESOURC1 uses the name of the program for the name of the cursor:

```
resourc1 CURSOR resourc1.cur
```

When RESOURCLC defines the window class, this szAppName variable is used for LoadCursor:

```
wndclass.hCursor = LoadCursor (hInstance, szAppName) ;
```

RESOURCES AND MEMORY

The LoadIcon and LoadCursor functions certainly sound as if they load the icon or cursor from the .EXE file into memory. They do not. Windows doesn't load the icon or cursor until it needs the object for drawing. During loading, Windows reduces the object to fit the dimensions of the display.

Icons and cursors (as well as all other resources except bitmaps) are "owned" by the program. In the HEAPWALK program you'll see icons and cursors identified with the program's module name. Multiple instances of the same program share the same cursors and icons loaded into memory. When the last instance terminates, Windows frees up the memory occupied by the resource. And for most resources, Windows can discard the resource from memory to generate free space and then load it back into memory when needed.

You can override some of these characteristics, however. For all resources except the keyboard accelerators (covered in Chapter 10), you can specify "load" and "memory" options in the resource script file. These options are similar to the module definition file options for code and data segments discussed in Chapter 8. In the resource script, the load and memory options follow the resource type. This is the generalized form of the ICON statement in a resource script file:

iconID ICON [load-option] [memory-option] iconfile.ico

The load option can be either PRELOAD or LOADONCALL. A resource defined as PRELOAD will be loaded into memory when the program is loaded. LOADONCALL means that the resource will not be loaded until Windows needs it. LOADONCALL is the default for all resources. You will probably want to use PRELOAD only when you know that your program will need the resource immediately after beginning to execute.

The memory options are FIXED, MOVEABLE, and DISCARDABLE. DISCARDABLE resources must also be MOVEABLE. For the resources discussed in this chapter, the icon, cursor, and character string resources have default memory options of MOVEABLE and DISCARDABLE. The bitmap and user-defined resources are MOVEABLE only. Why the difference? Icon, cursor, and character string resources are read-only, so Windows can safely discard them from memory. Windows allows bitmaps and user-defined resources to be modified from within a program, however, and modified resources cannot be discarded.

Bitmaps: Pictures in Pixels

We've already talked about the use of monochrome bitmaps in icons and cursors. Windows also includes a resource type called BITMAP.

Bitmaps are used for two major purposes. The first is to draw pictures on the display. For instance, the Windows display driver files contain lots of tiny bitmaps used for drawing the arrows in scroll bars, the check mark in pull-down menus, the system menu box, the size box, check boxes, and radio buttons. At the other extreme is the graphics menu that dominates the top of PAINT's client area. That menu is a bitmap 493 pixels wide and 83 pixels high. The second major use of bitmaps is to create brushes. Brushes, you'll recall, are patterns of pixels that Windows uses to fill an area of the display. (Chapter 10 discusses a third and less common use of bitmaps, as selection items in menus.)

The bitmaps used in icon and cursor resources are monochrome bitmaps that have one bit per pixel. However, bitmap resources can include color. Because ICONEDIT creates only monochrome bitmap resources, we'll have to use a different method to create a color bitmap resource later in this chapter.

Once we start talking about bitmaps, we're really verging on GDI territory. For that reason, the discussion about bitmaps here is brief; we'll pick up the topic again in Chapter 14.

The Bitmap File Format

Bitmap files usually have a .BMP extension. The general structure of these files is similar to that of .ICO and .CUR files except that the header is 16 bytes long:

Offset	Size	Value	
0	Byte	2	
1	Byte	80H for discardable bitmap	
4	Word	Width in pixels	
6	Word	Height in pixels	
8	Word	Width in bytes (must be even)	
10	Byte	Number of color planes	
11	Byte	Number of color bits per pixel	
16	is thicis.	Bitmap	

The bytes that make up the bitmap must use an even number of bytes per row. The bitmap is stored as if the width in pixels were a multiple of 16. However, the "width in pixels" field gives the actual width.

Notice that this file contains no information about the displayed size or aspect ratio of the bitmap. Bitmaps are inherently device dependent. Different displays have different resolutions and different aspect ratios. If you use bitmaps to draw pictures on the client area of your window, you must take this fact into account and use *StretchBlt* to scale the bitmap accordingly. This scaling can result in the same problems we encountered when designing icons and cursors.

The device-dependent aspect of bitmaps also presents a problem with color. You'll notice that the bitmap header has fields called "number of color planes" and "number of color bits per pixel." These two fields refer to the actual physical organization of memory in the display adapter (or if the display adapter is not memory mapped, to the organization of bitmap memory that must be passed to the display adapter by other means). When Windows uses the <code>BitBlt</code> function to transfer a bitmap stored in memory to the display, the bitmap must be organized in the same way as the memory on the display adapter.

Let's take an example. We'll assume that a particular video board and monitor can display 256 pure (nondithered) colors. These 256 colors are in turn made up of 8 primary colors. The memory on the video board can be organized in one of two ways. In the first approach, the display adapter has eight color planes, each occupying the same area in memory. The display driver can select any particular color plane by writing to an output port on the adapter. The color of a particular pixel is determined by 1 bit in each color plane. The "number of color planes" is eight, and the "number of color bits per pixel" is one. This organization method is shown in Figure 9-4.




Figure 9-4. The organization of video memory using multiple color planes

In the second approach, the display adapter uses 1 byte per pixel. Each bit of the byte represents one of the eight primary colors. The value of the byte is the color of the pixel. The "number of color planes" is one, and the "number of color bits per pixel" is eight. This organization method is shown in Figure 9-5.




Figure 9-5. The organization of video memory using consecutive bits per pixel

Obviously, one form of the bitmap could be translated into the other form, but how do you handle conversions of color bitmaps to display adapters with fewer colors? A solution to this problem awaits future releases of Windows. Currently, the only color bitmap format recommended for use is that for the IBM Enhanced Graphics Adapter and Video Graphics Array in the eight-color mode. This uses three color planes and one color bit per pixel. The red plane appears first in the file, followed by the green plane and the blue plane.

Using Bitmaps and Brushes

The RESOURC2 program, shown in Figure 9-6, is an upgraded version of RESOURC1 that includes a bitmap resource used to create a brush for the background of the client area. The bitmap was created in ICONEDIT with dimensions of 8 by 8, which is the minimum size for a brush.

```
resourc2.obj : resourc2.c
    c1 -c -D LINT_ARGS -Gsw -Os -W2 -Zp resourc2.c

resourc2.res : resourc2.rc resourc2.ico resourc2.cur resourc2.bmp
    rc -r resourc2.rc

resourc2.exe : resourc2.obj resourc2.def resourc2.res
    link4 resourc2, /align:16, /map, slibw, resourc2
    rc resourc2.res
```

```
/* RESOURC2.C -- Icon and Cursor Demonstration Program No. 2 */
#include <windows.h>
long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG) ;
     szAppName[] = "Resourc2" ;
HANDLE hinst ;
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
    HANDLE hInstance, hPrevInstance;
             lpszCmdLine ;
     LPSTR
             nCmdShow ;
     int
    HBITMAP hBitmap ;
     HBRUSH
             hBrush :
             hWnd ;
     HWND
     MSG
              msq ;
     WNDCLASS wndclass ;
     hBitmap = LoadBitmap (hInstance, szAppName) ;
     hBrush = CreatePatternBrush (hBitmap) ;
```

Figure 9-6. The RESOURC2 program, including an icon, a cursor, and a bitmap

Figure 9-6. Continued

```
if (!hPrevInstance)
            wndclass.style
                                       = CS HREDRAW | CS VREDRAW ;
            wndclass.lpfnWndProc
wndclass.cbClsExtra = 0;
wndclass.cbWndExtra = 0;
wndclass.hInstance = hInstance;
wndclass.hInstance = hInstance;
szAppName);
addlass.hIcon = LoadIcon (hInstance, szAppName);
            wndclass.hCursor = LoadIcon (hInstance, szAppName);
wndclass.hCursor = LoadCursor (hInstance, szAppName);
            wndclass.hbrBackground = hBrush ;
            wndclass.lpszMenuName = NULL;
wndclass.lpszClassName = szAppName;
            if (!RegisterClass (&wndclass))
                  return FALSE :
      hInst = hInstance ;
      hWnd = CreateWindow (szAppName, "Icon and Cursor Demo",
                              WS OVERLAPPEDWINDOW,
                              CW USEDEFAULT, 0,
                              CW USEDEFAULT, 0,
                              NULL, NULL, hInstance, NULL) ;
      ShowWindow (hWnd, nCmdShow) ;
      UpdateWindow (hWnd) ;
     while (GetMessage (&msg, NULL, 0, 0))
            TranslateMessage (&msg) ;
            DispatchMessage (&msg) ;
      DeleteObject (hBrush) ; /* clean-up */
      DeleteObject (hBitmap) ;
      return msg.wParam ;
long FAR PASCAL WndProc (hWnd, iMessage, wParam, lParam)
      HWND
                hWnd ;
iMessage ;
      unsigned
      WORD
                   wParam :
      LONG
                    1Param ;
      static HICON hIcon ;
      static short xIcon, yIcon, xClient, yClient;
                    hDC ;
     PAINTSTRUCT ps ;
     RECT
                     rect :
     short
                    x, y ;
     switch (iMessage)
            case WM CREATE:
                 hIcon = LoadIcon (hInst, szAppName) ;
                  xIcon = GetSystemMetrics (SM_CXICON) ;
                  yIcon = GetSystemMetrics (SM CYICON) ;
                  break ;
```

Figure 9-6. Continued

resourc2 ICON resourc2.ico resourc2 CURSOR resourc2.cur resourc2 BITMAP resourc2.bmp






Figure 9-6. Continued





NAME

STUB

CODE

DATA

RESOURC2 DESCRIPTION 'Icon and Cursor Demo Program No. 2 (C) Charles Petzold, 1987' 'WINSTUB.EXE' MOVEABLE MOVEABLE MULTIPLE HEAPSIZE 1024 STACKSIZE 4096 EXPORTS

The bitmap resource is included in the resource script in the same format as the icon and cursor:

resourc2 BITMAP resourc2.bmp

WndProc

The LoadBitmap function used in WinMain is similar to the LoadIcon and LoadCursor calls. It returns a handle to a bitmap:

hBitmap = LoadBitmap (hInstance, szAppName) ;

This handle is then used to create a pattern brush. The brush is based on the bitmap:

```
hBrush = CreatePatternBrush (hBitmap) ;
```

When Windows fills an area of the display with this brush, the bitmap is repeated horizontally and vertically every eight pixels. We want to use this brush to color the background of the client area, which we accomplish when defining the window class:

```
wndclass.hbrBackground = hBrush ;
```

The major difference between bitmaps and other resources is simply stated but practically significant: Bitmaps are GDI objects. They are *not* shared among instances of your program, and they are *not* automatically deleted from memory when your program terminates. If you run HEAPWALK when RESOURC2 is loaded, you will not see the bitmap listed with the RESOURC2 module name. The bitmap (and the brush created with that bitmap) will be one of the many objects identified with the GDI module name. Because bitmaps and brushes are GDI objects, they must be deleted before the program terminates. In RESOURC2 this is done at the end of *WinMain*:

```
DeleteObject (hBrush) ;
DeleteObject (hBitmap) ;
```

If you have an EGA working in color, you might want to try substituting a color bitmap for RESOURC2.BMP. Because ICONEDIT can't create color bitmaps, we have to crank this one out by hand. First, create a file called COLORBIT.SCR that looks like this:

```
N COLORBIT.BMP
E 100 2 0 0 0 8 0 8 0 2 0 3 1 0 0 0 0
E 110 0 0 7E 0 7E 0 18 0 18 0 0 0 0 0 0 0
E 120 0 0 0 0 0 0 7E 0 7E 0 0 0 0 0 0 0 0
E 130 0 0 0 0 0 18 0 18 0 7E 0 7E 0 0 0
R CX
40
W
```

This is a DEBUG script file. The third, fourth, and fifth lines are bit patterns for the red, green, and blue planes, in that order. (The initial E stands for "enter.") You can create COLORBIT.BMP by executing:

```
DEBUG < COLORBIT. SCR
```

Now change RESOURC2.RC to reference this bitmap:

```
resourc2 BITMAP colorbit.bmp
```

and change the line in the make file showing the files that contribute to RESOURC2.RES:

```
resourc2.res : resourc2.rc resourc2.ico resourc2.cur colorbit.bmp
rc -r resourc2.rc
```

Now recompile and run it.

CHARACTER STRINGS

Having a resource for character strings may seem odd at first. Certainly we haven't had any problem using regular old character strings defined as variables right in our source code.

Character string resources are primarily for easing the translation of your program to other languages. As you'll discover in the next two chapters, menus and dialog boxes are also part of the resource script. If you use character string resources rather than put strings directly into your source code, then all text that your program uses will be in one file—the resource script. If the text in this resource script is translated, all you need do to create a foreign-language version of your program is relink the program and add the translated resources to the .EXE file. This method is much safer than messing around with your source code. (Of course, you could alternatively define all your character strings as macros and store them in a header file. This method also avoids altering source code during language translations.)

A second reason for using character string resources is to reduce memory space. This reason is less obvious—in fact, if you use character string resources inefficiently, you might not reduce memory space at all. We'll examine this problem after we get through the basics.

Using Character String Resources

The character string resources are defined in your resource script using the keyword STRINGTABLE:

```
STRINGTABLE [load option] [memory option]

BEGIN

nID1, "character string 1"

nID2, "character string 2"

lother string definitions|

END
```

The resource script can contain only one string table. LOADONCALL is the default load option; MOVEABLE and DISCARDABLE are the default memory options. Each string can be only one line long with a maximum of 255 characters. The strings cannot contain any C-style control characters except for \t (tab). However, the strings can contain octal constants:

```
        Tab
        \011

        Linefeed
        \012

        Carriage return
        \015
```

These control characters are recognized by the DrawText and MessageBox functions.

Your program can use the *LoadString* call to copy a string resource into a buffer in the program's data segment:

```
LoadString (hInstance, nID, lpszBuffer, nMaxLength) ;
```

The nID parameter refers to the ID number that precedes each string in the resource script, lpszBuffer is a far (or long) pointer to a character array that receives the character string; and nMaxLength is the maximum number of characters to transfer into the lpszBuffer. The string ID numbers that precede each string are generally macro identifiers defined in a header file. Many Windows programmers use the prefix IDS_ to denote an ID number for a string. Sometimes a filename or other information must be imbedded in the string when the string is displayed. In this case you put C formatting characters in the string and use it as a formatting string in sprintf.

Using Strings with MessageBox

Let's look at an example of a program that uses three text strings to display three error messages in a message box. A header file that we'll call PROGRAM.H defines three identifiers for these messages:

```
#define IDS_FILENOTFOUND 1
#define IDS_FILETOOBIG 2
#define IDS_FILEREADONLY 3
```

The resource script looks like this:

The C source code file also includes this header file and defines a function to display a message box. (I'm assuming that szAppName is a global variable that contains the program name):

To display a message box containing the "file not found" message, the program calls:

```
OkMessage (hWnd, IDS_FILENOTFOUND, szFileName);
```

Character Strings and Memory Space

Character string resources usually save memory space, but the amount of space saved depends on how efficiently they're used. When the RC.EXE resource compiler adds strings to the .EXE file, the strings are grouped into different segments depending on the ID numbers of the strings. Each segment contains a maximum of 16 strings. Strings with ID numbers from 0 to 15 are stored in one segment, 16 through 31 are in another, and so forth. Because of this grouping into segments, your .EXE file will be shorter if you use consecutive numbers for your string IDs.

When you use LoadString to copy a string resource into memory, however, Windows loads the entire segment (containing up to 16 strings) into memory as a resource. Windows then also copies the content of the string specified in the LoadString call to a buffer in your program's data segment. So when string resources are loaded into memory, they initially occupy less memory if you do not use consecutive numbers for the string IDs. Probably the worst way to use string resources is to load all the strings into separate global static arrays during program initialization in WinMain. If you do that, you don't use any less space than if you had included the strings in your C source code. In fact, you'll use more space, because you'll set the size of these arrays somewhat larger than the actual string lengths. Here are some general rules for using string resources:

- Assign string ID numbers according to logical groupings. For instance, if five strings
 are involved in one section of your program and six strings are involved in another
 section, you might use ID numbers 0 to 4 for the first group of strings and 16 to 21 for
 the second group.
- Whenever possible, load the strings into automatic local variables within functions, thus freeing up the space when the function is exited. (The OkMessage function shown above uses this approach.)
- Alternatively, reuse a single static array for loading strings.

Here's an example of the last approach. Let's assume that your program never requires more than one string at a time. You can define a function that loads the string and returns a pointer to a static variable containing the string:

```
char *String (wID)
    WORD wID ;
    (
    static szBuffer [256] ;

LoadString (hInst, wID, szBuffer, 255) ;
    return buffer ;
}
```

If you want to use DrawText to display the string with ID number 45, you use this statement:

```
DrawText (hDC, String (45), -1, &rect, DT_LEFT) ;
```

Each call to String destroys the contents of the static buffer. If you require access to (for instance) three strings at one time, you can modify String as follows:

```
char *String (wID, n)
    WORD wID;
    short n;
    {
        static szBuffer [3][256];
    LoadString (hInst, wID, szBuffer [n], 255);
    return szBuffer [n];
}
```

When you call String now, you pass an ID number and a second parameter that is either 0, 1, or 2.

USER-DEFINED RESOURCES

The "user-defined resource" is convenient for attaching miscellaneous data to your .EXE file and obtaining access to that data within the program. The data can be in any format you want. The Windows functions used to access user-defined resources return a far pointer to the data when Windows loads the data into memory. You can do whatever you want with that data. For instance, suppose you have a file called PROGHELP.TXT that contains "help" text for your program. This file needn't be a pure ASCII file—it can also contain binary data, such as pointers that would aid your program in referencing various sections of this file. Reference this file with a statement in your resource script that looks like this:

```
helptext TEXT proghelp.txt
```

For helptext (the name of the resource) and TEXT (the type of the resource), you can use any names you want. I've capitalized TEXT simply to make it look like the ICON, CURSOR, and BIT-MAP statements. What we're doing here is making up our own type of resource called TEXT.

During program initialization (for instance, during processing of the WM_CREATE message), you can obtain a handle to this resource:

```
hResource = LoadResource (hInstance,
FindResource (hInstance, "helptext", "TEXT"));
```

The variable hResource can be defined with type HANDLE. Despite its name, LoadResource does not actually load the resource into memory just yet. The LoadResource and FindResource functions used together like this are essentially equivalent to the LoadIcon and LoadCursor functions. In fact, LoadIcon and LoadCursor use the LoadResource and FindResource functions.

You can use numbers rather than names for the resource name and resource type. The numbers can be converted to far pointers in the *FindResource* call using *MakeIntResource*. The numbers used for the resource type must be greater than 255. (Windows uses numbers between 1 and 9 when calling *FindResource* for existing resource types.)

When you need access to the text, call LockResource:

```
lpHelpText = LockResource (hResource) ;
```

LockResource loads the resource into memory (if it has not already been loaded), locks it using the GlobalLock function, and returns a far pointer to it. When you are finished accessing the memory, unlock the segment:

```
GlobalUnlock (hResource) ;
```

This allows Windows to move the segment in memory. When you're finished with the resource, you can free it from memory:

```
FreeResource (hResource) ;
```

The resource will be freed when your program terminates even if you don't call FreeResource.

Normally, user-defined resources are not discardable unless you include the DISCARD-ABLE keyword before the filename in the resource script. But if you use the pointer returned from LockResource to alter as well as read the data, don't make the resource DISCARDABLE. Note also that the same resource is shared among all instances of the program. If each instance needs its own copy of the resource, you should make the resource discardable, use LockResource to obtain a pointer to the resource, use GlobalAlloc to obtain a global memory block of the same size, use GlobalLock to lock that block, and then copy the contents of the resource into the global memory block.

Let's look at a sample program that uses three resources—an icon, a string table, and a user-defined resource. The POEPOEM program, shown in Figure 9-7, displays the text of Edgar Allan Poe's "Annabel Lee" in its client area. The user-defined resource is the file POEPOEM.ASC, which contains the text of the poem. The text file can be terminated with an ASCII end-of-file indicator or a 0.

Figure 9-7. The POEPOEM program, including an icon and a user-defined resource

```
/* POEPOEM.C -- Demonstrates User-Defined Resource */
#include <windows.h>
#include "poepoem.h"
long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG) ;
      szAppName [10] ;
char
     szCaption [35] ;
char
HANDLE hinst ;
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
     HANDLE hInstance, hPrevInstance;
               lpszCmdLine ;
     LPSTR
               nCmdShow ;
     int
     HWND
               hWnd :
     MSG
               msor
     WNDCLASS wndclass ;
     if (!hPrevInstance)
           LoadString (hInstance, IDS APPNAME, szAppName, sizeof szAppName) ;
           LoadString (hInstance, IDS CAPTION, szCaption, sizeof szCaption) ;
                                    = CS HREDRAW | CS VREDRAW ;
           wndclass.style
           wndclass.lpfnWndProc = WndProc ;
           wndclass.cbClsExtra = 0;
           wndclass.cbWndExtra = 0 ;
           wndclass.hInstance
                                    = hInstance ;
          wndclass.hIcon = LoadIcon (hInstance, szAppName
wndclass.hCursor = LoadCursor (NULL, IDC_ARROW);
                                    = LoadIcon (hInstance, szAppName) ;
           wndclass.hbrBackground = GetStockObject (WHITE BRUSH) ;
          wndclass.lpszMenuName = NULL ;
          wndclass.lpszClassName = szAppName ;
           if (!RegisterClass (&wndclass))
                return FALSE ;
     else
           GetInstanceData (hPrevInstance, szAppName, sizeof szAppName) ;
GetInstanceData (hPrevInstance, szCaption, sizeof szCaption) ;
     hInst = hInstance ;
     hWnd = CreateWindow (szAppName, szCaption, WS_OVERLAPPEDWINDOW | WS_CLIPCHILDREN,
                           CW USEDEFAULT, 0,
                            CW USEDEFAULT, 0,
                           NULL, NULL, hInstance, NULL) ;
     ShowWindow (hWnd, nCmdShow) ;
     UpdateWindow (hWnd) ;
     while (GetMessage (&msg, NULL, 0, 0))
           TranslateMessage (&msg) ;
           DispatchMessage (&msg) ;
     return msg.wParam ;
```

```
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
     HWND
                  hWnd ;
     unsigned
                  iMessage ;
     WORD
                   wParam ;
     LONG
                   1Param ;
     static HANDLE hResource ;
     static HWND hScroll; static short nPosition, xChar, yChar, yClient, nNumLines, xScroll;
     char
                   szPoemRes [15] ;
     char far
                   *lpText ;
                   hDC ;
     HDC
                   ps ;
     PAINTSTRUCT
     RECT
                   rect ;
     TEXTMETRIC
                   tm ;
     switch (iMessage)
          case WM CREATE:
               hDC = GetDC (hWnd) ;
               GetTextMetrics (hDC, &tm) ;
               xChar = tm.tmAveCharWidth ;
               yChar = tm.tmHeight + tm.tmExternalLeading ;
               ReleaseDC (hWnd, hDC) ;
               xScroll = GetSystemMetrics (SM CXVSCROLL) ;
               hScroll = CreateWindow ("scrollbar", NULL,
                               WS_CHILD | WS_VISIBLE | SBS_VERT,
                               0, 0, 0, 0,
hWnd, 1, hInst, NULL) ;
               LoadString (hInst, IDS_POEMRES, szPoemRes, sizeof szPoemRes) ;
               hResource = LoadResource (hInst,
FindResource (hInst, szPoemRes, "TEXT"));
               lpText = LockResource (hResource) ;
               nNumLines = 0 ;
               while (*lpText != '\0' && *lpText != '\x1A')
                     if (*lpText == '\n')
                          nNumLines ++ ;
                     lpText = AnsiNext (lpText) ;
                *lpText = '\0';
               GlobalUnlock (hResource) ;
               SetScrollRange (hScroll, SB_CTL, 0, nNumLines, FALSE) ;
               SetScrollPos (hScroll, SB CTL, 0, FALSE) ;
               break ;
          case WM SIZE:
               MoveWindow (hScroll, LOWORD (lParam) - xScroll, 0,
                    xScroll, yClient = HIWORD (1Param), TRUE) ;
               SetFocus (hWnd) ;
               break ;
```

```
case WM SETFOCUS:
          SetFocus (hScroll) ;
          break :
     case WM VSCROLL:
         switch (wParam)
               case SB TOP:
                    nPosition = 0 ;
                    break ;
               case SB BOTTOM:
                    nPosition = nNumLines ;
                    break ;
               case SB LINEUP:
                     nPosition -= 1 ;
                     break :
               case SB LINEDOWN:
                    nPosition += 1 ;
                     break ;
               case SB PAGEUP:
                    nPosition -= yClient / yChar ;
                    break ;
               case SB PAGEDOWN:
                     nPosition += yClient / yChar ;
                     break ;
               case SB THUMBPOSITION:
                    nPosition = LOWORD (1Param) ;
                     break :
          nPosition = max (0, min (nPosition, nNumLines));
          if (nPosition != GetScrollPos (hScroll, SB CTL))
               SetScrollPos (hScroll, SB CTL, nPosition, TRUE) ; InvalidateRect (hWnd, NULL, TRUE) ;
          break ;
     case WM PAINT:
          hDC = BeginPaint (hWnd, &ps) ;
          lpText = LockResource (hResource) ;
          GetClientRect (hWnd, &rect) ;
          rect.left += xChar
          rect.top += yChar * (1 - nPosition) ;
          DrawText (hDC, lpText, -1, &rect, DT_EXTERNALLEADING) :
          GlobalUnlock (hResource) ;
          EndPaint (hWnd, &ps) ;
          break ;
     case WM DESTROY:
          FreeResource (hResource) ;
          PostQuitMessage (0) ;
     default:
          return DefWindowProc (hWnd, iMessage, wParam, 1Param) ;
return OL ;
```

Figure 9-7. Continued

```
#define IDS_APPNAME 0
#define IDS_CAPTION 1
#define IDS_POEMRES 2
```

```
#include "poepoem.h"

poepoem ICON poepoem.ico
AnnabelLee TEXT poepoem.asc

STRINGTABLE

BEGIN

IDS_APPNAME, "poepoem"

IDS_CAPTION, """Annabel Lee"" by Edgar Allan Poe"

IDS_POEMRES, "AnnabelLee"

END
```



It was many and many a year ago,
In a kingdom by the sea,
That a maiden there lived whom you may know
By the name of Annabel Lee;
And this maiden she lived with no other thought
Than to love and be loved by me.

I was a child and she was a child
In this kingdom by the sea,
But we loved with a love that was more than love -I and my Annabel Lee -With a love that the winged seraphs of Heaven
Coveted her and me.

And this was the reason that, long ago,
In this kingdom by the sea,
A wind blew out of a cloud, chilling
My beautiful Annabel Lee;
So that her highborn kinsmen came
And bore her away from me,
To shut her up in a sepulchre
In this kingdom by the sea.

The angels, not half so happy in Heaven,
Went envying her and me -Yes! that was the reason (as all men know,
In this kingdom by the sea)
That the wind came out of the cloud by night,
Chilling and killing my Annabel Lee.

But our love it was stronger by far than the love
Of those who were older than we -Of many far wiser than we -And neither the angels in Heaven above
Nor the demons down under the sea
Can ever dissever my soul from the soul
Of the beautiful Annabel Lee:

For the moon never beams, without bringing me dreams
Of the beautiful Annabel Lee;
And the stars never rise, but I feel the bright eyes
Of the beautiful Annabel Lee:
And so, all the night-tide, I lie down by the side
Of my darling -- my darling -- my life and my bride,
In her sepulchre there by the sea -In her tomb by the sounding sea.

[May, 1849]

NAME POEPOEM
DESCRIPTION 'Demo of User-Defined Resource (C) Charles Petzold, 1987'
STUB 'WINSTUB.EXE'
CODE MOVEABLE MULTIPLE
HEAPSIZE 1024
EXPORTS Windproc

In the POEPOEM.RC resource script, the user-defined resource is given the type TEXT and the name *AnnabelLee*:

AnnabelLee TEXT poepoem.asc

During WM_CREATE processing in WndProc, a handle to the resource is obtained using FindResource and LoadResource. The resource is locked using LockResource, and a small routine replaces any end-of-file marker with a 0. (This is for the benefit of the

DrawText function used later.) In most cases it's not a good idea to write on a user-defined resource directly, because the same resource is shared among all instances of the program. However, later instances of POEPOEM will not encounter problems with the change we've made. The resource is then unlocked using GlobalUnlock.

The resource is also locked and unlocked during processing of WM_PAINT to write the text to the display using *DrawText*. Note the use of a child window scroll bar control rather than a window scroll bar. The child window scroll bar control has an automatic keyboard interface, so no WM_KEYDOWN processing is required in POEPOEM.

POEPOEM also uses three character strings, the IDs of which are defined in the POEPOEM.H header file. For the first instance of the program, the IDS_APPNAME and IDS_CAPTION strings are loaded into global static variables using LoadString:

```
LoadString (hInstance, IDS_APPNAME, szAppName, sizeof szAppName);
LoadString (hInstance, IDS_CAPTION, szCaption, sizeof szCaption);
```

However, for subsequent instances of POEPOEM, the strings are copied from the previous instance:

```
GetInstanceData (hPrevInstance, szAppName, sizeof szAppName);
GetInstanceData (hPrevInstance, szCaption, sizeof szCaption);
```

GetInstanceData is faster than LoadString if the string resource has been discarded from memory. The pointers (szAppName and szCaption) are near pointers to static global variables. Windows uses these pointers in combination with the data segment address of the previous instance and the data segment address of the current instance to copy the contents of the variables.

Now that we've defined all the text strings used in POEPOEM as resources, we've made it easier for translators to convert the program into a foreign-language version. Of course, they'd also have to translate the text of "Annabel Lee"—which would, I suspect, be a somewhat more difficult job.



Chapter 10

Menus and Accelerators

Menus are an important part of the consistent user interface that Windows programs offer. Adding a menu to your program is a relatively easy part of Windows programming: You simply define the structure of the menu in your resource script and assign a unique ID number to each menu item. You specify the name of the menu in the window class structure. When the user chooses a menu item, Windows sends your program a WM_COMMAND message containing that ID. But we won't stop with that simple example. One of the more interesting things you can do with menus is display bitmaps in the menu rather than character strings, so we'll take a detailed look at how that is done.

This chapter also covers "keyboard accelerators." These are key combinations that are used primarily to duplicate menu functions.

MENUS

A window's menu bar is displayed immediately below the caption bar. This menu bar is sometimes called a program's "main menu" or the "top-level menu." Items listed in the top-level menu almost always invoke a drop-down menu, which is called either a "popup menu" or a "submenu." Current versions of Windows do not support any additional nesting of popups. Sometimes items in popup menus invoke a dialog box for more information.

(Dialog boxes are covered in Chapter 11.) Most parent windows have, to the far left of the caption bar, a box containing a single dashed line. This box invokes the system menu, which is really another popup menu.

Menu items in popups can be "checked," which means that Windows draws a small check mark to the left of the menu text. This lets the user choose different program options from the menu. These options can be mutually exclusive, but they don't have to be. Top-level menu items cannot be checked.

Menu items in the top-level menu or in popup menus can be "enabled," "disabled," or "grayed." The words "active" and "inactive" are sometimes used synonymously with "enabled" and "disabled." Menu items flagged as enabled and disabled look the same to the user, but a grayed menu item is displayed in gray text.

From the perspective of the user, enabled, disabled, and grayed menu items can all be "selected," or highlighted. That is, the user can click the mouse on a disabled menu item, or move the reverse-video cursor bar to a disabled menu item, or trigger the menu item using the item's key letter. However, from the perspective of your program, enabled, disabled, and grayed menu items function differently. Windows sends your program a WM_COMMAND message only for enabled menu items. You use disabled and grayed menu items for options that are not currently valid. If you want to let the user know the option is not valid, make it grayed.

Menu Structure

When you create or change menus in a program, it's useful to think of the top-level menu and each popup menu as being separate menus. The top-level menu has a menu handle, each popup menu within a top-level menu has its own menu handle, and the system menu (which is also a popup) has a menu handle.

Each item in a menu is defined by three characteristics: The first characteristic is what appears in the menu. This is either a text string or a bitmap. The second characteristic is either an ID number that Windows sends to your program in a WM_COMMAND message or a popup menu that Windows displays when the user chooses that menu item. The third characteristic describes the attribute of the menu item, including whether the item is disabled, grayed, or checked.

The Menu Template

You can create a menu in three different ways. The most common (and the easiest) is to define the menu in your resource script in the form of a menu template. This example shows all the different options you can use in this template.

```
MyMenu MENU [load option] [memory option]
    BEGIN
         MENUITEM "&One", 1
         POPUP "&Two"
              BEGIN
                   MENUITEM "&Ten",
                                         10, CHECKED
                   MENUITEM "&Eleven",
                                         1.1
                   MENUITEM SEPARATOR
                                         12, INACTIVE
                   MENUITEM "Tawelve",
                   MENUITEM "T&hirteen", 13
                   MENUITEM "&Fourteen", 14, MENUBREAK
                   MENUITEM "F&ifteen",
                                          15,
                   MENUITEM "&Sixteen",
                                        16, MENUBARBREAK
                   MENUITEM "Seaventeen", 17,
                   MENUITEM "Ei&ghteen", 18, GRAYED
              END
         MENUITEM "Th&ree", 3
         MENUITEM "&Four",
                            4, INACTIVE
         MENUITEM "Fi&ve",
                            5
         MENUITEM "Si&x",
                            6, MENUBREAK
         MENUITEM "&Seven", 7,
         MENUITEM "&Eight", 8, GRAYED
         MENUITEM "\a&Help", 9, HELP
    END
```

This particular menu template defines a top-level menu that displays the labels "One" through "Eight" and "Help," as shown in Figure 10-1. Only the second item invokes a popup menu. The popup menu displays the labels "Ten" through "Eighteen," as shown in Figure 10-2.



Figure 10-1. A top-level menu




Figure 10-2. A popup menu

MyMenu is the name of the menu. This name performs the same function as the names of icon, cursor, and bitmap resources discussed in Chapter 9. As with other resources, the load option on the MENU statement can be either PRELOAD, in which case Windows loads the resource into memory when the program is executed; or LOADONCALL, in which case Windows loads the resource into memory only when it is needed. The default is LOADONCALL. The memory options are FIXED, MOVEABLE, and DISCARDABLE. The default is MOVEABLE and DISCARDABLE. Discardable menus must also be moveable. Although we'll change menus in some of the programs shown later, don't worry that the menu resource is discardable. Windows makes a copy of the menu for your program to use and change.

The top-level menu is enclosed within BEGIN and END statements. The two types of statements allowed within the BEGIN and END group are:

```
MENUITEM "text", wID, options and:
```

POPUP "text", options

The text displayed for each menu must be enclosed in double quotation marks. An ampersand (&) causes the character that follows it to be underlined when Windows displays the menu. This is also the character Windows searches for when you select a menu item using the Alt key. If you don't include an ampersand in the text, no underline will appear, and Windows will use instead the first letter of the text for Alt-key searches.

The options on the MENUITEM and POPUP statements that appear in the top-level menu list are as follows:

- GRAYED—The menu item is inactive and does not generate a WM_COMMAND message. The text is grayed.
- INACTIVE—The menu item is inactive and does not generate a WM_COMMAND message. The text is displayed normally.
- · MENUBREAK—This item and following items appear on a new line of the menu.
- HELP—When used in combination with \a before the text, this item is right
 justified with a box around it.

Options can be combined using the C bitwise OR symbol (|), but GRAYED and INACTIVE cannot be used together. MENUBREAK is uncommon in a top-level menu, because Windows automatically separates a top-level menu into multiple lines if the window is too narrow to fit the entire menu.

Following a POPUP statement in the main menu, the keywords BEGIN and END block off a list of items in the popup. The following statements are allowed in a popup definition:

```
MENUITEM "text", wID, options and:
```

MENUITEM SEPARATOR

MENUITEM SEPARATOR draws a horizontal line in the popup menu. This line is often used to separate groups of related options.

For items in popup menus, you can use the columnar tab character \t in the text string. Text following the \tau is placed in a new column spaced far enough to the right to accommodate the longest text string in the first column of the popup. We'll see how this works when discussing keyboard accelerators toward the end of this chapter. A \tau right-justifies the text that follows it. The options for MENUITEM in a popup are as follows:

- · CHECKED-A check mark appears to the left of the text.
- GRAYED—The menu item is inactive and does not generate a WM_COMMAND message. The text is grayed.
- INACTIVE—The menu item is inactive and does not generate a WM_COMMAND message. The text is displayed normally.
- MENUBREAK—This item and the following items appear in a new column of the menu.
- MENUBARBREAK—This item and the following items appear in a new column of the menu. A vertical line separates the columns.

GRAYED and INACTIVE cannot be used together. MENUBREAK and MENUBARBREAK cannot be used together. You should use either MENUBREAK or MENUBARBREAK when the number of items in a popup is too long to be displayed in a single column.

The wID values in the MENUITEM statements are the numbers that Windows sends to the window function in menu messages. The wID values should be unique within a menu. Instead of using numbers, you'll probably want to use macro identifiers defined in a header file. By convention, these macro identifiers begin with the letters IDM ("ID for a menu").

Referencing the Menu in Your Program

Most Windows applications have only one menu in the resource script. The program makes reference to this menu in the definition of the window class:

```
wndclass.lpszMenuName = "MyMenu";
```

Programmers often use the name of the program as the name of the menu so that the same text string can also be used for the window class, the name of the program's icon, and the name of the menu. However, you can also use a number (or a macro identifier) for the menu rather than a name. The resource script would look like this:

```
45 MENU
BEGIN
[menu definition]
END
```

In this case, the assignment statement for the *lpszMenuName* field of the window class structure can be either:

```
wndclass.lpszMenuName = MAKEINTRESOURCE (45) ;
or:
   wndclass.lpszMenuName = "#45" ;
```

Although specifying the menu in the window class is the most common way to reference a menu resource, you have alternatives. A Windows application can load a menu resource into memory with the *LoadMenu* function, which is similar to the *LoadIcon* and *LoadCursor* functions described in Chapter 9. If you use a name for the menu in the resource script, *LoadMenu* returns a handle to the menu:

```
hMenu = LoadMenu (hInstance, "MyMenu") ;
```

hMenu = LoadMenu (hInstance, "#45");

If you use a number, the LoadMenu call takes either this form:

```
hMenu = LoadMenu (hInstance, MAKEINTRESOURCE (45)) ;
or this form:
```

You can then specify this menu handle as the ninth parameter to CreateWindow:

In this case, the menu specified in the *CreateWindow* call overrides any menu specified in the window class. You can think of the menu in the window class as being a default menu for the windows based on the window class if the ninth parameter to *CreateWindow* is NULL. Thus you can use different menus for several windows based on the same window class.

You can also have a NULL menu in the window class and a NULL menu in the CreateWindow call and assign a menu to a window after the window has been created:

```
SetMenu (hWnd, hMenu) ;
```

This form lets you dynamically change a window's menu. We'll see an example of this in the NOPOPUPS program shown later in this chapter.

Menus and Messages

Windows usually sends a window function several different messages when the user selects a menu item. In most cases your program can ignore many of these messages and simply pass them to <code>DefWindowProc</code>. Let's take a look at them anyway.

The first message your program receives when the user selects a menu item with the keyboard or mouse is a WM_SYSCOMMAND message. The values of wParam and IParam are shown below:

	wParam	<i>IParam</i>	
Mouse:	F09x	0	
Keyboard:	F10x	0	

The WINDOWS.H identifier SC_MOUSEMENU is equal to F090H; SC_KEYMENU is F100H, but the last digit in wParam (indicated by an x in the table above) can be anything. Use:

(wParam & 0xFFF0)

if you need to check this value. Most programs pass these messages to DefWindowProc.

The second message your program receives is a WM_INITMENU message with the following parameters:

wParam	LOWORD (IParam)	HIWORD (IParam)	
Handle to main menu	0	0	

The value of wParam is the handle to your main menu even if the user is selecting an item from the system menu. Windows programs generally ignore the WM_INITMENU message. Although the message exists to give you the opportunity to change the menu before an item is chosen, I suspect any changes to the top-level menu at this time would be very disconcerting to the user.

The next message your program receives is WM_MENUSELECT. A program can receive many WM_MENUSELECT messages as the user moves the cursor or mouse among the menu items. The parameters that accompany WM_SELECT are as follows:

wParam	LOWORD (lParam)	HIWORD (lParam)
Selected item: Menu ID		
or popup menu handle	Selection flags	Handle to menu containing selected item

WM_MENUSELECT is a menu-tracking message. The value of wParam tells you what item of the menu is currently selected, or highlighted. The "selection flags" in the low word of IParam can be a combination of the following: MF_GRAYED, MF_DISABLED, MF_CHECKED, MF_BITMAP, MF_POPUP, MF_HELP, MF_SYSMENU, and MF_MOUSESELECT. You may want to use WM_MENUSELECT if you need to change something in the client area of your window based on the movement of the highlight among the menu items. Most programs pass this message to DefWindowProc.

When Windows is ready to display a popup menu, it sends the window function a WM_INITPOPUP message with the following parameters:

wParam	LOWORD (lParam)	HIWORD (lParam)	
Popup menu handle	Popup index	1 for system menu, 0 otherwise	

This message is important if you need to enable or disable items in a popup menu before it is displayed. For instance, suppose your program can copy text from the Clipboard using the Paste command on a popup menu. When you receive a WM_INITPOPUP message for that popup, you should determine if the Clipboard has text in it. If it doesn't, you should gray the Paste menu item. We'll see an example of this in the revised POPPAD program shown toward the end of this chapter.

The most important menu message is WM_COMMAND. This message indicates that the user has chosen an enabled menu item from your window's menu. You'll recall from Chapter 7 that WM_COMMAND messages also result from child window controls. If you happen to use the same ID codes for menus and child window controls, you can differentiate between them by the low word of *IParam*, which will be 0 for a menu item:

	wParam	LOWORD (lParam)	HIWORD (lParam)
Мепи:	Menu ID	0	0
Control:	Control ID	Child window handle	Notification code

The WM_SYSCOMMAND message is similar to the WM_COMMAND message except that WM_SYSCOMMAND signals that the user has chosen an enabled menu item from the system menu:

	wParam	LOWORD (lParam)	HIWORD (lParam)
System menu:	Menu ID	0	0

The menu ID indicates which item on the system menu has been chosen. For the predefined system menu items, the bottom four bits should be masked out. The resultant value will be one of the following: SC_SIZE, SC_MOVE, SC_MINIMIZE, SC_MAXIMIZE, SC_NEXTWINDOW, SC_PREVWINDOW, SC_CLOSE, SC_VSCROLL, SC_HSCROLL, SC_ARRANGE, and SC_RESTORE. In addition, wParam can be SC_MOUSEMENU or SC_KEYMENU, as indicated earlier.

If you add menu items to the system menu, wParam will be the menu ID that you define. To avoid conflicts with the predefined menu IDs, use values below F000H. It is important that you pass normal WM_SYSCOMMAND messages to DefWindowProc. If you do not, you'll effectively disable the normal system menu commands.

The final message we'll discuss is WM_MENUCHAR, which isn't really a menu message at all. Windows sends this message to your window function in one of two circumstances: if the user presses Alt and a character key that does not correspond to a menu item, or, when a popup is displayed, if the user presses a character key that does not correspond to an item in the popup. The parameters that accompany the WM_MENUCHAR message are as follows:

wParam	LOWORD (lParam)	HIWORD (lParam)	
ASCII code	Selection code	Handle to menu	

The selection code is:

- 0—No popup is displayed.
- MF_POPUP—Popup is displayed.
- MF_SYSMENU—System menu popup is displayed.

Windows programs usually pass this message to *DefWindowProc*, which normally returns a 0 to Windows, which causes Windows to beep. We'll see a use for the WM_MENUCHAR message in the GRAFMENU program shown later in this chapter.

A Sample Program

Let's look at a simple example. The MENUDEMO program, shown in Figure 10-3, has three items in the main menu—File, Edit, and Background. Each of these items has a popup. MENUDEMO does the simplest and most common type of menu processing, which involves trapping WM_COMMAND messages and checking the value of wParam.

Figure 10-3. The MENUDEMO program

Figure 10-3. Continued

```
if (!hPrevInstance)
           wndclass.style
                                     = CS_HREDRAW | CS_VREDRAW ;
           wndclass.lpfnWndProc = WndProc;
wndclass.cbClsExtra = 0;
wndclass.cbWndExtra = 0;
           wndclass.hInstance = hInstance;
wndclass.hIcon = LoadIcon (NULL, IDI_APPLICATION);
wndclass.hCursor = LoadCursor (NULL, IDC_ARROW);
wndclass.hbrBackground = GetStockObject (WHITE_BRUSH);
           wndclass.lpszMenuName = szAppName ;
           wndclass.lpszClassName = szAppName ;
            if (!RegisterClass (&wndclass))
                 return FALSE ;
     hWnd = CreateWindow (szAppName, "Menu Demonstration",
                              WS OVERLAPPEDWINDOW,
                              CW USEDEFAULT, 0,
                              CW USEDEFAULT, 0,
                             NULL, NULL, hInstance, NULL) ;
      ShowWindow (hWnd, nCmdShow) ;
      UpdateWindow (hWnd) ;
      while (GetMessage (&msg, NULL, 0, 0))
            TranslateMessage (&msg) ;
            DispatchMessage (&msg) ;
     return msg.wParam ;
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
                  hWnd ;
     HWND
      unsigned
                    iMessage ;
      WORD
                   wParam ;
      LONG
                    lParam ;
      static int wColorID [6] = ( WHITE BRUSH, LTGRAY BRUSH, GRAY BRUSH,
                                         DKGRAY BRUSH, BLACK BRUSH, HOLLOW BRUSH ) ;
      static WORD wSelection = IDM WHITE ;
     HMENU
                   hMenu ;
      switch (iMessage)
            case WM COMMAND:
                  switch (wParam)
                        case IDM NEW:
                        case IDM OPEN:
case IDM SAVE:
                        case IDM SAVEAS:
                        case IDM UNDO:
                        case IDM CUT:
                       case IDM COPY:
                        case IDM PASTE:
                        case IDM CLEAR:
```

Figure 10-3. Continued

```
MessageBeep (0) ;
                       break ;
                                          /* Note: Logic below */
/* assumes that IDM_WHITE */
/* through IDM_HOLLOW are */
/* consecutive numbers in */
/* the order shown here. */
                  case IDM WHITE:
                 case IDM_LTGRAY:
case IDM_GRAY:
                  case IDM DKGRAY:
                  case IDM BLACK:
                 case IDM HOLLOW:
                       hMenu = GetMenu (hWnd) ;
                       CheckMenuItem (hMenu, wSelection, MF UNCHECKED) ;
                       wSelection = wParam ;
                       CheckMenuItem (hMenu, wSelection, MF CHECKED) ;
                       SetClassWord (hWnd, GCW HBRBACKGROUND,
                             GetStockObject (wColorID [wParam - IDM WHITE])) ;
                       InvalidateRect (hWnd, NULL, TRUE) ;
                       break ;
                 case IDM ABOUT:
                       MessageBox (hWnd, "Menu Demonstration Program.",
                             szAppName, MB_ICONASTERISK | MB_OK) ;
                 case IDM EXIT:
                       SendMessage (hWnd, WM CLOSE, 0, 0L) ;
                       break ;
                 case IDM_HELP:
                       MessageBox (hWnd, "Help not yet implemented.",
                             szAppName, MB_ICONASTERISK | MB OK) ;
                       break :
                 default:
                       break ;
           break ;
     case WM DESTROY :
           PostQuitMessage (0) ;
           break ;
     default :
           return DefWindowProc (hWnd, iMessage, wParam, 1Param) ;
return OL ;
```

MENUDEMORC

Figure 10-3. Continued

```
#define IDM_NEW
#define IDM_OPEN
                        2
#define IDM SAVE
#define IDM_SAVEAS 4
#define IDM_EXIT 5
#define IDM_ABOUT 6
                        6
#define IDM_UNDO 7
#define IDM_CUT 8
#define IDM COPY
                        9
#define IDM PASTE 10
#define IDM CLEAR 11
 #define IDM WHITE 12
 #define IDM LTGRAY 13
 #define IDM GRAY
                        14
 #define IDM_DKGRAY 15
#define IDM_BLACK 16
#define IDM_HOLLOW 17
 #define IDM HELP 18
```

```
#include "menudemo.h"
MenuDemo MENU
      BEGIN
            POPUP "&File"
                   BEGIN
                         MENUITEM "&New",
MENUITEM "&Open...",
MENUITEM "&Save",
                                                                IDM NEW
                                                                IDM OPEN
                                                                IDM SAVE
                         MENUITEM "Save &As...",
                                                             IDM SAVEAS
                         MENUITEM SEPARATOR
                         MENUITEM "E&xit", IDM EXIT
MENUITEM "A&bout Menudemo...", IDM ABOUT
                  END
            POPUP "&Edit"
                   BEGIN
                         MENUITEM "&Undo",
                                                               IDM UNDO
                         MENUITEM SEPARATOR
                                                         IDM_CUT
                         MENUITEM "Cu&t",
MENUITEM "&Copy",
MENUITEM "&Paste",
MENUITEM "C&lear",
                                                          IDM_COPY
IDM_PASTE
IDM_CLEAR
                  END
            POPUP "&Background"
                   BEGIN
                                                    IDM WHITE, CHECKED
IDM LITGRAY
IDM GRAY
IDM DKGRAY
IDM BLACK
                         MENUITEM "&White",
                         MENUITEM "&Lt Gray",
                         MENUITEM "&Gray",
                         MENUITEM "&Dk Gray",
                         MENUITEM "&Black",
MENUITEM "&Hollow",
                                                      IDM HOLLOW
                   END
            MENUITEM "\a&Help",
                                                                IDM HELP
       END
```

Figure 10-3. Continued

NAME MENUDEMO DESCRIPTION 'Menu Demonstration Program (C) Charles Petzold, 1987' STUB 'WINSTUB. EXE' MOVEABLE CODE DATA MOVEABLE MULTIPLE HEAPSIZE 1024 STACKSIZE 4096 EXPORTS WndProc

Macro identifiers for all menu IDs are defined in MENUDEMO.H. This file must be specified (using a #include statement) in both the resource script file and the C source code file.
The identifiers begin with IDM. (The ID numbers defined for the menu items need not be
consecutive. However, if you process these IDs in your program using switch and case statements, keep in mind that the C compiler can best optimize this code using jump tables if you
use consecutive menu ID numbers.)

The MENUDEMO program simply beeps when it receives a WM_COMMAND message for most items in the File and Edit popups. The Background popup lists six stock brushes that MENUDEMO can use to color the background. In the MENUDEMO.RC resource script the White menu item (with a menu ID of IDM_WHITE) is flagged as CHECKED, which places a check mark next to the item. In MENUDEMO.C, the value of wSelection is initially set to IDM_WHITE.

The six brushes on the Background popup are mutually exclusive. When MENUDEMO.C receives a WM_COMMAND message where wParam is one of these six items on the Background popup, it must remove the check mark from the previously chosen background color and add a check mark to the new background color. To do this, it first gets a handle to its menu:

```
hMenu = GetMenu (hWnd) ;
```

The CheckMenuItem function is used to uncheck the currently checked item:

```
CheckMenuItem (hMenu, wSelection, MF_UNCHECKED) ;
```

The wSelection value is set to the value of wParam, and the new background color is checked:

```
wSelection = wParam ;
CheckMenuItem (hMenu, wSelection, MF_CHECKED) ;
```

The background color in the window class is then replaced with the new background color, and the window client area is invalidated. Windows erases the window using the new background color.

When MENUDEMO receives a WM_COMMAND message with the wParam parameter equal to IDM_ABOUT, it displays a message box. (In Chapter 11 we'll change this to a dialog box.)

When MENUDEMO receives a WM_COMMAND message with wParam equal to IDM_EXIT, it sends itself a WM_CLOSE message. This is the same message that DefWindowProc sends the window function when it receives a WM_SYSCOMMAND message with wParam equal to SC_CLOSE. We'll examine this more in the POPPAD program shown toward the end of this chapter.

Menu Etiquette

The format of the File and Edit popups in MENUDEMO follows the recommendations of the Windows Application Style Guide. Many Windows programs have File and Edit popups. (Of the programs included with Windows, CALENDAR, CARDFILE, NOTEPAD, PAINT, PIFEDIT, TERMINAL, and WRITE all have such menus.) One of the objectives of Windows is to provide a user with a recognizable interface that does not require relearning basic concepts for each program. It certainly helps if the File and Edit menus look the same in every Windows program and use the same letters for selection with the Alt key.

Beyond the File and Edit popups, the menus of most Windows programs will be different. When designing a menu you should look at existing Windows programs and aim for some consistency. Of course, if you think these other programs are wrong and you know the right way to do it, nobody's going to stop you. Also keep in mind that revising a menu usually requires revising only the resource script and not your program code. You can move menu items around at a later time without many problems.

At the beginning of this chapter I showed you a menu with nine top-level items but only one popup. This menu is certainly atypical. Most often, every top-level item has a popup, even if the popup has only one option. Top-level items without popups can be too easily chosen by mistake.

Defining a Menu the Hard Way

Definining a menu in a program's resource script is usually the easiest way to add a menu in your window, but it's not the only way. You can dispense with the resource script and create a menu entirely within your program using two functions called *CreateMenu* and *ChangeMenu*. After you finish defining the menu, you can pass the menu handle to *CreateWindow* or use *SetMenu* to set the window's menu.

Here's how it's done. CreateMenu simply returns a handle to a new menu:

```
hMenu = CreateMenu () ;
```

The menu is initially empty. *ChangeMenu* inserts items into the menu. You must obtain a different menu handle for the top-level menu item and for each popup. The popups are constructed separately; the popup menu handles are then inserted into the top-level menu. The code shown in Figure 10-4 creates a menu in this fashion; in fact, it is the same menu as in the MENUDEMO program.

```
hMenu = CreateMenu () ;
hMenuPopup = CreateMenu () :
ChangeMenu (hMenuPopup, NULL, "&New",
                                                                          IDM NEW,
                                                                                           MF APPEND)
ChangeMenu (hMenuPopup, NULL, "&Open...",
                                                                           IDM OPEN, MF APPEND)
ChangeMenu (hMenuPopup, NULL, "&Save",
ChangeMenu (hMenuPopup, NULL, "Save &As...",
                                                                            IDM SAVE,
                                                                                            MF APPEND)
                                                                            IDM_SAVEAS, MF_APPEND)
ChangeMenu (hMenuPopup, NULL, NULL,
                                                                                             MF_APPEND)
MF_APPEND)
                                                                            O,
IDM EXIT,
ChangeMenu (hMenuPopup, NULL, "Esxit", IDM EXIT, MF APPEND); ChangeMenu (hMenuPopup, NULL, "A&bout MenuDemo...", IDM ABOUT, MF APPEND);
ChangeMenu (hMenu, NULL, "&File", hMenuPopup, MF APPEND | MF POPUP) ;
hMenuPopup = CreateMenu () ;
ChangeMenu (hMenuPopup, NULL, "&Undo",
                                                          IDM_UNDO, MF_APPEND)
0, MF_APPEND)
ChangeMenu (hMenuPopup, NULL, NULL, 0, ChangeMenu (hMenuPopup, NULL, "Cu&t", IDM_CUT, ChangeMenu (hMenuPopup, NULL, "&Copy", IDM_COPY ChangeMenu (hMenuPopup, NULL, "&Paste", IDM_PAST
ChangeMenu (hMenuPopup, NULL, NULL,
                                                                           MF APPEND)
                                                            IDM_COPY,
                                                                           MF_APPEND)
ChangeMenu (hMenuPopup, NULL, "&Paste", IDM PASTE, MF APPEND)
ChangeMenu (hMenuPopup, NULL, "C&lear", IDM CLEAR, MF APPEND)
ChangeMenu (hMenu, NULL, "&Edit", hMenuPopup, MF_APPEND | MF_POPUP) ;
hMenuPopup = CreateMenu () ;
ChangeMenu (hMenuPopup, NULL, "&White", IDM_WHITE, MF_APPEND
ChangeMenu (hMenuPopup, NULL, "&Lt Gray", IDM_LTGRAY, MF_APPEND)
                                                          IDM_WHITE, MF_APPEND | MF_CHECKED) ;
ChangeMenu (hMenuPopup, NULL, "&Dk Gray", IDM DKGRAY, MF APPEND)
ChangeMenu (hMenuPopup, NULL, "&Black", IDM BLACK, MF APPEND)
ChangeMenu (hMenuPopup, NULL, "&Hollow", IDM HOLLOW, MF APPEND)
ChangeMenu (hMenu, NULL, "&Background", hMenuPopup, MF APPEND | MF POPUP) ;
```

Figure 10-4. C code that creates the same menu used in the MENUDEMO program but without requiring a resource script file

I think you'll agree that the resource script menu template is easier and clearer. I'm not recommending that you define a menu in this way, only showing that it can be done. Certainly you can cut down on the code size substantially by using some arrays of structures containing all the menu item character strings, IDs, and flags. But if you do that, you might as well take advantage of the third method Windows provides for defining a menu.

A Third Approach to Defining Menus

The LoadMenuIndirect function accepts a pointer to a structure of type MENUITEMTEMPLATE and returns a handle to a menu. This function is used within Windows to construct a menu after loading the normal menu template from a resource script. If you're brave, you can try using it yourself.

Be forewarned, however: The MENUITEMTEMPLATE structure has a field defined as LPSTR that is set to a far pointer to a character string, a handle to a popup, or a handle to a bit-map. But you can't simply define a MENUITEMTEMPLATE structure in your program and initialize the field to a character string. During compilation, the pointer to the character string

is converted to a far pointer. This violates one of the most important rules discussed in Chapter 8: Don't store far pointers to your data segment. Instead, immediately before calling *LoadMenuIndirect*, you must have a series of assignment statements that set this field to the character string pointers. Between these assignment statements and the *LoadMenuIndirect* call, you can't make any Windows calls that can result in your data segment being moved (such as *GetMessage*).

Using the System Menu

Parent windows created with a style that includes WS_SYSMENU have a system menu box at the left of the caption bar, If you like, you can modify this menu. For instance, you can add your own menu commands to the system menu. The Application Style Guide recommends that programmers add only an About option to the system menu, and then only if the window doesn't include its own menu. However, modifying the system menu is often a quick-and-dirty way to add a menu to a short program without making up a separate resource script and header file. The only restriction is this: The ID numbers you use to add commands to the system menu must be lower than F000H. Otherwise, they will conflict with the IDs that Windows uses for the normal system menu commands. And remember: When you process WM_SYSCOMMAND messages in your window function for these new menu items, you must pass the other WM_SYSCOMMAND messages to DefWindowProc. If you don't, you'll effectively disable all normal options on the system menu.

The program POORMENU ("poor person's menu"), shown in Figure 10-5, adds a separator bar and three commands to the system menu. The last of these commands removes the additions.

```
poormenu.obj : poormenu.c

cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp poormenu.c

poormenu.exe : poormenu.obj poormenu.def

link4 poormenu, /align:16, /map, slibw, poormenu
```

```
/* POORMENU.C -- The Poor Person's Menu */
#include <windows.h>
#define IDM_ABOUT 1
#define IDM_HELP 2
#define IDM_REMOVE 3
long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG);
static char szAppName [] = "PoorMenu";
```

Figure 10-5. The POORMENU program

Figure 10-5. Continued

```
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
      HANDLE hInstance, hPrevInstance;
      LPSTR
                 lpszCmdLine ;
      int
                 nCmdShow ;
      HMENU
                 hMenu ;
      HWND
                 hWnd ;
      MSG
                 msq ;
      WNDCLASS wndclass ;
      if (!hPrevInstance)
            wndclass.style
                                      = CS HREDRAW | CS VREDRAW ;
            wndclass.lpfnWndProc = WndProc ;
            wndclass.cbClsExtra = 0;
wndclass.cbWndExtra = 0;
wndclass.hInstance = hInstance;
wndclass.hIcon = LoadIcon (NULL, IDI APPLICATION);
wndclass.hCursor = LoadCursor (NULL, IDC ARROW);
            wndclass.hbrBackground = GetStockObject (WHITE BRUSH) ;
            wndclass.lpszMenuName = NULL ;
            wndclass.lpszClassName = szAppName ;
            if (!RegisterClass (&wndclass))
                  return FALSE ;
      hWnd = CreateWindow (szAppName, "The Poor-Person\'s Menu",
                               WS OVERLAPPEDWINDOW,
                               CW USEDEFAULT, 0,
                               CW USEDEFAULT, 0,
                               NULL, NULL, hInstance, NULL) ;
      hMenu = GetSystemMenu (hWnd, FALSE);
      ChangeMenu (hMenu, NULL, NULL, 0, MF_APPEND); ChangeMenu (hMenu, NULL, "About...", IDM_ABOUT, MF_APPEND); ChangeMenu (hMenu, NULL, "Help...", IDM_HELP, MF_APPEND); ChangeMenu (hMenu, NULL, "Remove Additions", IDM_REMOVE, MF_APPEND);
      ShowWindow (hWnd, nCmdShow) ;
      UpdateWindow (hWnd) ;
      while (GetMessage (&msg, NULL, 0, 0))
            TranslateMessage (&msq) ;
            DispatchMessage (&msg) ;
      return msg.wParam ;
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
      HWND hWnd;
      unsigned iMessage ;
      WORD wParam ;
      LONG
                lParam ;
      switch (iMessage)
            case WM SYSCOMMAND:
                  switch (wParam)
```

Figure 10-5. Continued

```
case IDM ABOUT:
                    MessageBox (hWnd, "A Poor-Person\'s Menu Program.",
                               szAppName, MB OK | MB ICONEXCLAMATION) ;
                    break ;
               case IDM HELP:
                    MessageBox (hWnd, "Help not yet implemented.",
                               szAppName, MB OK | MB ICONEXCLAMATION) ;
                    break :
               case IDM REMOVE:
                    GetSystemMenu (hWnd, TRUE) ;
                    break :
               default:
                    return DefWindowProc (hWnd, iMessage,
                                              wParam, 1Param) ;
          break ;
     case WM DESTROY:
          PostQuitMessage (0) ;
          break :
     default:
          return DefWindowProc (hWnd, iMessage, wParam, 1Param) ;
return OL ;
```

```
POORMENU
NAME
DESCRIPTION
               'The Poor Person's Menu (C) Charles Petzold, 1987'
               'WINSTUB.EXE'
STUB
CODE
               MOVEABLE
              MOVEABLE MULTIPLE
DATA
HEAPSIZE
              1024
STACKSIZE
               4096
EXPORTS
              WndProc
```

The three menu IDs are defined near the top of POORMENU.C:

```
#define IDM_ABOUT 1
#define IDM_HELP 2
#define IDM_REMOVE 3
```

After the program's window has been created, POORMENU obtains a handle to the system menu:

```
hMenu = GetSystemMenu (hWnd, FALSE) ;
```

When you first call GetSystemMenu, you should set the second parameter to FALSE in preparation for modifying the menu.

The menu is altered with four ChangeMenu calls:

```
ChangeMenu (hMenu, NULL, NULL, 0, MF_APPEND);
ChangeMenu (hMenu, NULL, "About...", IDM_ABOUT, MF_APPEND);
ChangeMenu (hMenu, NULL, "Help...", IDM_HELP, MF_APPEND);
ChangeMenu (hMenu, NULL, "Remove Additions", IDM_REMOVE, MF_APPEND);
```

The first ChangeMenu call adds the separator bar. Choosing the Remove Additions menu item causes POORMENU to remove these additions, which it accomplishes simply by calling *Get-SystemMenu* again with the second parameter set to TRUE:

```
GetSystemMenu (hWnd, TRUE) ;
```

The standard system menu has the options Restore, Move, Size, Minimize, Maximize, and Close. These generate WM_SYSCOMMAND messages with wParam equal to SC_RESTORE, SC_MOVE, SC_SIZE, SC_MINIMUM, SC_MAXIMUM, and SC_CLOSE. Although Windows programs do not normally do so, you can process these messages yourself rather than pass them on to DefWindowProc. You can also disable or remove some of these standard options from the system menu using methods described below. The Windows documentation also includes some standard additions to the system menu. These use the identifiers SC_NEXTWINDOW, SC_PREVWINDOW, SC_VSCROLL, SC_HSCROLL, and SC_ARRANGE. You might find it appropriate to add these commands to the system menu in some applications.

The ChangeMenu Function

We've already used the *ChangeMenu* function to define a menu entirely within a program and to add menu items to the system menu. But *ChangeMenu* is more versatile than that. In fact, *ChangeMenu* is so versatile that from the programmer's perspective it is one of the most complex functions in all of Windows. Here's the general *ChangeMenu* syntax:

```
ChangeMenu (hMenu, wID, lpszNew, wIDNew, wChange);
```

The *hMenu* parameter is a handle to a top-level menu, a popup menu, or the system menu. The interpretation of the middle three parameters depends on the value of *wChange*, which is one or more identifiers that begin with the letters MF ("menu format") combined with the C bitwise OR (|) operator. These identifiers fall into several groups; the identifiers in each group are mutually exclusive. The parameters marked as "default" have a value of 0.

These five identifiers specify the type of change you want to make to the menu:

MF_INSERT (default)—A new menu item is to be inserted in the menu at the
position currently occupied by the wID parameter. The item currently at that
position and all following items are pushed down. The wIDNew parameter is the
new menu ID or a handle to a popup.

- MF_CHANGE—The wID menu item is to be changed. The wIDNew parameter is the new menu ID or a handle to a popup.
- MF_APPEND—A new menu item is to be added to the end of the menu. The wIDNew
 parameter is the new menu ID or a handle to a popup. The wID parameter is ignored.
- MF_REMOVE—Similar to MF_DELETE, but if wID is a handle to a popup menu, MF_DELETE deletes the popup menu, and MF_REMOVE doesn't.
- MF_DELETE—The wID menu item is to be deleted. The wIDNew and lpszNew parameters are ignored.

These identifiers specify how the wID parameter to ChangeMenu is to be interpreted:

- MF_BYCOMMAND (default)—wID is a menu ID.
- MF_BYPOSITION—wID is a positional index number in the menu starting at 0 for the first menu item.

If hMenu is a handle to a top-level menu and you want to change a popup, then you must use MF_BYCOMMAND.

These identifiers specify what the new or changed menu item is:

- MF_STRING (default)—lpszNew points to a text string.
- MF_BITMAP—The low word of *lpszNew* is a handle to a bitmap; the high word is 0.
- MF_SEPARATOR—The new menu item is a separator bar. The *lpszNew* parameter is ignored. (If *lpszNew* is NULL, MF_SEPARATOR is assumed.)

If the MF_POPUP identifier is present, the new menu item will have a popup associated with it, and wIDNew is interpreted as a handle to the popup. Otherwise wIDNew is a menu ID.

These identifiers specify the "enable" state of the new menu item (if a menu item is being added) or of an existing menu item:

- MF_ENABLED—The item is enabled (default).
- MF_DISABLED—Item is disabled.
- MF_GRAYED—Item is grayed.

These identifiers specify the check state of the new or existing menu item:

- MF_UNCHECKED—The item is unchecked (default).
- MF_CHECKED—The item is checked.

These identifiers specify whether the new or existing menu item is to begin in a new row or column:

- MF_MENUBREAK—The item begins in a new row or column.
- MF_MENUBARBREAK—The item in a popup begins in a new column with a vertical line separating the columns.

When you construct a *ChangeMenu* call, start with the *hMenu* and *wChange* parameters. The parameters you use govern the interpretation of the *wID*, *wIDNew*, and *lpszString* parameters. And don't feel bad if you never use any of this information: It's probably much more than you'll ever need. In real life, most menu items remain the same except for graying and checking. While you can gray and check menu items using *ChangeMenu*, other functions do the job faster and easier.

Other Menu Commands

Let's quickly review the menu functions we've already covered: LoadMenu loads a menu resource into memory and returns a handle. CreateMenu returns a handle to a new, empty menu. ChangeMenu lets you construct or change a menu. SetMenu assigns a menu to a window. GetMenu returns the top-level menu handle for a window. GetSystemMenu returns the handle to a window's system menu.

Here are some more commands: When you change a top-level menu item, the change is not shown until Windows redraws the menu bar. You can force this redrawing by calling:

```
DrawMenuBar (hWnd) :
```

Note that the parameter to *DrawMenuBar* is a handle to the window rather than a handle to the menu.

You can obtain the handle of a popup menu using:

```
hMenuPopup = GetSubMenu (hMenu, nPos) ;
```

where *nPos* is the index (starting at 0) of the popup within the top-level menu indicated by *hMenu*. You can then use the popup menu handle with other functions (such as *ChangeMenu*).

You can obtain the current number of items in a top-level or popup menu using:

```
nCount = GetMenuItemCount (hMenu) ;
```

You can obtain the menu ID for an item in a popup menu from:

```
wID = GetMenuItemID (hMenuPopup, nPosition) ;
```

where nPosition is the position (starting at 0) of the item within the popup.

In MENUDEMO you saw how to check or uncheck an item in a popup menu using:

```
CheckMenuItem (hMenu, wID, wCheck) ;
```

In MENUDEMO, hMenu was the handle to the top-level menu, wID was the menu ID, and the value of wCheck was either MF_CHECKED or MF_UNCHECKED. If hMenu is a handle to a popup menu, then the wID parameter can be a positional index rather than a menu ID. If an index is more convenient, you include MF_BYPOSITION in the third parameter. For instance:

```
CheckMenuItem (hMenu, nPosition, MF_CHECKED | MF_BYPOSITION) ;
```

The EnableMenuItem function works similarly to CheckMenuItem except the third parameter is MF_GRAYED, MF_ENABLED, or MF_DISABLED. If you use EnableMenuItem on a top-level menu item that has a popup, you must also use the MF_BYPOSITION identifier in the third parameter because the menu item has no menu ID. We'll see an example of EnableMenuItem in the POPPAD program shown later in this chapter. HiliteMenuItem is similar to CheckMenuItem and EnableMenuItem but uses MF_HILITE and MF_UNHILITE. This highlighting is the reverse video that Windows uses when you move among menu items. You do not normally need to use HiliteMenuItem.

What else do you need to do with your menu? Have you forgotten what character string you used in a menu? You can refresh your memory by calling:

```
nByteCount = GetMenuString (hMenu, wID, lpString, nMaxCount, wFlag) ;
```

The wFlag is either MF_BYCOMMAND (where wID is a menu ID) or MF_BYPOSITION (wID is a positional index). The function copies up to nMaxCount bytes of the text string into lpString and returns the number of bytes copied.

Or perhaps you'd like to know what the current flags of a menu item are:

```
wFlags = GetMenuState (hMenu, wID, wFlag) ;
```

Again, wFlag is either MF_BYCOMMAND or MF_BYPOSITION. The wFlags parameter is a combination of all the current flags. You can determine them by testing against the MF_DISABLED, MF_GRAYED, MF_CHECKED, MF_MENUBREAK, MF_MENUBARBREAK, and MF_SEPARATOR identifiers.

Or maybe by this time you're a little fed up with menus. In that case you'll be pleased to know that if you no longer need a menu in your program, you can destroy it:

```
DestroyMenu (hMenu) ;
```

This invalidates the menu handle.

An Unorthodox Approach to Menus

Now let's step a little off the beaten path. Instead of having drop-down menus in your program, how about creating multiple top-level menus without any popups and switching between the top-level menus using the <code>SetMenu</code> call? The NOPOPUPS program, shown in Figure 10-6, demonstrates how to do it. This program includes the same File and Edit popups that MENUDEMO uses but displays them as top-level menus invoked by the File and Edit options on the main menu.

```
nopopups.obj : nopopups.c nopopups.h
    cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp nopopups.c

nopopups.res : nopopups.rc nopopups.h
    rc -r nopopups.rc

nopopups.exe : nopopups.obj nopopups.def nopopups.res
    link4 nopopups, /align:16, /map, slibw, nopopups
    rc nopopups.res
```

```
/* NOPOPUPS.C -- Demonstrates No-Popup Nested Menu */
#include <windows.h>
#include "nopopups.h"
long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG) ;
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
              hInstance, hPrevInstance;
     HANDLE
     LPSTR
                   lpszCmdLine ;
                  nCmdShow ;
     static char szAppName [] = "NoPopUps" ;
     HWND hWnd;
     MSG
                  msq ;
     WNDCLASS wndclass;
     if (!hPrevInstance)
           wndclass.style
                                   = CS HREDRAW | CS VREDRAW ;
           wndclass.lpfnWndProc = WndProc ;
          wndclass.cbClsExtra = 0;
wndclass.cbClsExtra = 0;
wndclass.cbMndExtra = 0;
wndclass.hInstance = hInstance;
wndclass.hIcon = LoadIcon (NULL, IDI_APPLICATION);
wndclass.hCursor = LoadCursor (NULL, IDC_ARROW);
           wndclass.hbrBackground = GetStockObject (WHITE BRUSH) ;
           wndclass.lpszMenuName = NULL ;
           wndclass.lpszClassName = szAppName ;
           if (!RegisterClass (&wndclass))
                return FALSE ;
     hWnd = CreateWindow (szAppName, "No-Popup Nested Menu Demonstration",
                            WS OVERLAPPEDWINDOW,
                            CW USEDEFAULT, 0,
                            CW USEDEFAULT, O.
                            NULL, NULL, hinstance, NULL) ;
     ShowWindow (hWnd, nCmdShow) ;
     UpdateWindow (hWnd) ;
     while (GetMessage (&msg, NULL, 0, 0))
          TranslateMessage (&msg) ;
           DispatchMessage (&msg) ;
     return msg.wParam ;
```

Figure 10-6. The NOPOPUPS program

Figure 10-6. Continued

```
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
                   hWnd ;
     HWND
                   iMessage ;
     unsigned
                    wParam ;
     WORD
     LONG
                     1Param ;
      static HMENU hMenuMain, hMenuEdit, hMenuFile;
                  hInstance ;
     HANDLE
     switch (iMessage)
           case WM CREATE:
                 hInstance = GetWindowWord (hWnd, GWW_HINSTANCE) ;
                 hMenuMain = LoadMenu (hInstance, "MenuMain") ;
hMenuFile = LoadMenu (hInstance, "MenuFile") ;
hMenuEdit = LoadMenu (hInstance, "MenuEdit") ;
                 SetMenu (hWnd, hMenuMain) ;
                 break :
           case WM COMMAND:
                 switch (wParam)
                       case IDM MAIN:
                             SetMenu (hWnd, hMenuMain) ;
                             break :
                       case IDM FILE:
                             SetMenu (hWnd, hMenuFile) ;
                             break :
                       case IDM EDIT:
                             SetMenu (hWnd, hMenuEdit) ;
                             break ;
                       case IDM NEW:
                       case IDM OPEN:
case IDM SAVE:
                       case IDM SAVEAS:
                       case IDM UNDO:
                       case IDM CUT:
case IDM COPY:
                       case IDM PASTE:
                       case IDM CLEAR:
                             MessageBeep (0) ;
                             break ;
                 break ;
            case WM_DESTROY:
                 PostQuitMessage (0) ;
                  break ;
            default:
                  return DefWindowProc (hWnd, iMessage, wParam, 1Param) ;
      return OL ;
```

Figure 10-6. Continued

```
#define IDM NEW 1
#define IDM OPEN 2
#define IDM_SAVE 3
#define IDM_SAVEAS 4

#define IDM_UNDO 5
#define IDM_CUT 6
#define IDM_COPY 7
#define IDM_PASTE 8
#define IDM_CLEAR 9

#define IDM_MAIN 10
#define IDM_MAIN 10
#define IDM_FILE 12
```

```
#include "nopopups.h"
MenuMain MENU
           BEGIN
                       MENUITEM "MAIN:", 0,
MENUITEM "&File...", IDM FILE
MENUITEM "&Edit...", IDM_EDIT
           END
MenuFile MENU
          BEGIN
                      MENUITEM "FILE:", 0, 1DM NEW MENUITEM "&New", 1DM NEW MENUITEM "&Open...", 1DM OPEN MENUITEM "&Save", 1DM SAVE MENUITEM "Save &As...", 1DM SAVEAS MENUITEM "(AMAIN.")
                                                                                                        INACTIVE
                       MENUITEM "(&Main)", IDM_MAIN
           END
MenuEdit MENU
           BEGIN
                      MENUITEM "EDIT:", 0,
MENUITEM "$Undo", IDM_UNDO
MENUITEM "Cu&t", IDM_CUT
MENUITEM "&COPY", IDM_COPY
MENUITEM "$Paste", IDM_PASTE
MENUITEM "C$lear", IDM_CLEAR
MENUITEM "(6Main)", IDM_MAIN
                                                                                             INACTIVE
           END
```

```
NAME NOPOPUPS
DESCRIPTION 'Demonstration of No-Popup Menu (C) Charles Petzold, 1987'
STUB 'WINSTUB.EXE'
CODE MOVEABLE
DATA MOVEABLE MULTIPLE
HEAPSIZE 1024
STACKSIZE 4096
EXPORTS WndProc
```

The resource script has three menus rather than one. When the window function processes the WM_CREATE message, Windows loads each of the menu resources into memory:

```
hMenuMain = LoadMenu (hInstance, "MenuMain");
hMenuFile = LoadMenu (hInstance, "MenuFile");
hMenuEdit = LoadMenu (hInstance, "MenuEdit");
```

Initially, the program displays the main menu:

```
SetMenu (hWnd, hMenuMain) ;
```

The main menu lists the three options using the character strings "MAIN:", "File...", and "Edit..." However, "MAIN:" is disabled, so it doesn't cause WM_COMMAND messages to be sent to the window function. The File and Edit menus begin "FILE:" and "EDIT:" to identify these as submenus. The last item in each menu is the character string "(Main)"; this option indicates a return to the main menu. Switching between these three menus is simple:

USING BITMAPS IN MENUS

In exploring the *ChangeMenu* function, we encountered the identifier MF_BITMAP, which seems to indicate that we can use a bitmap rather than a string in a menu. If you got a little excited at this possibility, that's good, because we're about to explore it in depth. On the other hand, if you immediately recoiled at the thought of pictures of file folders, paste jars, and trash cans in a menu, don't think of pictures. Think instead of how useful menu bitmaps might be for a drawing program. Think of using different fonts and font sizes, line widths, hatch patterns, and colors in your menus.

The program we're going to examine is called GRAFMENU ("graphic menu"). The top-level menu is shown in Figure 10-7. The enlarged block letters are derived from bitmap files created in ICONEDIT and saved as .BMP files; they could be pictures instead.




Figure 10-7. The GRAFMENU program's top-level menu

Choosing FONT from the menu invokes a popop with three options—Courier, Helvetica, and Times Roman—each displayed in its respective font (Figure 10-8). These bitmaps were created in the program using a technique involving a "memory device context."




Figure 10-8. The GRAFMENU program's popup FONT menu

Finally, when you pull down the system menu, you see that you have access to some "help" information, with the word "Help" perhaps mirroring the desperation of a new user (Figure 10-9). This bitmap was created in ICONEDIT.




Figure 10-9. The GRAFMENU program's system menu

The GRAFMENU program, including the four bitmaps created in ICONEDIT, is shown in Figure 10-10.

```
/* GRAFMENU.C -- Demonstrates Bitmap Menu Items */
#include <windows.h>
#include <string.h>
#include "grafmenu.h"
```

Figure 10-10. The GRAFMENU program

```
long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG);
HBITMAP StretchBitmap (HBITMAP) ;
HBITMAP GetBitmapFont (int) ;
char szAppName [] = "GrafMenu" ;
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
     HANDLE hinstance, hPrevinstance;
     LPSTR
              lpszCmdLine ;
     int
              nCmdShow ;
     HBITMAP hBitmapHelp, hBitmapFile, hBitmapEdit, hBitmapFont, hBitmapPopFont [3];
     HMENU
              hMenu, hMenuPopup;
     HWND
              hWnd ;
              1 :
     int
     MSG
              msq
     WNDCLASS wndclass ;
     if (!hPrevInstance)
          wndclass.style
                                  = CS HREDRAW | CS VREDRAW ;
          wndclass.lpfnWndProc = WndProc ;
          wndclass.cbClsExtra
                                  = 0 ;
          wndclass.cbWndExtra = 0;
wndclass.hInstance = hInstance;
          wndclass.hIcon = LoadIcon (NULL, IDI_APPLICATION) ;
wndclass.hCursor = LoadCursor (NULL, IDC_ARROW) ;
          wndclass.hbrBackground = GetStockObject (WHITE_BRUSH) ;
          wndclass.lpszMenuName = NULL ;
          wndclass.lpszClassName = szAppName ;
          if (!RegisterClass (&wndclass))
               return FALSE ;
     hMenu = CreateMenu () ;
     hMenuPopup = LoadMenu (hInstance, "MenuFile") ;
     hBitmapFile = StretchBitmap (LoadBitmap (hInstance, "BitmapFile")) ;
     ChangeMenu (hMenu, NULL, (PSTR) hBitmapFile, hMenuPopup,
                                          MF APPEND | MF BITMAP | MF POPUP) ;
     hMenuPopup = LoadMenu (hInstance, "MenuEdit") ;
     hBitmapEdit = StretchBitmap (LoadBitmap (hInstance, "BitmapEdit")) ;
     ChangeMenu (hMenu, NULL, (PSTR) hBitmapEdit, hMenuPopup,
                                          MF APPEND | MF BITMAP | MF POPUP) ;
     hMenuPopup = CreateMenu () ;
     for (i = 0 ; i < 3 ; i++)
          hBitmapPopFont [i] = GetBitmapFont (i) ;
          ChangeMenu (hMenuPopup, NULL, (PSTR) hBitmapPopFont [i],
                                          IDM COUR + i, MF APPEND | MF BITMAP) ;
     hBitmapFont = StretchBitmap (LoadBitmap (hInstance, "BitmapFont")) ;
     ChangeMenu (hMenu, NULL, (PSTR) hBitmapFont, hMenuPopup,
                                          MF APPEND | MF BITMAP | MF POPUP) ;
```

```
hWnd = CreateWindow (szAppName, "Bitmap Menu Demonstration",
                            WS OVERLAPPEDWINDOW,
                            CW_USEDEFAULT, 0,
                            CW USEDEFAULT, 0,
NULL, hMenu, hInstance, NULL) ;
     hMenu = GetSystemMenu (hWnd, FALSE);
hBitmapHelp = StretchBitmap (LoadBitmap (hInstance, "BitmapHelp"));
     ChangeMenu (hMenu, NULL, NULL, 0, MF_APPEND | MF_SEPARATOR);
     ChangeMenu (hMenu, NULL, (PSTR) hBitmapHelp, IDM HELP, MF_APPEND | MF_BITMAP) ;
     ShowWindow (hWnd, nCmdShow) ;
     UpdateWindow (hWnd) ;
     while (GetMessage (&msg, NULL, 0, 0))
           TranslateMessage (&msg) ;
           DispatchMessage (&msg) ;
     DeleteObject (hBitmapHelp) ;
     DeleteObject (hBitmapEdit) ;
     DeleteObject (hBitmapFile) ;
DeleteObject (hBitmapFont) ;
     for (i = 0 ; i < 3 ; i++)
           DeleteObject (hBitmapPopFont [i]) ;
     return msg.wParam ;
HBITMAP StretchBitmap (hBitmap1)
     HBITMAP
                hBitmapl ;
     BITMAP
                 bml, bm2 ;
               hBitmap2 ;
     HBITMAP
                  hDC, hMemDC1, hMemDC2;
     TEXTMETRIC tm ;
     hDC = CreateIC ("DISPLAY", NULL, NULL, NULL) ;
     GetTextMetrics (hDC, &tm) ;
     hMemDC1 = CreateCompatibleDC (hDC) ;
     hMemDC2 = CreateCompatibleDC (hDC) ;
     DeleteDC (hDC) ;
     GetObject (hBitmap1, sizeof (BITMAP), (LPSTR) &bml) ;
     bm2 = bm1:
                      = (tm.tmAveCharWidth * bm2.bmWidth) / 4 ;
= (tm.tmHeight * bm2.bmHeight) / 8 ;
     bm2.bmWidth
     bm2.bmHeight
     bm2.bmWidthBytes = ((bm2.bmWidth + 15) / 16) * 2;
     hBitmap2 = CreateBitmapIndirect (&bm2) ;
     SelectObject (hMemDC1, hBitmap1);
SelectObject (hMemDC2, hBitmap2);
```

```
StretchBlt (hMemDC2, 0, 0, bm2.bmWidth, bm2.bmHeight, hMemDC1, 0, 0, bm1.bmWidth, bm1.bmHeight, SRCCOPY);
     DeleteDC (hMemDC1) ;
     DeleteDC (hMemDC2) ;
     DeleteObject (hBitmap1) ;
     return hBitmap2 ;
HBITMAP GetBitmapFont (i)
     int
     static struct
           BYTE lfPitchAndFamily ;
           BYTE lfFaceName [LF_FACESIZE] ;
           char *szMenuText ;
           1fSet [3] =
           FIXED PITCH | FF MODERN, "Courier", "Courier", VARIABLE PITCH | FF SWISS, "Helvetica", "Helvetica", VARIABLE_PITCH | FF_ROMAN, "Tms Rmn", "Times Roman"
                                                          "Times Roman"
     DWORD
              dwSize ;
     HBITMAP hBitmap ;
     HDC hDC, hMemDC;
HFONT hFont;
     LOGFONT 1f ;
     hFont = GetStockObject (SYSTEM FONT) ;
     GetObject (hFont, sizeof (LOGFONT), (LPSTR) &lf) ;
     lf.lfHeight *= 2 ;
     lf.lfWidth *= 2 ;
     lf.lfPitchAndFamily = lfSet[i].lfPitchAndFamily ;
     strcpy (lf.lfFaceName, lfSet[i].lfFaceName) ;
     hDC = CreateIC ("DISPLAY", NULL, NULL, NULL) ;
     hMemDC = CreateCompatibleDC (hDC) ;
     SelectObject (hMemDC, CreateFontIndirect (&lf)) ;
     dwSize = GetTextExtent (hMemDC, lfSet[i].szMenuText,
                                  strlen (lfSet[i].szMenuText)) ;
     hBitmap = CreateBitmap (LOWORD (dwSize), HIWORD (dwSize), 1, 1, NULL) ;
     SelectObject (hMemDC, hBitmap) ;
     TextOut (hMemDC, 0, 0, lfSet[i].szMenuText,
                                  strlen (lfSet[i].szMenuText)) ;
     DeleteObject (SelectObject (hMemDC, hFont)) ;
     DeleteDC (hMemDC) ;
     DeleteDC (hDC) ;
     return hBitmap ;
```

```
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
     HWND hWnd;
     unsigned iMessage :
     WORD
           wParam ;
     LONG
              1Param ;
     HMENU
             hMenu ;
     static
             short nCurrentFont = IDM COUR ;
     switch (iMessage)
          case WM CREATE:
               CheckMenuItem (GetMenu (hWnd), nCurrentFont, MF_CHECKED) ;
               break ;
          case WM SYSCOMMAND:
               switch (wParam)
                     case IDM HELP:
                          MessageBeep (0);
                          MessageBox (hWnd, "Help not yet implemented.", szAppName, MB_OK | MB_ICONEXCLAMATION) ;
                     default:
                          return DefWindowProc (hWnd, iMessage,
                                                          wParam, 1Param) ;
               break :
          case WM COMMAND:
               switch (wParam)
                     case IDM NEW:
                    case IDM OPEN:
                     case IDM SAVE:
                     case IDM SAVEAS:
                    case IDM UNDO:
                    case IDM_CUT:
                     case IDM COPY:
                     case IDM PASTE:
                     case IDM CLEAR:
                          MessageBeep (0) ;
                          break ;
                     case IDM_COUR:
                     case IDM HELV:
                     case IDM_TMSRMN:
                          hMenu = GetMenu (hWnd) ;
                          CheckMenuItem (hMenu, nCurrentFont, MF_UNCHECKED) ;
                          nCurrentFont = wParam ;
                          CheckMenuItem (hMenu, nCurrentFont, MF CHECKED) ;
                          break :
               break ;
```

```
#define IDM_NEW 1
#define IDM_OPEN 2
#define IDM_SAVE 3
#define IDM_SAVEAS 4

#define IDM_UNDO 5
#define IDM_COPT 6
#define IDM_COPT 7
#define IDM_PASTE 8
#define IDM_CLEAR 9


#define IDM_CLEAR 9


#define IDM_CLEAR 10
#define IDM_HELV 11
#define IDM_TMSRMN 12

#define IDM_HELP 13
```

```
#include "grafmenu.h"
BitmapEdit BITMAP editlabl.bmp
BitmapFile BITMAP filelabl.bmp
BitmapFont BITMAP fontlabl.bmp
BitmapHelp BITMAP bighelp.bmp
MenuFile MENU
       BEGIN
              MENUITEM "$New", IDM NEW MENUITEM "$Open...", IDM OPEN MENUITEM "$Save", IDM_SAVE
              MENUITEM "Save &As...", IDM_SAVEAS
       END
MenuEdit MENU
       BEGIN
              MENUITEM "&Undo",
                                               IDM UNDO
              MENUITEM "SUPARATOR
MENUITEM "CU&t", IDM_CUT
MENUITEM "&Copy", IDM_COPY
MENUITEM "&Paste", IDM_PASTE
MENUITEM "C&lear", IDM_CLEAR
       END
```

Figure 10-10. Continued









Figure 10-10. Continued



GRAFMENU NAME DESCRIPTION 'Demo of Bitmapped Menu Items (C) Charles Petzold, 1987' 'WINSTUB.EXE' STUB CODE MOVEABLE DATA MOVEABLE MULTIPLE HEAPSIZE 1024 STACKSIZE 4096 EXPORTS WndProc

To examine the subject of bitmaps and menus in the detail it deserves, we'll need to cross the border into GDI territory—a full exploration of which awaits us in the next section of this book. The discussion here will serve as a preview of topics that we'll come to again in Chapter 12.

Two Methods of Creating Bitmaps for Menus

You can't actually draw on the menu from within your Windows program. If you want something other than system font text, you must use *ChangeMenu* to insert a bitmap into the menu. Where does this bitmap come from? It can come from one of two places. First, you can create a bitmap using ICONEDIT and include the bitmap file in your resource script. Within the program, you can use *LoadBitmap* to load the bitmap resource into memory and use *ChangeMenu* to attach it to the menu. There's a problem with this approach, however. The bitmap will not be suitable for all types of video resolutions and aspect ratios; you have to stretch the loaded bitmap to account for this. Alternatively, you can create the bitmap right in the program and attach it to the menu.

Both of these methods sound a lot more difficult than they actually are. We don't have to mess around with the actual bits themselves. Windows provides functions that let us manipulate bitmaps cleanly using something called the "memory device context."

The Memory Device Context

When you use GDI calls (such as *TextOut*) to write on the client area of your window, you're actually writing to a block of memory (the video display memory) that is organized much like a giant bitmap. The width and height of this bitmap are equal to the resolution of the video adapter. The number of color planes and the color bits per pixel are also defined by the video adapter. Windows should also be able to pretend that a block of regular memory is video display memory. It should be able to write on this memory the same way it writes on the screen. We should then be able to use this block of memory as a bitmap.

That's exactly what a memory device context is. It helps us fill up and manipulate bitmaps in a Windows program. Here are the steps involved:

- Create a memory device context using the CreateCompatibleDC call. Initially, the display surface of this memory device context contains one monochrome pixel. You can think of this device context as being one pixel high and one pixel wide, with two colors (black and white).
- Create an uninitialized bitmap using CreateBitmap, CreateBitmapIndirect, or CreateCompatibleBitmap. When you create the bitmap, you specify the height, width, number of color planes, and number of color bits per pixel. However, the pixels of the bitmap need not actually represent anything yet. Save the handle to the bitmap.
- Select the bitmap into the memory device context using SelectObject. Now the memory device context has a display surface that is the size of the bitmap with the same number of colors as defined by the bitmap.
- 4. Use GDI functions to draw on the memory device context the same way you use GDI functions to draw on a normal device context. Anything you draw within the display surface of the memory device context is actually drawn on the bitmap selected into the device context.
- Delete the memory device context. You are left with a handle to a bitmap that contains a pixel representation of what you drew on the memory device context.

Creating a Bitmap with Text

The GetBitmapFont function in GRAFMENU takes a parameter of 0, 1, or 2 and returns a handle to a bitmap. This bitmap contains the string "Courier," "Helvetica," or "Times Roman" in the appropriate font and about twice the size of the normal system font. Let's see how it does it. (The code that follows is not the same as that in the GRAFMENU.C file. For purposes of clarity, I've replaced references to the IfSet structure with the values appropriate for Times Roman.)

The first step is to get a handle to the system font and use *GetObject* to copy characteristics of that font into the structure *lf* that has type LOGFONT ("logical font"):

```
hFont = GetStockObject (SYSTEM_FONT) ;
GetObject (hFont, sizeof (LOGFONT), (LPSTR) &lf) ;
```

Certain fields of this logical font structure must be modified to make it describe a larger Times Roman font:

```
lf.lfHeight *= 2 ;
lf.lfWidth *= 2 ;
lf.lfPitchAndFamily = VARIABLE_PITCH | FF_ROMAN ;
strcpy (lf.lfFaceName, "Tms Rmn") ;
```

The next step is to get a device context for the screen and create a memory device context compatible with the screen:

```
hDC = CreateIC ("DISPLAY", NULL, NULL, NULL) ;
hMemDC = CreateCompatibleDC (hDC) ;
```

The handle to the memory device context is hMemDC. Next, we create a font based on the modified lf structure and select that font into the memory device context:

```
SelectObject (hMemDC, CreateFontIndirect (&lf));
```

Now when we write some text to the memory device context, Windows will use the Times Roman font selected into the device context.

But this memory device context still has a one-pixel monochrome device surface. We have to create a bitmap large enough for the text we want to display on it. You can obtain the dimensions of the text through <code>GetTextExtent</code> and create a bitmap based on these dimensions with <code>CreateBitmap</code>:

```
dwSize = GetTextExtent (hMemDC, "Times Roman", 11);
hBitmap = CreateBitmap (LOWORD (dwSize), HIWORD (dwSize), 1, 1, NULL);
SelectObject (hMemDC, hBitmap);
```

This device context now has a monochrome display surface exactly the size of the text. Now all we have to do is write the text to it. You've seen this function before:

```
TextOut (hMemDC, 0, 0, "Times Roman", 11) ;
```

We're finished except for cleaning up. To do so, we select the system font (with handle hFont) back into the device context using SelectObject, and we delete the previous font handle that SelectObject returns, which is the handle to the Times Roman font:

```
DeleteObject (SelectObject (hMemDC, hFont));
```

Now we can also delete the two device contexts:

```
DeleteDC (hMemDC) ;
DeleteDC (hDC) ;
```

We're left with a bitmap that has the text "Times Roman" in a Times Roman font.

Scaling Bitmaps

The memory device context also comes to the rescue when we need to scale fonts to a different display resolution or aspect ratio. I created the four bitmaps used in GRAFMENU to be the correct size for a display that has a system font height of 8 pixels and width of 4 pixels. For other system font dimensions, the bitmap has to be stretched. This is done in GRAFMENU's *StretchBitmap* function.

The first step is to get the device context for the screen, obtain the text metrics for the system font, and create two memory device contexts:

```
hDC = CreateIC ("DISPLAY", NULL, NULL, NULL);
GetTextMetrics (hDC, &tm);
hMemDC1 = CreateCompatibleDC (hDC);
hMemDC2 = CreateCompatibleDC (hDC);
DeleteDC (hDC);
```

The bitmap handle passed to the function is hBitmap1. The program can obtain the dimensions of this bitmap using GetObject:

```
GetObject (hBitmap1, sizeof (BITMAP), (LPSTR) &bm1);
```

This copies the dimensions into a structure *bm1* of type BITMAP. The structure *bm2* is set equal to *bm1*, and then certain fields are modified based on the system font dimensions:

```
bm2 = bm1;
bm2.bmWidth = (tm.tmAveCharWidth * bm2.bmWidth) / 4;
bm2.bmHeight = (tm.tmHeight * bm2.bmHeight) / 8;
bm2.bmWidthBytes = ((bm2.bmWidth + 15) / 16) * 2;
```

Then a new bitmap with handle hBitmap2 can be created based on the altered dimensions:

```
hBitmap2 = CreateBitmapIndirect (&bm2) ;
```

You can then select these two bitmaps into the two memory display contexts:

```
SelectObject (hMemDC1, hBitmap1);
SelectObject (hMemDC2, hBitmap2);
```

We want to copy the first bitmap to the second bitmap and stretch it in the process. This involves the StretchBlt call:

```
StretchBlt (hMemDC2, 0, 0, bm2.bmWidth, bm2.bmHeight, hMemDC1, 0, 0, bm1.bmWidth, bm1.bmHeight, SRCCOPY);
```

Now the second bitmap has the properly scaled bitmap. We'll use that one in the menu. Cleanup is simple:

```
DeleteDC (hMemDC1);
DeleteDC (hMemDC2);
DeleteObject (hBitmap1);
```

Putting the Menu Together

GRAFMENU's WinMain function uses the StretchBitmap and GetBitmapFont functions when constructing the menu. GRAFMENU has two menus already defined in the resource script. These will become popups for the File and Edit options.

GRAFMENU begins by obtaining a handle to an empty menu:

```
hMenu = CreateMenu ();
```

The popup menu for File (containing the four options New, Open, Save, and Save As) is loaded from the resource script:

```
hMenuPopup = LoadMenu (hInstance, "MenuFile") ;
```

The bitmap containing the word "FILE" is also loaded from the resource script and stretched using StretchBitmap:

```
hBitmapFile = StretchBitmap (LoadBitmap (hInstance, "BitmapFile")) ;
```

The bitmap handle and popup menu handle become parameters in the ChangeMenu call:

```
ChangeMenu (hMenu, NULL, (PSTR) hBitmapFile, hMenuPopup,
MF_APPEND | MF_BITMAP | MF_POPUP);
```

The same procedure is followed for the Edit menu:

```
hMenuPopup = LoadMenu (hInstance, "MenuEdit");
hBitmapEdit = StretchBitmap (LoadBitmap (hInstance, "BitmapEdit"));
ChangeMenu (hMenu, NULL, (PSTR) hBitmapEdit, hMenuPopup,

MF_APPEND | MF_BITMAP | MF_POPUP);
```

The popup menu for the three fonts is constructed from calls to the GetBitmapFont function:

The popup is then added to the menu:

```
hBitmapFont = StretchBitmap (LoadBitmap (hInstance, "BitmapFont"));
ChangeMenu (hMenu, NULL, (PSTR) hBitmapFont, hMenuPopup,
MF_APPEND | MF_BITMAP | MF_POPUP);
```

The window menu is complete. Now you can include hMenu in the CreateWindow call:

```
hWnd = CreateWindow (szAppName, "Bitmap Menu Demonstration",
WS_OVERLAPPED,
CW_USEDEFAULT, 0, CW_USEDEFAULT, 0,
NULL, hMenu, hInstance, NULL);
```

After hWnd is available, GRAFMENU can alter the system menu. GRAFMENU first obtains a handle to it:

```
hMenu = GetSystemMenu (hWnd, FALSE);
```

This loads the "Help" bitmap and stretches it to an appropriate size:

```
hBitmapHelp = StretchBitmap (LoadBitmap (hInstance, "BitmapHelp")) ;
```

This adds a separator bar and the stretched bitmap to the system menu:

```
ChangeMenu (hMenu, NULL, NULL, 0, MF_APPEND | MF_SEPARATOR);
ChangeMenu (hMenu, NULL, (PSTR) hBitmapHelp, IDM_HELP,
MF_APPEND | MF_BITMAP);
```

Remember that bitmaps are GDI objects and must be explicitly deleted before your program terminates. You accomplish this after GRAFMENU exits from its message loop:

```
DeleteObject (hBitmapHelp) ;
DeleteObject (hBitmapFile) ;
DeleteObject (hBitmapFont) ;

for (i = 0 ; i < 3 ; i++)
    DeleteObject (hBitmapPopFont [i]) ;</pre>
```

I'll conclude this section with a couple of miscellaneous notes:

 In a top-level menu, Windows adjusts the height of the menu bar to accommodate the tallest bitmap. Other bitmaps (or character strings) are aligned at the top of the menu bar. The size of the menu bar obtained from:

GetSystemMetrics (SM_CYMENU)

is no longer valid after you put bitmaps in a top-level window.

 As you can see from playing with GRAFMENU, you can use check marks with bitmapped menu items in popups, but the check mark is of normal size. If that bothers you, you can create two versions of your bitmap—one with and one without the check mark—and swap them using ChangeMenu.

Adding a Keyboard Interface

Now we have another problem. When the menu contains text, Windows automatically adds a keyboard interface. You can select a menu item using the Alt key in combination with a letter of the character string. But once you put a bitmap in a menu, you've eliminated that keyboard interface. Even if the bitmap says something, Windows doesn't know about it.

This is where the WM_MENUCHAR message comes in handy. Windows sends a WM_MENUCHAR message to your window function when you press Alt with a character key that does not correspond with a menu item. We need to intercept WM_MENUCHAR messages and check the value of wParam (the ASCII character of the pressed key). If this corresponds to a menu item, we have to return a long integer back to Windows where the high word is set to 2 and the low word is set to the index of the menu item we want associated with that key. Windows does the rest.

KEYBOARD ACCELERATORS

Described as simply as possible, keyboard accelerators are key combinations that generate WM_COMMAND (or in some cases WM_SYSCOMMAND) messages. Most often, programs use keyboard accelerators to duplicate the action of common menu options. (However, keyboard accelerators can also perform nonmenu functions.) For instance, many Windows programs have an Edit menu that includes a Cut option; these programs conventionally assign the Del key as a keyboard accelerator for this option. The user can choose the Cut option from the menu by pressing an Alt-key combination or can use the keyboard accelerator by simply pressing the Del key. When the window function gets a WM_COMMAND message, it does not have to determine whether the menu or the keyboard accelerator was used.

Why You Should Use Keyboard Accelerators

You may ask: Why should I use keyboard accelerators? Why can't I simply trap WM_KEYDOWN or WM_CHAR messages and duplicate the menu functions myself? What's the advantage? For a single-window application, you can certainly trap keyboard messages, but you get certain advantages from using keyboard accelerators: You don't need to duplicate the menu and keyboard accelerator logic. If the keyboard accelerator duplicates a menu function, Windows flashes the top-level item on the menu when a keyboard accelerator is used, thus providing some visual feedback to the user.

For applications with multiple windows and multiple window functions, keyboard accelerators become very important. As we've seen, Windows sends keyboard messages to the window function for the window that currently has the input focus. For keyboard accelerators, however, Windows sends the WM_COMMAND message to the window function whose handle is specified in the Windows function *TranslateAccelerator*. Generally, this will be your main window, the same window that has the menu, which means that the logic for acting upon keyboard accelerators does not have to be duplicated in every window function.

This advantage becomes particularly important if you use modeless dialog boxes (discussed in Chapter 11) or child windows on your main window's client area. If a particular keyboard accelerator is defined to move between different windows, then only one window function has to include this logic. The child windows do not receive WM_COMMAND messages from the keyboard accelerators.

Some Rules on Assigning Accelerators

In theory, you can define a keyboard accelerator for any virtual key or any character key in combination with the Shift key, the Ctrl key, or both. However, the Windows Application Style Guide offers several recommendations that are intended to achieve some consistency among applications and to avoid interfering with Windows' use of the keyboard. For programs that have an Edit menu, the Application Style Guide highly recommends use of the following accelerators:

Key	Function	
Alt+Backspace	Undo	
Del	Cut	
Ctrl+Ins	Copy	
Shift+Ins	Paste	
Shift+Del	Clear	

You should avoid using Tab, Enter, Esc, and the Spacebar in keyboard accelerators, because these are often used for system functions.

Although some older Windows programs use alphabetic keys in combination with the Ctrl key for keyboard accelerators, more recent Windows programs use function keys, sometimes in combination with the Shift key, the Ctrl key, or both. The Application Style Guide recommends the use of these function keys for specific purposes:

Key	Function		
F1	Help		
F3	Save		
F6	Next window		
Shift+F6	Previous window		
Ctrl+F6	Next section		
Shift+Ctrl+F6	Previous section		

The Accelerator Table

Keyboard accelerator tables are defined in your .RC resource script. The general form is shown here:

```
MyAccelerators ACCELERATORS
BEGIN

[accelerator definitions]
END
```

This accelerator table name is MyAccelerators. The ACCELERATORS table does not include load and memory options. You can have multiple ACCELERATORS tables in your resource script.

Each keyboard accelerator you define requires a different line in the table. There are four types of accelerator definitions:

```
"char", wID [,NOINVERT] [,SHIFT] [,CONTROL]

"^char", wID [,NOINVERT] [,SHIFT] [,CONTROL]

nCode, wID, ASCII [,NOINVERT] [,SHIFT] [,CONTROL]

nCode, wID, VIRTKEY [,NOINVERT] [,SHIFT] [,CONTROL]
```

In these examples, "char" means a single character enclosed in double quotation marks, and "^char" is the character ^ and a single character in double quotation marks. The wID number performs a function similar to the menu ID in a menu definition. It is the value that Windows sends to your window function in the WM_COMMAND message to identify the accelerator. These are usually identifiers defined in a header file. When the keyboard accelerator duplicates a menu command, use the same ID for both the menu and the accelerator. When the keyboard accelerator does not duplicate a menu command, use a unique ID.

Keyboard accelerators almost always select options in popup menus. Windows automatically flashes a top-level menu item when you press an accelerator key that duplicates an option in a popup. (For example, the Edit text flashes if you press the Del key.) If you don't want the menu to flash, include the option NOINVERT.

In the first type of accelerator definition, the keyboard accelerator is a case-sensitive match of the character in double quotes:

```
"char", wID [, NOINVERT] [, SHIFT] [, CONTROL]
```

If you want to define a keyboard accelerator for that key in combination with the Shift or Ctrl key or both, simply add SHIFT or CONTROL or both.

In the second type of definition, the keyboard accelerator is the character in combination with the Ctrl key:

```
"^char", wID [,NOINVERT] [,SHIFT] [,CONTROL]
```

This type is the same as the first type when the CONTROL keyword is used with the character alone.

The third and fourth types use a number (nCode) rather than a character in quotes:

```
nCode, wID, ASCII [,NOINVERT] [,SHIFT] [,CONTROL]
nCode, wID, VIRTKEY [,NOINVERT] [,SHIFT] [,CONTROL]
```

This number is interpreted as either case-sensitive ASCII code or a virtual key code, depending on the ASCII or VIRTKEY keyword.

The most common keyboard accelerators are the second and fourth types. You use the second type for character keys in combination with Ctrl. For example, this defines an accelerator for Ctrl-A:

```
"A", WID
```

Use the fourth type for virtual key codes such as function keys. This defines an accelerator for the Ctrl-F9 combination:

```
VK_F9, wID, VIRTKEY, CONTROL
```

The identifier VK_F9 is defined in WINDOWS.H as the virtual key code for the F9 key, so you have to include the statement:

```
#include <windows.h>
```

near the top of the resource script. The resource compiler defines an identifier named RC_INVOKED that causes much of WINDOWS.H to be ignored. Alternatively, the Windows Software Development Kit includes a header file called STYLE.H that is much smaller

than WINDOWS.H but contains most of the identifiers you'll need in resource scripts, including virtual key codes. So you need only add the statement:

```
#include <style.h>
```

to the top of your resource script.

The first and third types of definition shown above are rarely used. If you want to use them, watch out for case-sensitivity. Windows does a case-sensitive match on the "char" or nCode based on the character you press. When you add the SHIFT keyboard, Windows checks to see if the Shift key is depressed. This situation sometimes causes results you may not anticipate. For instance, if "char" is "A", the keyboard accelerator is invoked when you press the A key with the Shift key down or Caps Lock on, but not both. If you use "A" with SHIFT, the A key must be pressed with Shift down, but the accelerator can't be invoked at all when Caps Lock is on. Similarly, "a" by itself is a keyboard accelerator for the unshifted A key or for the A key with both Shift down and Caps Lock on. But "a" with SHIFT invokes the accelerator only when Shift is down and Caps Lock is on.

When you define keyboard accelerators for a menu item, you should include the key combination in the menu item text. The tab (\textit{t}) character separates the text from the accelerator so that the accelerators align in a second column. To notate accelerator keys in a menu, the Application Style Guide recommends the text Ctrl or Shift followed by a plus sign and the key—for instance:

- F6
- · Shift+F6
- Ctrl+F6

Loading the Accelerator Table

Within your program, you use the LoadAccelerators function to load the accelerator table into memory and obtain a handle to it. The LoadAccelerators statement is very similar to the LoadIcon, LoadCursor, LoadBitmap, and LoadMenu statements.

First, define a handle to an accelerator table as type HANDLE:

```
HANDLE haccel ;
```

Then load the accelerator table:

```
hAccel = LoadAccelerators (hInstance, "MyAccelerators") ;
```

As with icons, cursors, bitmaps, and menus, you can use a number for the accelerator table name and then use that number in the *LoadAccelerators* statement with the MAKEINTRESOURCE macro or in quotations preceded by a # character.

Translating the Keystrokes

We will now tamper with three lines of code that are common to all the Windows programs that we've created so far in this book. The code is the standard message loop:

```
while (GetMessage (&msg, NULL, 0, 0))
{
    TranslateMessage (&msg) ;
    DispatchMessage (&msg) ;
}
```

Here's how we change it to use the keyboard accelerator table:

The TranslateAccelerator function determines if the message stored in the msg message structure is a keyboard message. If it is, the function searches for a match in the accelerator table whose handle is hAccel. If it finds a match, it calls the window function for the window whose handle is hWnd. If the keyboard accelerator ID corresponds to a menu item in the system menu, then the message is WM_SYSCOMMAND. Otherwise, the message is WM_COMMAND.

When TranslateAccelerator returns, the return value is nonzero if the message has been translated (and already sent to the window function) and 0 if not. If TranslateAccelerator returns a nonzero value, you should not call TranslateMessage and DispatchMessage but rather loop back to the GetMessage call.

The hWnd parameter in TranslateMessage looks a little out of place because it's not required in the other three functions in the message loop. Moreover, the message structure itself (the structure variable msg) has a member named hwnd, which is also a handle to a window.

The fields of the *msg* structure are filled in by the *GetMessage* call. When the second parameter of *GetMessage* is NULL, the function retrieves messages for all windows belonging to the application. When *GetMessage* returns, the *hwnd* member of the *msg* structure is the window handle of the window that will get the message. However, when *TranslateAccelerator* translates a keyboard message into a WM_COMMAND or WM_SYSCOMMAND message, it replaces the *msg.hwnd* window handle with the window handle *hWnd* specified as the first parameter to the function. That is how Windows sends all keyboard accelerator messages to the same window function even if another window in the application currently has the input focus. *TranslateAccelerator* does not translate keyboard messages when a modal dialog box or message box has the input focus, because messages for these windows do not come through the program's message loop.

In some cases in which another window in your program (such as a modeless dialog box) has the input focus, you may not want keyboard accelerators to be translated. You'll see how to handle this in Chapter 11.

Receiving the Accelerator Messages

When a keyboard accelerator corresponds to a menu item in the system menu, TranslateAccelerator sends the window function a WM_SYSCOMMAND message. If you need to, you can differentiate between a direct system menu selection and a keyboard accelerator for that system menu item by the high word of IParam:

16	wParam	LOWORD (IParam)	HIWORD (lParam)
Accelerator:	Accelerator ID	0	1
Мепи:	Menu ID	0	0

If the accelerator ID corresponds to a menu item (or does not correspond to any item on the menu or system menu), *TranslateAccelerator* sends the window function a WM_COMMAND message. The following table shows the types of WM_COMMAND messages you can receive for keyboard accelerators, menu commands, and child window controls:

	wParam	LOWORD (lParam)	HIWORD (lParam)
Accelerator:	Accelerator ID	0	1
Мепи:	Menu ID	0	0
Control:	Control ID	Child window handle	Notification code

If the keyboard accelerator corresponds to a menu item, the window function also receives WM_INITMENU, WM_INITMENUPOPUP, and WM_MENUSELECT messages, just as if the menu option had been chosen. Programs usually enable and disable items in a popup menu when processing WM_INITMENUPOPUP, so you still have that facility when using keyboard accelerators. If the keyboard accelerator corresponds to a disabled or grayed menu item, however, TranslateAccelerator does not send the window function a WM_COMMAND or WM_SYSCOMMAND message.

If the active window is minimized, TranslateAccelerator sends the window function WM_SYSCOMMAND messages—but not WM_COMMAND messages—for keyboard accelerators that correspond to enabled system menu items. TranslateAccelerator also sends that window function WM_COMMAND messages for accelerators that do not correspond to any menu items.

POPPAD with a Menu and Accelerators

In Chapter 7 we created a program called POPPAD that uses a child window edit control to mimic some of the workings of Windows' NOTEPAD program. In this chapter we'll add a File and Edit menu to POPPAD. The Edit items will all be functional; we'll finish the File functions in Chapter 11 and the Print function in Chapter 16. This revised version of POPPAD is shown in Figure 10-11 (beginning on the following page).

```
poppad.obj : poppad.c poppad.h
     cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp poppad.c

poppad.res : poppad.rc poppad.h poppad.ico
     rc -r poppad.rc

poppad.exe : poppad.obj poppad.def poppad.res
     link4 poppad, /align:l6, /map, slibw, poppad.def
     rc poppad.res
```

```
/* POPPAD.C -- Popup Editor (second version: includes menu) */
#include <windows.h>
#include "poppad.h"
long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG);
char szAppName [] = "PopPad" ;
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
     HANDLE
               hInstance, hPrevInstance;
      LPSTR
                lpszCmdLine;
      int
                nCmdShow;
     HANDLE
              hAccel ;
      HWND
                hWnd ;
     MSG
                ESQ;
     WNDCLASS wndclass ;
      if (!hPrevInstance)
                                      = CS HREDRAW | CS VREDRAW ;
            wndclass.style
            wndclass.lpfnWndProc = WndProc;
            wndclass.cbClsExtra = 0;
wndclass.cbWndExtra = 0;
           wndclass.hInstance = hInstance;
wndclass.hIncon = LoadIcon (hInstance, szAppName);
wndclass.hCursor = LoadCursor (NULL, IDC_ARROW);
wndclass.hbrBackground = GetStockObject (WHITE_BRUSH);
            wndclass.lpszMenuName = szAppName ;
            wndclass.lpszClassName = szAppName ;
            if (!RegisterClass (&wndclass))
                  return FALSE;
      hWnd = CreateWindow (szAppName, szAppName,
                              WS OVERLAPPEDWINDOW,
                              CW_USEDEFAULT, 0,
GetSystemMetrics (SM_CXSCREEN) / 2,
                              GetSystemMetrics (SM CYSCREEN) / 2,
                              NULL, NULL, hinstance, NULL) ;
      ShowWindow (hWnd, nCmdShow) ;
      UpdateWindow (hWnd);
```

Figure 10-11. The POPPAD program

```
hAccel = LoadAccelerators (hInstance, szAppName) ;
      while (GetMessage (&msg, NULL, 0, 0))
            if (!TranslateAccelerator (hWnd, hAccel, &msq))
                 TranslateMessage (&msg) :
                 DispatchMessage (&msg) ;
      return msg.wParam ;
AskConfirmation (hWnd)
      HWND hWnd ;
      return MessageBox (hWnd, "Really want to close PopPad?",
                                szAppName, MB YESNO | MB ICONQUESTION) ;
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
     HWND
                   hWnd;
     unsigned
                   iMessage;
      WORD
                   wParam;
     LONG
                   1Param;
     static HWND hWndEdit ;
     LONG
                   1Select :
     WORD
                   wEnable ;
     switch (iMessage)
           case WM CREATE:
                 hWndEdit = CreateWindow ("edit", NULL,
WS_CHILD | WS_VISIBLE | WS_HSCROLL | WS_VSCROLL |
WS_BORDER | ES_LEFT | ES_MULTILINE |
ES_AUTOHSCROLL | ES_AUTOVSCROLL,
                             0, 0, 0, 0,
                             hWnd, 1, ((LPCREATESTRUCT) 1Param) ->hInstance, NULL) ;
                 break ;
           case WM SETFOCUS:
                 SetFocus (hWndEdit) ;
                 break ;
           case WM SIZE:
                 MoveWindow (hWndEdit, 0, 0, LOWORD (lParam),
                                                 HIWORD (1Param), TRUE) ;
                 break :
           case WM INITMENUPOPUP:
                 if (lParam == 1)
                       EnableMenuItem (wParam, IDM_UNDO,
                             SendMessage (hWndEdit, EM CANUNDO, 0, 0L) ?
MF_ENABLED : MF_GRAYED) ;
```

```
EnableMenuItem (wParam, IDM_PASTE,
                 IsClipboardFormatAvailable (CF TEXT) ?
                      MF ENABLED : MF GRAYED) ;
           lSelect = SendMessage (hWndEdit, EM GETSEL, 0, 0L) ;
           if (HIWORD (1Select) == LOWORD (1Select))
                 wEnable = MF_GRAYED ;
           else
                 wEnable = MF ENABLED ;
           EnableMenuItem (wParam, IDM CUT, wEnable) :
EnableMenuItem (wParam, IDM_COPY, wEnable) :
EnableMenuItem (wParam, IDM_CLEAR, wEnable) :
     break ;
case WM COMMAND :
      if (LOWORD (lParam))
            if (wParam == 1 && HIWORD (1Param) == EN ERRSPACE)
                 MessageBox (hWnd, "Edit control out of space.",
                      szAppName, MB OK | MB ICONHAND) ;
     else
            switch (wParam)
                 case IDM NEW:
                 case IDM OPEN:
                 case IDM_SAVE:
case IDM_SAVEAS:
                  case IDM PRINT:
                       MessageBeep (0);
                       break ;
                  case IDM EXIT:
                       SendMessage (hWnd, WM CLOSE, 0, 0L) ;
                       break ;
                 case IDM ABOUT:
                        MessageBox (hWnd,
                             "POPPAD by Charles Petzold, 1987",
szAppName, MB OK | MB_ICONASTERISK) ;
                       break ;
                  case IDM UNDO:
                       SendMessage (hWndEdit, WM UNDO, 0, 0L) ;
                        break :
                  case IDM CUT:
                        SendMessage (hWndEdit, WM CUT, 0, 0L) ;
                        break :
                  case IDM COPY:
                        SendMessage (hWndEdit, WM COPY, 0, 0L) ;
                        break ;
```


```
case IDM PASTE:
                         SendMessage (hWndEdit, WM PASTE, 0, 0L) ;
                         break ;
                    case IDM CLEAR:
                         SendMessage (hWndEdit, WM CLEAR, 0, 0L) ;
                         break ;
                    case IDM SELALL:
                         SendMessage (hWndEdit, EM SETSEL, 0,
                                       MAKELONG (0, 32767));
                         break ;
          break ;
    case WM CLOSE:
          if (IDYES == AskConfirmation (hWnd))
              DestroyWindow (hWnd) ;
          break ;
     case WM QUERYENDSESSION:
          if (IDYES == AskConfirmation (hWnd))
              return 1L ;
          break ;
     case WM DESTROY :
         PostQuitMessage (0) ;
         break ;
    default :
          return DefWindowProc (hWnd, iMessage, wParam, lParam) ;
return OL ;
```

```
#define IDM NEW
                    1
#define IDM OPEN
                    2
#define IDM_SAVE
                     3
#define IDM SAVEAS 4
#define IDM PRINT
#define IDM EXIT
                    6
#define IDM ABOUT
#define IDM UNDO
                    8
#define IDM_CUT
#define IDM_COPY
                    10
#define IDM PASTE
                   11
#define IDM_CLEAR
                    12
#define IDM_SELALL 13
```

Figure 10-11. Continued

```
#include "style.h"
#include "poppad.h"
PopPad ICON poppad.ico
PopPad MENU
      BEGIN
             POPUP "&File"
                    BEGIN
                          MENUITEM "&New",
                                                                   IDM NEW
                          MENUITEM "&Open...",
                                                                   IDM OPEN
                           MENUITEM "&Save",
                           MENUITEM "Save &As ... ",
                                                                   IDM SAVEAS
                           MENUITEM SEPARATOR
                          MENUITEM "&Print",
MENUITEM SEPARATOR
                                                                   IDM PRINT
                          MENUITEM "E&xit",
                                                                   IDM EXIT
                           MENUITEM "A&bout PopPad...", IDM ABOUT
                    END
             POPUP "&Edit"
                    BEGIN
                           MENUITEM "&Undo\tAlt+BkSp", IDM_UNDO
                           MENUITEM SEPARATOR
                          MENUITEM "Cust\tDel", IDM_CUT
MENUITEM "&Copy\tCtrl+Ins", IDM_COPY
MENUITEM "&Paste\tShift+Ins", IDM_PASTE
MENUITEM "C&lear\tShift+Del", IDM_CLEAR
                           MENUITEM SEPARATOR
                           MENUITEM "&Select All",
                                                                   IDM SELALL
                    END
        END
PopPad ACCELERATORS
       BEGIN
              VK_DELETE, IDM_CUT,
                                         VIRTKEY
             VK_INSERT, IDM_COPY, VIRTKEY, CONTROL VK_INSERT, IDM_PASTE, VIRTKEY, SHIFT VK_DELETE, IDM_CLEAR, VIRTKEY, SHIFT
       END
```

POPPAD -- CO



```
NAME POPPAD
DESCRIPTION 'Popup Editor (C) Charles Petzold, 1987'
STUB 'WINSTUB.EXE'
CODE MOVEABLE
DATA MOVEABLE MULTIPLE
HEAPSIZE 1024
STACKSIZE 4096
EXPORTS WndProc
```

The POPPAD.RC resource script file contains the menu and accelerator table. You'll notice that the accelerators are all indicated within the text strings of the Edit popup menu following the tab (\t) character.

Enabling Menu Items

The major job in the window function now involves enabling and graying the options in the Edit menu, which is done when processing the WM_INITMENUPOPUP. First, the program checks to see if the Edit popup is about to be displayed. Because the position index of Edit in the menu (starting with File at 0) is 1, *IParam* equals 1 if the Edit popup is about to be displayed.

To determine if the Undo option can be enabled, POPPAD sends an EM_CANUNDO message to the edit control. The SendMessage call returns nonzero if the edit control can perform an Undo action, in which case the option is enabled; otherwise, it is grayed:

```
EnableMenuItem (wParam, IDM_UNDO,
SendMessage (hWndEdit, EM_CANUNDO, 0, 0L) ?

MF_ENABLED : MF_GRAYED) ;
```

The Paste option should be enabled only if the Clipboard currently contains text. We can determine this through the IsClipboardFormatAvailable call with the CF_TEXT identifier:

The Cut, Copy, and Clear options should be enabled only if text in the edit control has been selected. Sending the edit control an EM_GETSEL message returns a long integer containing this information:

```
1Select = SendMessage (hWndEdit, EM_GETSEL, 0, 0L) ;
```

The low word of *ISelect* is the position of the first selected character, the high word of *ISelect* is the position of the character following the selection. If these two words are equal, no text has been selected:

```
if (HIWORD (lSelect) == LOWORD (lSelect))
    wEnable = MF_GRAYED ;
else
    wEnable = MF_ENABLED ;
```

The value of wEnable is then used for the Cut, Copy, and Clear options:

```
EnableMenuItem (wParam, IDM_CUT, wEnable);
EnableMenuItem (wParam, IDM_COPY, wEnable);
EnableMenuItem (wParam, IDM_CLEAR, wEnable);
```

Processing the Menu Options

Of course, if we were not using a child window edit control for POPPAD, we would now be faced with the problems involved with actually implementing the Undo, Cut, Copy, Paste, Clear, and Select All options from the Edit menu. But the edit control makes this process easy, because we merely send the edit control a message for each of these options:

```
case IDM_UNDO:
     SendMessage (hWndEdit, WM_UNDO, 0, 0L) ;
case IDM_CUT:
     SendMessage (hWndEdit, WM_CUT, 0, 0L) ;
     break ;
case IDM_COPY:
     SendMessage (hWndEdit, WM_COPY, 0, 0L);
    break ;
case IDM_PASTE:
     SendMessage (hWndEdit, WM_PASTE, 0, 0L);
     break ;
case IDM_CLEAR:
     SendMessage (hWndEdit, WM_CLEAR, 0, 0L) ;
     break ;
case IDM_SELALL:
     SendMessage (hWndEdit, EM_SETSEL, 0,
                             MAKELONG (0, 32767));
```

Notice that we could have simplified this even further by making the values of IDM_UNDO, IDM_CUT, and so forth equal to the values of the corresponding window messages WM_UNDO, WM_CUT, and so forth.

The About option for the File popup invokes a simple message box:

In Chapter 11 we'll make this a dialog box.

The Exit option sends the window function a WM_CLOSE message:

```
case IDM_EXIT:
    SendMessage (hWnd, WM_CLOSE, 0, 0L);
    break;
```

That is precisely what DefWindowProc does when it receives a WM_SYSCOMMAND message with wParam equal to SC_CLOSE.

In previous programs we have not processed the WM_CLOSE messages in our window function but have simply passed them to <code>DefWindowProc</code>. <code>DefWindowProc</code> does something very simple with WM_CLOSE: It calls the <code>DestroyWindow</code> function. Rather than send WM_CLOSE messages to <code>DefWindowProc</code>, however, POPPAD processes them. This fact is not so important now, but it will become very important in Chapter 11 when POPPAD can actually edit files:

```
case WM_CLOSE:
   if (IDYES == AskConfirmation (hWnd))
       DestroyWindow (hWnd);
   break;
```

AskConfirmation is a function in POPPAD that displays a message box asking for confirmation to close the program:

The message box (as well as the AskConfirmation function) returns IDYES if the Yes button is selected. Only then does POPPAD call DestroyWindow. Otherwise, the program is not terminated.

If you want to ask for confirmation before terminating a program, you must also process WM_QUERYENDSESSION messages. Windows begins sending every window function a WM_QUERYENDSESSION message when the user chooses Close from the MS-DOS Executive system menu. If any window function returns 0 from this message, the Windows session is not terminated. Here's how we handle WM_QUERYENDSESSION:

```
case WM_QUERYENDSESSION:
   if (IDYES == AskConfirmation (hWnd))
       return 1L;
   break;
```

The WM_CLOSE and WM_QUERYENDSESSION messages are the only two messages you have to process if you want to ask for user confirmation before ending a program. That's why we

made the Exit menu option in POPPAD send the window function a WM_CLOSE message—by doing so, we avoided having to ask for confirmation at yet a third point.

If you process WM_QUERYENDSESSION messages, you may also be interested in the WM_ENDSESSION message. Windows sends this message to every window function that has previously received a WM_QUERYENDSESSION message. The wParam parameter is 0 if the session fails to terminate because another program has returned 0 from WM_QUERYENDSESSION. The WM_ENDSESSION message essentially answers the question: I told Windows it was OK to terminate me, but did I really get terminated?

Although I've included the normal New, Open, Save, and Save As options in POPPAD's File menu, they are currently nonfunctional. To process these commands, we need to use dialog boxes. You're now ready to learn about them.

Chapter 11

Dialog Boxes

Dialog boxes are most often used for obtaining additional input from the user beyond what can be easily managed through a menu. The programmer indicates that a menu item invokes a dialog box by adding an ellipsis (...) to the menu item text.

A dialog box generally takes the form of a popup window containing various child window controls. The size and placement of these controls are specified in a "dialog box template" in the program's resource script file. Windows is responsible for creating the dialog box popup window and the child window controls and for providing a window function to process dialog box messages (including all keyboard and mouse input). The collection of code within Windows that does all this is sometimes referred to as the "dialog box manager."

Many of the messages that are processed by the dialog box window function within Windows are also passed to a function within your own program, often called a "dialog box function" or "dialog function." This function is similar to a normal window function, but with some important differences. Generally, you will not be doing very much within the dialog function except initializing the child window controls when the dialog box is created, processing messages from the child window controls, and ending the dialog box.

The subject of dialog boxes would normally be a big one, because it involves the use of child window controls. However, we have already explored child window controls in Chapter 7. When you use child window controls in dialog boxes, the Windows dialog box manager picks up a lot of the responsibilities that we assumed in Chapter 7. In particular, the problems we encountered with passing the input focus between the scroll bars in the COLORSCR program does not occur with dialog boxes. Windows handles all the logic necessary to shift input focus between controls in a dialog box.

However, adding a dialog box to a program is not a trivial undertaking. It involves changes to several files—the dialog box template goes in the resource script file, the dialog box function goes in the source code file, the name of the dialog box function goes in the

module definition file, and identifiers used in the dialog box often go in the program's header file. We'll begin with a simple dialog box so that you get a feel for the interconnections between these various pieces.

MODAL DIALOG BOXES

Dialog boxes are either "modal" or "modeless." The modal dialog box is the most common. When your program displays a modal dialog box, the user cannot switch between the dialog box and another window in your program. The user must explicitly end the dialog box, usually by clicking a push button marked either OK or Cancel. The user can, however, generally switch to another program while the dialog box is still displayed. Some dialog boxes (called "system modal") do not allow even this. System modal dialog boxes must be ended before the user does anything else in Windows.

Creating an "About" Dialog Box

Even if a Windows program requires no user input (like CLOCK, for instance), it will often have a dialog box that is invoked by an About option on the menu. This dialog box displays the name and icon of the program, a copyright notice, a push button labeled OK, and perhaps other information. The first program we'll look at does nothing except display an About dialog box. The ABOUT1 program is shown in Figure 11-1.

```
about1.obj : about1.c
    cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp about1.c

about1.res : about1.rc about1.ico
    rc -r about1.rc

about1.exe : about1.obj about1.def about1.res
    link4 about1, /align:16, /map, slibw, about1
    rc about1.res
```

```
ABOUT 1 . C
```

```
/* ABOUT1.C -- About Box Demo Program No. 1 */
#include <windows.h>
#define IDM_ABOUT 1
long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG);
```

Figure 11-1. The ABOUT1 program

Figure 11-1. Continued

```
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
     HANDLE hInstance, hPrevInstance;
     LPSTR
                  lpszCmdLine;
     int
                  nCmdShow;
     static char szAppName [] = "About1" ;
                  msq;
                  hWnd ;
     HWND
     WNDCLASS
                  wndclass ;
     if (!hPrevInstance)
          wndclass.style
                                  = CS_HREDRAW | CS_VREDRAW ;
          wndclass.lpfnWndProc = WndProc ;
          wndclass.cbClsExtra = 0;
          wndclass.cbWndExtra = 0;
          wndclass.hInstance = hInstance; szAppName); speciass.hIcon = LoadIcon (hInstance, szAppName);
          wndclass.hbrBackground = GetStockObject (WHITE_BRUSH) ;
          wndclass.lpszMenuName = NULL ;
          wndclass.lpszClassName = szAppName ;
          if (!RegisterClass (&wndclass))
               return FALSE;
     hWnd = CreateWindow (szAppName, "About Box Demo Program",
                          WS OVERLAPPEDWINDOW,
CW_USEDEFAULT, 0,
                          CW USEDEFAULT, 0,
                          NULL, NULL, hinstance, NULL) ;
     ShowWindow (hWnd, nCmdShow) ;
     UpdateWindow (hWnd);
     while (GetMessage (&msg, NULL, 0, 0))
          TranslateMessage (&msg) ;
          DispatchMessage (&msg) ;
     return msg.wParam ;
BOOL FAR PASCAL AboutDlgProc (hDlg, iMessage, wParam, 1Param)
     HWND
           hDlq ;
     unsigned iMessage ;
     WORD
              wParam ;
     LONG
              lParam ;
     switch (iMessage)
          case WM INITDIALOG:
               break :
```

Figure 11-1. Continued

```
case WM COMMAND:
               switch (wParam)
                     case IDOK:
                          EndDialog (hDlg, 0);
                          break :
                     default:
                          return FALSE ;
                break ;
          default:
                return FALSE ;
     return TRUE ;
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
     HWND
                    hWnd;
     unsigned
                     iMessage;
     WORD
                     wParam;
     LONG
                     1Param:
     static FARPROC lpfnAboutDlgProc ;
     static HWND hInstance ;
                     hMenu ;
     HMENU
     switch (iMessage)
           case WM CREATE:
                hInstance = ((LPCREATESTRUCT) 1Param) ->hInstance ;
                lpfnAboutDlgProc = MakeProcInstance (AboutDlgProc, hInstance) ;
                hMenu = GetSystemMenu (hWnd, FALSE);
ChangeMenu (hMenu, 0, NULL, 0, MF_APPEND);
ChangeMenu (hMenu, 0, "A&bout About1...", IDM_ABOUT, MF_APPEND);
                break ;
          case WM SYSCOMMAND:
                switch (wParam)
                     case IDM ABOUT:
                           DialogBox (hInstance, "AboutBox", hWnd,
                                           lpfnAboutDlgProc) ;
                           break ;
                return DefWindowProc (hWnd, iMessage, wParam, 1Param) ;
           case WM DESTROY :
                PostQuitMessage (0) ;
                break ;
           default :
                return DefWindowProc (hWnd, iMessage, wParam, 1Param) ;
     return OL ;
```

Figure 11-1. Continued

```
#include "style.h"
About1 ICON about1.ico
AboutBox DIALOG 20, 20, 160, 80
STYLE WS_POPUP | WS_DLGFRAME
                                                   -1,
           CTEXT "About1"
                                                         0, 12, 160,
                                                   -1,
                                                         8, 8, 0,
0, 36, 160,
           ICON "About1"
           CTEXT "About Box Demo Program"
                                                  -1,
                                                                        8
                                                  -1,
           CTEXT "(C) Charles Petzold, 1987"
                                                        0, 48, 160,
           DEFPUSHBUTTON "OK"
                                                IDOK, 64, 60, 32, 14, WS GROUP
     END
```



```
NAME ABOUT1
DESCRIPTION 'About Box Demo No. 1 (C) Charles Petzold, 1987'
STUB 'WINSTUB.EXE'
CODE MOVEABLE
DATA MOVEABLE MULTIPLE
HEAPSIZE 1024
STACKSIZE 4096
EXPORTS WndProc
AboutDlgProc
```

The Dialog Box Template

The first job involved in adding a dialog box to a program is designing the dialog box template. This template can go directly in the resource script file, or it can be in a separate file that by convention uses the extension .DLG (for "dialog"). If you put the template in a separate file, you include the line:

rcinclude filename.dlg

in the resource script file.

You can create the dialog box template by hand in a text editor, or you can use the DLGBOX program included with the Windows Software Development Kit. Because the output from DLGBOX is virtually unreadable, I'll be showing dialog box templates that look as if they were created by hand. A discussion of DLGBOX concludes this chapter.

The dialog box template for ABOUT1 looks like this:

```
AboutBox DIALOG 20, 20, 160, 80

STYLE WS_POPUP | WS_DLGFRAME

BEGIN

CTEXT "About1" -1, 0, 12, 160, 8

ICON "About1" -1, 8, 8, 0, 0

CTEXT "About Box Demo Program" -1, 0, 36, 160, 8

CTEXT "(C) Charles Petzold, 1987" -1, 0, 48, 160, 8

DEFPUSHBUTTON "OK" IDOK, 64, 60, 32, 14, WS_GROUP
```

The first line gives the dialog box a name (in this case, *AboutBox*). As is the case for other resources, you can use a number instead. The name is followed by the keyword DIALOG and four numbers. The first two numbers are the x and y coordinates of the upper left corner of the dialog box, relative to the client area of its parent when the dialog box is invoked by the program. The second two numbers are the width and height of the dialog box.

These coordinates and sizes are *not* in units of pixels. They are instead based on a special coordinate system used only for dialog box templates. The numbers are based on the size of a system font character: x coordinates and width are expressed in units of ¼ of a character width; y coordinates and height are expressed in units of ¼ of a character height. Thus for this particular dialog box, the upper left corner of the dialog box is 5 characters from the left of the main window's client area and 2½ characters from the top. It is 40 characters wide and 10 characters high.

This coordinate system allows you to use coordinates and sizes that will retain the general dimensions and look of the dialog box regardless of the resolution of the video display. Because system font characters are often approximately twice as high as they are wide, the units on both the x and y axes are about the same.

The DIALOG statement can also include load options (PRELOAD and LOADONCALL) and memory options (FIXED, MOVEABLE, and DISCARDABLE) immediately following the word DIALOG. The defaults are LOADONCALL and MOVEABLE. The STYLE statement in the template is similar to the style field of a *CreateWindow* call. Using WS_POPUP and WS_DLGFRAME is normal for modal dialog boxes, but we'll explore some alternatives later on.

Between the BEGIN and END statements, you define the child window controls that will appear in the dialog box. This dialog box uses three types of child window controls: CTEXT (centered text), ICON (an icon), and DEFPUSHBUTTON (a default push button). The format of these statements is:

```
control-type "text" nID, xPos, yPos, xWidth, yHeight, dwStyle
```

The dwStyle value at the end is optional; it specifies additional window styles using identifiers defined in WINDOWS.H.

These CTEXT, ICON, and DEFPUSHBUTTON identifiers are used only in dialog boxes. They are shorthand for a particular window class and window style. For example, CTEXT indicates that the class of the child window control is "static" and that the style is:

WS_CHILD | SS_CENTER | WS_VISIBLE | WS_GROUP

Although this is the first time we've encountered the WS_GROUP identifier, we used the WS_CHILD, SS_CENTER, and WS_VISIBLE window styles when creating static child window text controls in the COLORSCR program in Chapter 7.

For the icon, the text field is the name of the program's icon resource, which is also defined in the ABOUTI resource script. For the push button, the text field is the text that appears inside the push button. This text is equivalent to the text specified as the second parameter to a *CreateWindow* call when you create a child window control in a program.

The nID field is a value that the child window uses to identify itself when sending messages (usually WM_COMMMAND messages) to its parent. The parent window of these child window controls is the dialog box window itself, which sends these messages to a window function in Windows. However, this window function also sends these messages to the dialog box function that you'll include in your program. The nID values are equivalent to the child window IDs used in the CreateWindow function when we created child windows in Chapter 7. Because the text and icon controls do not send messages back to the parent window, these values are set to −1. The nID value for the push button is IDOK, which is defined in WINDOWS.H as 1.

The next four numbers set the position of the child window control (relative to the upper left corner of the dialog box's client area) and the size. The position and size are expressed in units of ¼ the width and ⅓ the height of a system font character. The width and height values are ignored for the ICON statement.

The DEFPUSHBUTTON statement in the dialog box template includes the window style WS_GROUP in addition to the window style implied by the DEFPUSHBUTTON keyword. I'll have more to say about WS_GROUP (and the related WS_TABSTOP style) when discussing the second version of this program, ABOUT2, a bit later.

The Dialog Box Function

The dialog box function within your program handles messages to the dialog box. Although it looks very much like a window function, it is not a true window function. The window function for the dialog box is within Windows. That window function calls your dialog box function with many of the messages that it receives. Here's the dialog box function for ABOUT1:

```
BOOL FAR PASCAL AboutDlgProc (hDlg, iMessage, wParam, lParam)
     HWND
             hDlg ;
     unsigned iMessage ;
     WORD
              wParam ;
     LONG
               lParam ;
     switch (iMessage)
          case WM_INITDIALOG:
               break ;
          case WM_COMMAND:
               switch (wParam)
                    case IDOK:
                         EndDialog (hDlg, 0);
                         break ;
                    default:
                         return FALSE ;
               break :
          default:
               return FALSE ;
     return TRUE ;
```

The parameters to this function are the same as those for a normal window function. (Although I've used hDlg for the handle to the dialog box window, you can use hWnd instead if you like.) Let's note first the differences between this function and a window function:

- A window function returns a long; a dialog box function returns a BOOL (which is defined in WINDOWS.H as an int).
- A window function calls DefWindowProc if it does not process a particular message; a dialog box function returns TRUE (nonzero) if it processes a message and FALSE (0) if it does not.
- A dialog box function does not need to process WM_PAINT or WM_DESTROY
 messages. A dialog box function will not receive a WM_CREATE message; instead,
 the dialog box function does initialization during the special WM_INITDIALOG
 message.

Some programmers prefer using if and else statements for processing messages in very simple dialog boxes. The logic equivalent to that in AboutDlgProc would look like this:

```
if (iMessage == WM_INITDIALOG)
    return TRUE ;
```

```
else if (iMessage == WM_COMMAND && wParam == IDOK)
    {
        EndDialog (hDlg, 0) ;
        return TRUE ;
     }
else
    return FALSE ;
```

The WM_INITDIALOG message is the first message the dialog box function receives. This message is sent only to dialog box functions. If the dialog box function returns TRUE, then Windows sets the input focus to the first child window control in the dialog box that has a WS_TABSTOP style (which I'll explain in the discussion of ABOUT2). In this dialog box, the first child window control that has a WS_TABSTOP style is the push button. Alternatively, during processing of WM_INITDIALOG the dialog box function can use SetFocus to set the focus to one of the child window controls in the dialog box and then return FALSE.

The only other message this dialog box processes is WM_COMMAND. This is the message the push-button control sends to its parent window either when the button is clicked with the mouse or when the Spacebar is pressed while the button has the input focus. The ID of the control (which we set to IDOK in the dialog box template) is in wParam. For this message, the dialog box function calls EndDialog, which tells Windows to destroy the dialog box. For all other messages, the dialog box function returns FALSE to tell the dialog box window function within Windows that our dialog box function did not process the message.

Using *switch* and *case* constructions to return TRUE or FALSE values from the dialog box function can be a little confusing at times. Here are three simple rules:

- Include a default in every switch block and return FALSE for the default case.
- · Use break with every message you process.
- Return TRUE from the dialog box function.

The messages for a modal dialog box don't go through your program's message queue, so you needn't worry about the effect of any keyboard accelerators within the dialog box.

Exporting the Dialog Box Function

Because this dialog box function is called from outside the program, it must be included in the EXPORTS section of the module definition file:

```
EXPORTS WndProc
AboutDlgProc
```

This is the easiest part of the job but also the easiest to forget. I forget to export the dialog box function about one time in four. Often the function will seem to work (more or less), but because it's not using the program's data segment, it could be altering data inside Windows' data segment. Our simple dialog box function doesn't reference anything in ABOUTI's

data segment, so strictly speaking, exporting the function is not required. But get into the habit of exporting the function; I hope you achieve a better record than mine.

Invoking the Dialog Box

In ABOUTI.C, the dialog box is invoked by an About option added to the system menu. This menu option is added during processing of the WM_CREATE message in WndProc:

```
hMenu = GetSystemMenu (hWnd, FALSE);
ChangeMenu (hMenu, 0, NULL, 0, MF_APPEND);
ChangeMenu (hMenu, 0, "A&bout About1...", IDM_ABOUT, MF_APPEND);
```

IDM_ABOUT is defined at the top of the program. For programs that do not have a window menu, it is normal to add to the system menu the menu option that invokes the dialog box. Otherwise, the dialog box should be invoked by an option on the first popup menu.

Also during processing of WM_CREATE, the program's instance handle is obtained (and stored in a static variable) and *MakeProcInstance* is called to create an instance thunk for the dialog function. The pointer to the instance thunk is also stored in a static variable:

```
hInstance = ((LPCREATESTRUCT) lParam)->hInstance;
lpfnAboutDlgProc = MakeProcInstance (AboutDlgProc, hInstance);
```

The MakeProcInstance function assures that AboutDlgProc obtains the correct data segment address for this instance of ABOUT1.

The program then checks for WM_SYSCOMMAND messages where wParam is equal to IDM_ABOUT. When it gets one, the program calls DialogBox:

```
DialogBox (hInstance, 'AboutBox', hWnd, lpfnAboutDlgProc);
```

This function requires the instance handle (saved during WM_CREATE), the name of the dialog box (as defined in the resource script), the parent of the dialog box (which is the program's main window), and the address of the instance thunk return from <code>MakeProcInstance</code>. If you use a number rather than a name for the dialog box template, you can convert it into a string using the <code>MAKEINTRESOURCE</code> macro.

Selecting "About About1..." from the system menu displays the dialog box, as shown in Figure 11-2. You can end this dialog box by clicking the OK button with the mouse, by pressing the Spacebar, or by pressing Enter. For any dialog box that contains a default push button, Windows sends a WM_COMMAND message to the dialog box, with wParam equal to the ID of the default push button when Enter or the Spacebar is pressed.




Figure 11-2. The ABOUT1 program's dialog box

The *DialogBox* function you call to display the dialog box will not return control to *WndProc* until the dialog box is ended. The value returned from *DialogBox* is the second parameter to the *EndDialog* function called within the dialog box function. (This value is not used in ABOUT1 but is used in ABOUT2.) *WndProc* can then return control to Windows.

Even when the dialog box is displayed, WndProc can continue to receive messages. In fact, you can send messages to WndProc from within the dialog box function. ABOUTI's main window is the parent of the dialog box popup window, so the SendMessage call in AboutDlgProc would start off like this:

```
SendMessage (GetParent (hDlg), ...);
```

If you have a lot of dialog boxes within your program, you may not want to create and save instance thunks for all of them. You can instead create instance thunks as needed and free them after *DialogBox* returns:

```
lpfnDlgProc = MakeProcInstance (AboutDlgProc, hInstance);
DialogBox (hInstance, "AboutBox", hWnd, lpfnDlgProc);
FreeProcInstance (lpfnDlgProc);
```

More on the Dialog Box Style

The window style of the dialog box is specified in the STYLE line of the dialog box template. For ABOUT1, we used a style that is most common for modal dialog boxes:

```
STYLE WS_POPUP | WS_DLGFRAME
```

However, you can also experiment with other styles. For example, you can try:

```
STYLE WS_POPUP | WS_CAPTION
```

This creates a dialog box with a caption bar and a normal window border. The caption bar allows the user to move the dialog box around the display using the mouse. When you use WS_CAPTION, the x and y coordinates specified in the DIALOG statement are the coordinates of the dialog box's client area, relative to the upper left corner of the parent window's client area. The caption bar will be shown above the y coordinate.

If you have a caption bar, you can put text in it using the CAPTION statement in the dialog box template:

```
CAPTION "Dialog Box Caption"
```

Or while processing the WM_INITDIALOG message in the dialog function, you can use:

```
SetWindowText (hDlg, "Dialog Box Caption");
```

If you use the WS_CAPTION style, you can also add a system menu box with the WS_SYSMENU style:

```
STYLE WS_POPUP | WS_CAPTION | WS_SYSMENU
```

This style allows the user to select Move from the system menu and move the dialog box around the display using the keyboard. The Close option will also be enabled, but the WM_CLOSE message will not be processed by the dialog box window function within Windows.

Adding WS_THICKFRAME to the style allows the user to resize the dialog box, although resizing is unusual for a dialog box. If you don't mind being a little unusual, you can also try adding WS_MAXIMIZEBOX to the STYLE statement.

The STYLE statement is not required. If you do not include a STYLE or CAPTION statement in the template, the default style is:

```
WS_POPUP | WS_BORDER
```

But this is rather dull looking, WS_DLGFRAME produces much more attractive results. If you include a CAPTION statement with a STYLE statement, the default style is:

```
WS_POPUP | WS_CAPTION | WS_SYSMENU
```

Another window style specifically for dialog boxes is DS_SYSMODAL, which should change a modal dialog box into a system modal dialog box. It should, but it doesn't. If you want to create a system modal dialog box, you'll have to call <code>SetSysModalWindow</code> while processing WM_INITDIALOG in the dialog function.

You can also add a menu to a dialog box by specifying:

```
MENU menu-name
```

in the dialog box template. The argument is either the name or number of a menu in the resource script. Menus are highly uncommon for modal dialog boxes. If you use one, be sure that all the ID numbers in the menu and the dialog box controls are unique.

Although the dialog box window function is normally within Windows, you can use one of your own window functions to process dialog box messages. To do so, you specify a window class name in the dialog box template:

```
CLASS "class-name"
```

This approach is rare, but we'll use it in the HEXCALC program shown later in this chapter.

When you call *DialogBox* specifying the name of a dialog box template, Windows has almost everything it needs to create a popup window by calling the normal *CreateWindow* function. Windows obtains the coordinates and size of the window, the window style, the caption, and the menu from the dialog box template. Windows gets the instance handle and the parent window handle from the parameters to *DialogBox*. The only other piece of information it needs is a window class (assuming the dialog box template does not specify one). Windows registers a special window class for dialog boxes. The window function for this window class has access to the pointer to your dialog box function (which you provide in the *DialogBox* call), so it can keep your program informed of messages that this popup window receives. Of course, you can create and maintain your own dialog box by creating the popup window yourself. Using *DialogBox* is simply an easier approach.

Chapter 11: Dialog Boxes

More on Defining Controls

In the dialog box template in ABOUTLRC, we used the shorthand notation CTEXT, ICON, and DEFPUSHBUTTON to define the three types of child window controls we wanted in the dialog box. There are eight others you can use. Each type implies a particular predefined window class and a window style. The following table shows the equivalent window class and window style for each of the 11 control types:

Control Type	Window Class	Window Style
PUSHBUTTON	button	BS_PUSHBUTTON WS_TABSTOP
DEFPUSHBUTTON	button	BS_DEFPUSHBUTTON WS_TABSTOP
CHECKBOX	button	BS_CHECKBOX WS_TABSTOP
RADIOBUTTON	button	BS_RADIOBUTTON
GROUPBOX	button	BS_GROUPBOX
LTEXT	static	SS_LEFT WS_GROUP
CTEXT	static	SS_CENTER WS_GROUP
RTEXT	static	SS_RIGHT WS_GROUP
ICON	static	SS_ICON WS_GROUP
EDITTEXT	edit	ES_LEFT WS_BORDER WS_TABSTOP
LISTBOX	listbox	LBS_NOTIFY LBS_SORT WS_BORDER WS_VSCROLL

The RC resource compiler is the only program that understands this shorthand notation. In addition to the window styles shown above, each of these controls has the style:

```
WS_CHILD | WS_VISIBLE
```

For all these control types except LISTBOX and EDITTEXT, the format of the control statement is:

```
control-type "text", nID, xPos, yPos, xWidth, yHeight, dwStyle
```

For LISTBOX and EDITTEXT, the format is:

```
control-type nID, xPos, yPos, xWidth, yHeight, dwStyle
```

which excludes the text field. In both statements, the dwStyle parameter is optional.

In Chapter 7 I discussed rules for determining the width and height of predefined child window controls. You might want to refer back to that chapter for these rules, keeping in mind that sizes specified in dialog box templates are always in terms of ¼ the character width and ½ the character height.

The "style" field of the control statements is optional. It allows you to include other window style identifiers. For instance, if you wanted to create a check box consisting of text to the left of a square box, you could use:

CHECKBOX "text", nID, xPos, yPos, xWidth, yHeight, BS_LEFTTEXT

While the shorthand notation for child window controls is convenient, it is also incomplete. You can't create a child window edit control without a border or a list box that isn't sorted. And you can't create scroll bars at all. For this reason, the RC resource compiler also recognizes a generalized control statement that looks like this:

```
CONTROL "text", nID, "class", dwStyle, xPos, yPos, xWidth, yHeight
```

This statement allows you to create any type of child window control by specifying the window class and the complete window style. For example, instead of using:

```
PUSHBUTTON "OK", IDOK, 10, 20, 32, 14

you can use:

CONTROL "OK", IDOK, "button", Ws_CHILD | Ws_VISIBLE |

BS_PUSHBUTTON | WS_TABSTOP, 10, 20, 32, 14
```

When the resource script is compiled, these two statements are encoded identically in the .RES file and the .EXE file.

When you use CONTROL statements in a dialog box template, you don't need to include the WS_CHILD and WS_VISIBLE styles. Windows includes these in the window style when creating the child windows. The format of the CONTROL statement also clarifies what the Windows dialog manager does when it creates a dialog box. First, as I described above, it creates a popup window whose parent is the window handle that was provided in the DialogBox function. Then for each control in the dialog template, the dialog box manager creates a child window. The parent of each of these controls is the popup dialog box. The CONTROL statement shown above is translated into a CreateWindow call that looks like this:

```
CreateWindow ("button", "OK",

WS_CHILD | WS_VISIBLE | WS_TABSTOP | BS_PUSHBUTTON,

10 * xChar / 4, 20 * yChar / 8,

32 * xChar / 4, 14 * yChar / 8,

hDlg, nID, hInstance, NULL);
```

where xChar and yChar are the width and height of a system font character. The hDlg parameter is returned from the CreateWindow call that creates the dialog box window. The hInstance parameter is obtained from the original DialogBox call.

A More Complex Dialog Box

The simple dialog box in ABOUT1 demonstrates the basics of getting a dialog box up and running; now let's try something a little more complex. The ABOUT2 program, shown in Figure 11-3, demonstrates how to manage controls (in this case radio buttons) within a dialog box function and also how to paint on the client area of the dialog box.

```
/* ABOUT2.C -- About Box Demo Program No. 2 */
#include <windows.h>
#include "about2.h"
#define IDM ABOUT 1
long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG);
short nCurrentColor = IDD BLACK, nCurrentFigure = IDD RECT ;
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
     HANDLE
                  hInstance, hPrevInstance;
     LPSTR
                   lpszCmdLine;
                  nCmdShow;
     int
     static char szAppName [] = "About2" ;
                  msg;
     MSG
     HWND
                  hWnd ;
     WNDCLASS
                  wndclass ;
     if (!hPrevInstance)
           wndclass.style
                                   = CS HREDRAW | CS VREDRAW ;
           wndclass.lpfnWndProc = WndProc ;
           wndclass.cbClsExtra = 0;
           wndclass.cbWndExtra = 0;
wndclass.hInstance = hInstance;
          wndclass.hInstance = hInstance;
wndclass.hIcon = LoadIcon (hInstance, szAppName);
wndclass.hCursor = LoadCursor (NULL, IDC_ARROW);
           wndclass.hbrBackground = GetStockObject (WHITE_BRUSH) ;
          wndclass.lpszMenuName = NULL;
wndclass.lpszClassName = szAppName;
           if (!RegisterClass (&wndclass))
                return FALSE;
     hWnd = CreateWindow (szAppName, "About Box Demo Program",
                            WS OVERLAPPEDWINDOW,
                            CW USEDEFAULT, 0,
                            CW USEDEFAULT, 0,
                            NULL, NULL, hInstance, NULL) ;
     ShowWindow (hWnd, nCmdShow) ;
     UpdateWindow (hWnd);
```

Figure 11-3. The ABOUT2 program

```
while (GetMessage (&msg, NULL, 0, 0))
          TranslateMessage (&msg) ;
          DispatchMessage (&msg) ;
    return msg.wParam ;
void PaintWindow (hWnd, nColor, nFigure)
                  hWnd ;
     HWND
     short
                 nColor, nFigure ;
     static DWORD dwColor [8] = ( RGB (0,
                                              0, 0), RGB ( 0, 0, 255),
                                   RGB (0, 255, 0), RGB ( 0, 255, 255),
                                   RGB (255, 0, 0), RGB (255, 0, 255),
RGB (255, 255, 0), RGB (255, 255, 255) );
    HBRUSH
                  hBrush ;
    HDC
                  hDC :
     RECT
                  rect ;
     hDC = GetDC (hWnd) ;
     GetClientRect (hWnd, &rect) ;
     hBrush = CreateSolidBrush (dwColor [nColor - IDD BLACK]) ;
     hBrush = SelectObject (hDC, hBrush) ;
     if (nFigure == IDD RECT)
         Rectangle (hDC, rect.left, rect.top, rect.right, rect.bottom) ;
     else
          Ellipse
                   (hDC, rect.left, rect.top, rect.right, rect.bottom) ;
     DeleteObject (SelectObject (hDC, hBrush)) ;
     ReleaseDC (hWnd, hDC) ;
void PaintTheBlock (hCtrl, nColor, nFigure)
     HWND hCtrl ;
     short nColor, nFigure ;
     InvalidateRect (hCtrl, NULL, TRUE) ;
     UpdateWindow (hCtrl) :
     PaintWindow (hCtrl, nColor, nFigure) ;
BOOL FAR PASCAL AboutDlgProc (hDlg, iMessage, wParam, 1Param)
                hDlg ;
     HWND
     unsigned
                  iMessage ;
     WORD
                  wParam ;
     LONG
                 lParam ;
     static HWND hCtrlBlock ;
     static short nColor, nFigure ;
     switch (iMessage)
          case WM INITDIALOG:
               nColor = nCurrentColor ;
               nFigure = nCurrentFigure ;
               CheckRadioButton (hDlg, IDD_BLACK, IDD_WHITE, nColor) ;
               CheckRadioButton (hDlg, IDD_RECT, IDD_ELL, nFigure) ;
```

Figure 11-3. Continued

```
hCtrlBlock = GetDlgItem (hDlg, IDD PAINT) ;
               SetFocus (GetDlgItem (hDlg, nColor)) ;
               return FALSE ;
          case WM COMMAND:
               switch (wParam)
                    case IDOK:
                          nCurrentColor = nColor ;
                          nCurrentFigure = nFigure ;
                          EndDialog (hDlg, TRUE) ;
                          break ;
                    case IDCANCEL:
                          EndDialog (hDlg, FALSE) ;
                          break ;
                     case IDD BLACK:
                    case IDD RED:
                    case IDD GREEN:
                    case IDD_YELLOW:
                    case IDD_BLUE:
case IDD_MAGENTA:
case IDD_CYAN:
                    case IDD WHITE:
                          nColor = wParam ;
                          CheckRadioButton (hDlg, IDD BLACK, IDD WHITE, wParam);
                          PaintTheBlock (hCtrlBlock, nColor, nFigure) ;
                          break ;
                    case IDD RECT:
                     case IDD ELL:
                          nFigure = wParam ;
                          CheckRadioButton (hDlg, IDD RECT, IDD ELL, wParam) ;
                          PaintTheBlock (hCtrlBlock, nColor, nFigure) ;
                          break ;
                     default:
                         return FALSE ;
               break ;
          case WM_PAINT:
                PaintTheBlock (hCtrlBlock, nColor, nFigure) ;
               return FALSE ;
          default:
               return FALSE ;
     return TRUE ;
long FAR PASCAL WndProc (hWnd, iMessage, wParam, lParam)
                hWnd;
     unsigned
                    iMessage;
     WORD
                    wParam;
     LONG
                    lParam;
```

```
static FARPROC lpfnAboutDlgProc ;
static HWND
                hInstance ;
HMENU
                hMenu :
PAINTSTRUCT
                ps ;
switch (iMessage)
     case WM CREATE:
           hInstance = ((LPCREATESTRUCT) 1Param) ->hInstance ;
           lpfnAboutDlqProc = MakeProcInstance (AboutDlqProc, hInstance) ;
          hMenu = GetSystemMenu (hWnd, FALSE) ;
ChangeMenu (hMenu, 0, NULL, 0, MF_APPEND) ;
ChangeMenu (hMenu, 0, "A&bout About2...", IDM_ABOUT, MF_APPEND);
           break ;
     case WM SYSCOMMAND:
           switch (wParam)
                 case IDM ABOUT:
                      if (DialogBox (hInstance, "AboutBox", hWnd,
                                       lpfnAboutDlgProc))
                            InvalidateRect (hWnd, NULL, TRUE) ;
                      break ;
           return DefWindowProc (hWnd, iMessage, wParam, lParam) ;
     case WM PAINT:
           BeginPaint (hWnd, &ps) ;
           EndPaint (hWnd, &ps) ;
           PaintWindow (hWnd, nCurrentColor, nCurrentFigure) ;
           break ;
     case WM DESTROY :
           PostQuitMessage (0) ;
           break :
     default :
           return DefWindowProc (hWnd, iMessage, wParam, 1Param) ;
return OL ;
```

```
#define IDD_BLUE 11
#define IDD_GREEN 12
#define IDD_CYAN 13
#define IDD_RED 14
#define IDD_MAGENTA 15
#define IDD_YELLOW 16
#define IDD_WHITE 17
```

Figure 11-3. Continued

```
#define IDD_RECT 20
#define IDD_ELL 21
#define IDD_PAINT 30
```

```
#include <style.h>
#include "about2.h"
about2 ICON about2.ico
#define TABGRP (WS TABSTOP | WS GROUP)
AboutBox DIALOG 20, 20, 140, 188
                 STYLE WS_POPUP | WS_DLGFRAME
                 BEGIN
                                  CTEXT
                                                                         "About2"
                                                                                                                                                                              0, 12, 140,
                                                                                                                               -1,
                                                                                                                             -1,
                                                                                                                                                                          8,
                                                                            "About2"
                                                                                                                                                                                                                                   0
                                  ICON
                                                                                                                                                                                          8, 0,
                                                                         "About Box Demo Program" -1, 4, 36, 130,
                                  CTEXT
                                                                                                                 IDD PAINT, 68, 54, 60,
-1, 4, 50, 54,
IDD BLACK, 8, 60, 40,
IDD BLUE, 8, 72, 40,
                                  CTEXT
                                                                                                                                                                                                                              60
                                  GROUPBOX
                                                                         "&Color"
                                                                                                                                                                                                                            112
                                  RADIOBUTTON "&Black"
                                                                                                                                                                                                                                           TABGRP
                                                                                                                                                                                                                               12,
                                  RADIOBUTTON "B&lue"
                                                                                                                                                                                                                              12
                                                                                                                                                                            8, 84, 40,
8, 96, 40,
8, 108, 40,
                                  RADIOBUTTON "&Green"
                                                                                                                            IDD GREEN,
                                                                                                                                                                                                                             12
                                                                                                                          IDD CYAN, 8, 96, 40, IDD RED, 8, 108, 40, IDD MAGENTA, 8, 120, 40, IDD YELLOW, 8, 132, 40, 40, 100 YELLOW, 8, 132, 40, 100 YELLOW, 8, 132, 40, 100 YELLOW, 100 YEL
                                  RADIOBUTTON "Cya&n"
                                                                                                                                                                                                                              12
                                  RADIOBUTTON "&Red"
                                                                                                                                                                                                                               12
                                  RADIOBUTTON "&Magenta"
                                                                                                                                                                                                                               12
                                  RADIOBUTTON "&Yellow"
                                                                                                                                                                                                            40,
                                                                                                                                                                                                                              12
                                  RADIOBUTTON "&White"
                                                                                                                               IDD_WHITE,
                                                                                                                                                                           8, 144,
68, 120,
                                                                                                                                                                                                            40,
                                                                                                                                                                                                                              12
                                                                   "&Figure"
                                                                                                                                                                                                                              40, WS GROUP
                                  GROUPBOX
                                                                                                                               -1,
                                                                                                                                                                                                              60,
                                                                                                                               IDD RECT,
                                                                                                                                                                                                              50,
                                  RADIOBUTTON "Rec&tangle"
                                                                                                                                                                          72, 134,
                                                                                                                                                                                                                            12, TABGRP
                                  RADIOBUTTON "&Ellipse"
                                                                                                                               IDD ELL,
                                                                                                                                                                         72, 146, 50,
                                                                                                                                                                                                                            12
                                                                                                                               IDOK, 20, 168, 40, 14, WS GROUP IDCANCEL, 80, 168, 40, 14, WS GROUP
                                   DEFPUSHBUTTON "OK"
                                   PUSHBUTTON "Cancel"
                 END
```



Figure 11-3. Continued

```
NAME
               ABOUT2
DESCRIPTION
               'About Box Demo No. 2 (C) Charles Petzold, 1987'
               'WINSTUB.EXE'
STUB
CODE
               MOVEABLE
DATA
               MOVEABLE MULTIPLE
HEAPSIZE
               1024
STACKSIZE
               4096
EXPORTS
               WndProc
               AboutDlgProc
```

The About box in ABOUT2 has two groups of radio buttons. One group is used to select a color, and the other group is used to select either a rectangle or an ellipse. The rectangle or ellipse is shown in the dialog box with the interior colored with the current color selection. If you press the OK button, the dialog box is ended, and the program's window function draws the selected figure on its own client area. If you press Cancel, the client area of the main window remains the same. The dialog box is shown in Figure 11-4.



Figure 11-4. The ABOUT2 program's dialog box

Although the ABOUT2 dialog box uses the predefined identifiers IDOK and IDCANCEL for the two push buttons, each of the radio buttons has its own identifier beginning with the letters IDD ("ID for dialog box control"). These identifiers are defined in ABOUT2.H.

Working with Dialog Box Controls

In Chapter 7, you discovered that most child window controls send WM_COMMAND messages to the parent window. (The exception is scroll bar controls.) You also saw that the parent window can alter child window controls (for instance, checking or unchecking radio buttons or check boxes) by sending messages to the controls. You can similarly alter controls

Chapter 11: Dialog Boxes

in a dialog box function. If you have a series of radio buttons, for example, you can check and uncheck the buttons by sending them messages. However, Windows also provides several shortcuts when working with controls in dialog boxes. Let's look at the way in which the dialog box function and the child window controls communicate.

The dialog box template for ABOUT2 is shown in the ABOUT2,RC resource script in Figure 11-3. The GROUPBOX control is simply a frame with a title (either Color or Figure) that surrounds each of the two groups of radio buttons. The eight radio buttons in the first group are mutually exclusive, as are the two radio buttons in the second group.

When one of the radio buttons is clicked with the mouse (or when the Spacebar is pressed while the radio button has the input focus), the child window sends its parent a WM_COMMAND message with wParam set to the ID of the control. The low word of IParam is the window handle of the control, and the high word of IParam is a notification code. For a radio button, this notification code is BN_CLICKED, or 0. The dialog box window function in Windows then passes this WM_COMMAND message to the dialog box function within ABOUT2.C. When the dialog box function receives a WM_COMMAND message for one of the radio buttons, it turns on the check mark for that button and turns off the check marks for all the other buttons in the group.

You may recall from Chapter 7 that checking and unchecking a button requires that you send the child window control a BM_CHECK message. To turn on a button check, you use:

```
SendMessage (hWndCtrl, BM_SETCHECK, 1, 0L) ;
```

To turn off the check, you use:

```
SendMessage (hWndCtrl, BM_SETCHECK, 0, 0L);
```

The hWndCtrl parameter is the window handle of the child window button control.

But this method presents a little problem in the dialog box function, because you don't know the window handles of all radio buttons. You know only the one you're getting the message from. Fortunately, Windows provides you with a function to obtain the window handle of a dialog box control using the dialog box window handle and the control ID:

```
hWndCtrl = GetDlgItem (hDlg, nID);
```

(You can also obtain the ID value of a control from the window handle by using this function:

```
nID = GetWindowWord (hWndCtrl, GWW_ID) ;
```

but this is rarely necessary.)

You'll notice in the ABOUT2.H header file shown in Figure 11-3 that the ID values for the eight colors are sequential from IDD_BLACK to IDD_WHITE. This arrangement helps in processing the WM_COMMAND messages from the radio buttons. For a first attempt at checking and unchecking the radio buttons, you might try something like this in the dialog box function:

```
static short nColor :
     [other program lines]
case WM_COMMAND:
     switch (wParam)
          [other program lines]
          case IDD_BLACK:
          case IDD_RED:
          case IDD_GREEN:
          case IDD_YELLOW:
          case IDD_BLUE:
          case IDD_MAGENTA:
          case IDD_CYAN:
          case IDD_WHITE:
               nColor = wParam ;
               for (n = IDD_BLACK, n <= IDD_WHITE, n++)
                     SendMessage (GetDlgItem (hDlg, n),
                          BM_SETCHECK, n == wParam, OL) ;
                     break ;
          [other program lines]
```

This approach works satisfactorily. You've saved the new color value in *nColor*, and you've also set up a loop that cycles through all the ID values for the eight colors. You obtain the window handle of each of these eight radio button controls and use *SendMessage* to send each handle a BM_SETCHECK message. The *wParam* value of this message is set to 1 only for the button that sent the WM_COMMAND message to the dialog box window function.

The first shortcut is the special dialog box function SendDlgItemMessage:

```
SendDlgItemMessage (hDlg, nCtrlID, iMessage, wParam, 1Param);

It is equivalent to:

SendMessage (GetDlgItem (hDlg, nCtrlID), iMessage, wParam, 1Param);

Now the loop would look like this:

for (n = IDD_BLACK, n <= IDD_WHITE, n++)

SendDlgItemMessage (hDlg, n, BM_SETCHECK, n == wParam, OL);
```

That's a little better. But the real breakthrough comes when you discover the CheckRadioButton function:

```
CheckRadioButton (hDlg, nIDFirst, nIDLast, nIDCheck);
```

This function turns off the checks on all radio button controls with IDs from *nIDFirst* to *nIDLast* except for the radio button with an ID of *nIDCheck*, which is checked. The IDs must be sequential. So we can get rid of the loop entirely and use:

```
CheckRadioButton (hDlg, IDD_BLACK, IDD_WHITE, wParam);
```

That's how it's done in the dialog box function in ABOUT2.

A similar shortcut function is provided for working with check boxes. If you create a CHECKBOX dialog window control, you can turn the check mark on and off using the function:

```
CheckDlgButton (hDlg, nIDCheckbox, wCheck) ;
```

If wCheck is set to 1, the button is checked; if it's set to 0, the button is unchecked. You can obtain the status of a check box in a dialog box using:

```
wCheck = IsDlgButtonChecked (hDlg, nIDCheckbox);
```

You can either retain the current status of the check mark as a static variable within the dialog box function, or you can do something like this to toggle the button on a WM_COMMAND message:

```
CheckDlgButton (hDlg, nIDCheckbox,
!IsDlgButtonChecked (hDlg, nIDCheckbox));
```

If you define a BS_AUTOCHECKBOX control, then you don't need to process the WM_COMMAND message at all. You can simply obtain the current status of the button using IsDlgButtonChecked before terminating the dialog box.

The OK and Cancel Buttons

ABOUT2 has two push buttons, labeled OK and Cancel. In the dialog box template in ABOUT2.RC, the OK button has an ID of IDOK (defined in WINDOWS.H as 1) and the Cancel button an ID of IDCANCEL (defined in WINDOWS.H as 2). The OK button is the default:

```
DEFPUSHBUTTON "OK" IDOK, 20, 168, 40, 14, WS_GROUP
PUSHBUTTON "Cancel" IDCANCEL, 80, 168, 40, 14, WS_GROUP
```

This arrangement is normal for OK and Cancel buttons in dialog boxes; having the OK button as the default helps out with the keyboard interface. Here's how: Normally, you would end the dialog box by clicking one of these buttons with the mouse or pressing the Spacebar when the desired button has the input focus. However, the dialog box window function also generates a WM_COMMAND message when the user presses Enter, regardless of which control has the input focus. The value of wParam is set to the ID value of the default push button in the dialog box unless another push button has the input focus. In that case, wParam is set to the ID of the push button with the input focus. If no push button in the dialog box is a default push button, then Windows sends the dialog box function a WM_COMMAND message with wParam equal to IDOK. If the user presses the Esc key or Ctrl-Break, Windows sends the dialog box function a WM_COMMAND message with wParam equal to IDCANCEL. So you don't have to add separate keyboard logic to the dialog box function, because the keystrokes that normally terminate a dialog box are translated by Windows into WM_COMMAND messages for these two push buttons.

The AboutDlgProc function handles these two WM_COMMAND messages by calling EndDialog:

```
switch (wParam)
{
   case IDOK:
        nCurrentColor = nColor;
        nCurrentFigure = nFigure;
        EndDialog (hDlg, TRUE);
        break;

case IDCANCEL:
        EndDialog (hDlg, FALSE);
        break;
```

ABOUT2's window function uses the global variables *nCurrentColor* and *nCurrentFigure* when drawing the rectangle or ellipse in the program's client area. *AboutDlgProc* uses the static local variables *nColor* and *nFigure* when drawing the figure within the dialog box.

Notice the different values in the second parameter of EndDialog. This is the value that is passed back as the return value from the original DialogBox function in WndProc:

If DialogBox returns TRUE (nonzero), meaning that the OK button was pressed, then the WndProc client area needs to be updated with the new figure and color. These were saved in the global variables nCurrentColor and nCurrentFigure by AboutDlgProc when it received an WM_COMMAND message with wParam equal to IDOK. If DialogBox returns FALSE, the main window continues to use the original settings of nCurrentColor and nCurrentFigure.

TRUE and FALSE are commonly used in *EndDialog* calls to signal to the main window function whether the user ended the dialog box with OK or Cancel. However, the parameter to *EndDialog* is actually an *int*, and *DialogBox* returns an *int*, so it's possible to return more information in this way than simply TRUE or FALSE.

Tab Stops and Groups

In Chapter 7 we used window subclassing to add a facility to COLORSCR that let us move from one scroll bar to another by pressing the Tab key. In a dialog box, window subclassing is unnecessary: Windows does all the logic for moving the input focus from one control to another. However, you have to help out by using the WS_TABSTOP and WS_GROUP window styles in the dialog box template. For all controls that you want to access using the Tab key, specify WS_TABSTOP in the window style. If you refer back to the table on page 427, you'll notice that the PUSHBUTTON, DEFPUSHBUTTON, CHECKBOX, and EDITTEXT controls all include WS_TABSTOP as a default. The static controls—LTEXT, CTEXT, RTEXT, and ICON—do

not have the WS_TABSTOP style. These controls should not get the input focus because they can't do anything with it. Unless you set the input focus to a specific control in a dialog box during processing of the WM_INITDIALOG message and return FALSE from the message, Windows sets the input focus to the first control in the dialog box that has the WS_TABSTOP style.

The second keyboard interface that Windows adds to a dialog box involves the cursor movement keys. This interface is of particular importance with radio buttons. After you use the Tab key to move to the currently checked radio button within a group, you need to use the cursor movement keys to change the input focus from that radio button to other radio buttons within the group. You accomplish this by using the WS_GROUP window style. For a particular series of controls in the dialog box template, Windows will use the cursor movement keys to shift the input focus from the first control that has the WS_GROUP style up to (but not including) the next control that has the WS_GROUP style. Windows will cycle from the last control in a dialog box to the first control if necessary to find the end of group.

By default, the controls LTEXT, CTEXT, RTEXT, and ICON include the WS_GROUP style, which conveniently marks the end of a group. You often have to add WS_GROUP styles to other types of controls.

Let's look at some examples. ABOUTI.RC contains this dialog box template:

```
AboutBox DIALOG 20, 20, 160, 80

STYLE WS_POPUP | WS_DLGFRAME

BEGIN

CTEXT "About1" -1, 0, 12, 160, 8

ICON "About1" -1, 8, 8, 0, 0

CTEXT "About Box Demo Program" -1, 0, 36, 160, 8

CTEXT "(C)Charles Petzold, 1987" -1, 0, 48, 160, 8

DEFPUSHBUTTON "OK" IDOK, 64, 60, 32, 14, WS_GROUP
```

The WS_GROUP style is included as a default in the ICON control and all the CTEXT controls but not in DEFPUSHBUTTON. It had to be explicitly added.

What if we leave it out? Well, nothing really bad happens, but the keyboard interface is not quite correct. The last CTEXT control has the WS_GROUP style by default, as does the first CTEXT control, which means that the last CTEXT control and the DEFPUSHBUTTON control are in a group. When the push button has the input focus, pressing a cursor movement key shifts the focus to the last CTEXT control; repeating the action shifts the focus back to the push button. Adding WS_GROUP to the DEFPUSHBUTTON control defines the push button as a group—a group that contains only the push button—so pressing a cursor movement key now has no effect.

In the dialog box template for ABOUT2, the use of WS_TABSTOP and WS_GROUP is a little more complex. First, to simplify the appearance of the template, an identifier is defined in ABOUT2.RC that combines WS_TABSTOP and WS_GROUP:

```
#define TABGRP (WS_TABSTOP | WS_GROUP)
```

The template looks like this:

```
AboutBox DIALOG 20, 20, 140, 188
 STYLE WS_POPUP | WS_DLGFRAME
 BEGIN
                                              12, 140,
                "About2"
                              -1,
      CTEXT
                                              8,
                "About 2"
                              -1,
                                          8,
                                                    0,
      ICON
               "About Box Demo Program" -1, 4, 36, 130,
                                                        8
      CTEXT
                    IDD_PAINT, 68, 54, 60,
                                                       60
      CTEXT
      GROUPBOX "&Color"
                                          4, 50,
                                                   54, 112
                                                       12
                              IDD_BLACK,
                                          8, 60, 40,
      RADIOBUTTON "&Black"
                                                           TARGRE
                                          8, 72,
                                                   40.
                                                       12
                              IDD_BLUE,
      RADIOBUTTON "Balue"
      RADIOBUTTON "&Green"
                             IDD_GREEN,
                                          8, 84, 40,
                                                       12
      RADIOBUTTON "Cyasn" IDD_CYAN,
                                          8, 96, 40,
                                                       12
                                          8, 108, 40,
                                                       12
      RADIOBUTTON "&Red"
                              IDD_RED,
      RADIOBUTTON "&Magenta"
                              IDD_MAGENTA, 8, 120,
                                                  40,
                                                       12
      RADIOBUTTON "&Yellow" IDD_YELLOW, 8, 132, 40,
                                                       12
                                          8, 144, 40, 12
      RADIOBUTTON "&White"
                              IDD_WHITE,
                "&Figure"
                                         68, 120,
                                                   60, 40 WS_GROUP
                              -1,
     GROUPBOX
                                                       12, TABGRP
                                         72, 134, 50,
      RADIOBUTTON "Rec&tangle"
                              IDD_RECT,
                                         72, 146, 50, 12
      RADIOBUTTON "&Ellipse"
                              IDD_ELL,
                                        20, 168, 40, 14, WS_GROUP
      DEFPUSHBUTTON "OK"
                              IDOK,
                              IDCANCEL, 80, 168, 40, 14, WS_GROUP
      PUSHBUTTON "Cancel"
 END
```

The four controls that have the WS_TABSTOP style are the first radio buttons of each group (explicitly included) and the two push buttons (by default). When you first invoke the dialog box, these are the four controls you can move among using the Tab key.

Within each group of radio buttons, you use the cursor movement keys to change the input focus and the check mark. For example, the first radio button of the Color group (Black) and the group box labeled Figure have the WS_GROUP style. This means that you can use the cursor movement keys to move the focus from the Black radio button up to (but not including) the Figure group box. Similarly, the first radio button of the Figure group (Rectangle) and DEFPUSHBUTTON have the WS_GROUP style, so you can use the cursor movement keys to move between the two radio buttons in this group: Rectangle and Ellipse. Both push buttons get a WS_GROUP style to prevent the cursor movement keys from doing anything when the push buttons have the input focus.

You'll notice when using ABOUT2 that the dialog box manager in Windows performs some magic in the two groups of radio buttons. As expected, the cursor movement keys within a group of radio buttons shift the input focus and send a WM_COMMAND message to the dialog box function. But when you change the checked radio button within the group, Windows also assigns the newly checked radio button the WS_TABSTOP style. The next time you tab to that group, Windows will set the input focus to the checked radio button.

An ampersand (&) causes the letter that follows to be underlined and adds another keyboard interface. You can move the input focus to any of the radio buttons by pressing the underlined letter. By pressing C (for the Color group box) or F (for the Figure group box), you can move the input focus to the currently checked radio button in that group.

Although programmers normally let the dialog box manager take care of all this, Windows includes two functions that let you search for the next or previous tab stop or group item. These functions are:

```
hWndCtrl = GetNextDlgTabItem (hDlg, hWndCtrl, bPrevious);
and:

hWndCtrl = GetNextDlgGroupItem (hDlg, hWndCtrl, bPrevious);
```

If bPrevious is TRUE, the functions return the previous tab stop or group item; if FALSE, they return the next tab stop or group item.

Painting on the Dialog Box

ABOUT2 also does something relatively unusual: It paints on the dialog box. Let's see how this works. Within the dialog box template in ABOUT2.RC, a blank text control is defined with a position and size for the area we want to paint:

```
CTEXT "" IDD_PAINT, 68, 54, 60, 60
```

This area is 15 characters wide and 7½ characters high. Because this control has no text, all that the window function for the "static" class does is erase the background when the child window control has to be repainted.

When the current color or figure selection changes or when the dialog box itself gets a WM_PAINT message, the dialog box function calls *PaintTheBlock*, which is a function in ABOUT2.C:

```
PaintTheBlock (hCtrlBlock, nColor, nFigure);
```

The window handle hCtrlBlock had been set during processing of the WM_INITDIALOG message:

```
hCtrlBlock = GetDlgItem (hDlg, IDD_PAINT);

Here's the PaintTheBlock function:

void PaintTheBlock (hCtrl, nColor, nFigure)
HWND hCtrl;
short nColor, nFigure;
(
InvalidateRect (hCtrl, NULL, TRUE);
UpdateWindow (hCtrl);
PaintWindow (hCtrl, nColor, nFigure);
```

This invalidates the child window control, updates it, and then calls another function in ABOUT2 called PaintWindow.

ABOUT 3

The PaintWindow function obtains a device context handle for hCtrl and draws the selected figure, filling it with a colored brush based on the selected color. The size of the child window control is obtained from GetClientRect. Although the dialog box template defines the size of the control in terms of characters, GetClientRect obtains the dimensions in pixels. You can also use the function MapDialogRect to convert the character coordinates in the dialog box to pixel coordinates in the client area.

We're not really painting the dialog box's client area—we're actually painting the client area of the child window control. Whenever the dialog box gets a WM_PAINT message, the child window control is invalidated and then updated to make it believe that its client area is now valid. We then paint on top of it.

Using Other Functions with Dialog Boxes

Most functions that you can use with child windows you can also use with controls in a dialog box. For instance, if you're feeling devious, you can use *MoveWindow* to move the controls around the dialog box and have the user chase them around with the mouse.

Sometimes you need to dynamically enable or disable certain controls in a dialog box, depending on the settings of other controls. This call:

```
EnableWindow (hWndCtrl, bEnable) ;
```

enables the control where bEnable is TRUE (nonzero) and disables it where bEnable is FALSE (0). When a control is disabled, it receives no keyboard or mouse input.

Defining Your Own Controls

Although Windows assumes much of the responsibility for maintaining the dialog box and child window controls, various methods let you slip some of your own code into this process. We've already seen a method that allows you to paint on the surface of a dialog box. You can also use window subclassing (discussed in Chapter 7) to alter the operation of child window controls.

You can also define your own child window controls and use them in a dialog box. For example, suppose you don't particularly care for the normal rectangular push buttons with rounded corners and would prefer to create elliptical push buttons. You can do this by registering a window class and using your own window function to process messages for your customized child window. You then specify this window class in a CONTROL statement in the dialog box template. The ABOUT3 program, shown in Figure 11-5, does exactly that.

```
about3.obj : about3.c
cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp about3.c
about3.res : about3.rc about3.ico
rc -r about3.rc
```

Figure 11-5. The ABOUT3 program

```
about3.exe : about3.obj about3.def about3.res
link4 about3, /align:16, /map, slibw, about3
rc about3.res
```

```
/* ABOUT3.C -- About Box Demo Program No. 3 */
#include <windows.h>
#define IDM ABOUT 1
long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG) ;
long FAR PASCAL EllipPushWndProc (HWND, unsigned, WORD, LONG) ;
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
     HANDLE hInstance, hPrevInstance;
                  lpszCmdLine;
     int
                  nCmdShow;
     static char szAppName [] = "About3" ;
                  msg;
     HWND
                   hWnd :
     WNDCLASS
                  wndclass ;
     if (!hPrevInstance)
           wndclass.style = CS_HREDRAW | CS_VREDRAW ;
wndclass.lpfnWndProc ;
wndclass.cbClsExtra = 0 ;
           wndclass.cbWndExtra = 0;
          wndclass.hInstance = hInstance;
wndclass.hIcon = LoadIcon (hInstance, szAppName);
wndclass.hCursor = LoadCursor (NULL, IDC_ARROW);
           wndclass.hbrBackground = GetStockObject (WHITE_BRUSH) ;
           wndclass.lpszMenuName = NULL ;
           wndclass.lpszClassName = szAppName ;
           if (!RegisterClass (&wndclass))
                return FALSE;
           wndclass.style
                                    = CS HREDRAW | CS VREDRAW ;
           wndclass.lpfnWndProc = EllipPushWndProc;
           wndclass.cbWndExtra = 0;
wndclass.bWndExtra = hInstance;
           wndclass.cbClsExtra = 0;
          wndclass.hInstance = hInstance = NULL;
           wndclass.hCor = NULL;
wndclass.hCursor = LoadCursor (NULL, IDC_ARROW);
           wndclass.hbrBackground = COLOR_WINDOW + 1 ;
           wndclass.lpszMenuName = NULL ;
           wndclass.lpszClassName = "EllipPush" ;
           if (!RegisterClass (&wndclass))
                return FALSE;
```

```
hWnd = CreateWindow (szAppName, "About Box Demo Program",
                         WS OVERLAPPEDWINDOW,
                         CW_USEDEFAULT, 0,
CW_USEDEFAULT, 0,
                         NULL, NULL, hInstance, NULL) ;
     ShowWindow (hWnd, nCmdShow) ;
    UpdateWindow (hWnd);
     while (GetMessage (&msg, NULL, 0, 0))
          TranslateMessage (&msg) ;
          DispatchMessage (&msg) ;
    return msg.wParam ;
BOOL FAR PASCAL AboutDlgProc (hDlg, iMessage, wParam, lParam)
    HWND
            hDlg ;
    unsigned iMessage ;
    WORD
            wParam ;
     LONG
             lParam ;
    switch (iMessage)
          case WM INITDIALOG:
              break ;
          case WM COMMAND:
               switch (wParam)
                    case IDOK:
                         EndDialog (hDlg, 0) ;
                         break ;
                    default:
                         return FALSE ;
               break ;
          default:
               return FALSE ;
     return TRUE ;
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
                hWnd;
     HWND
     unsigned
                    iMessage;
     WORD
                    wParam;
                    1Param;
     LONG
     static FARPROC lpfnAboutDlgProc ;
     static HWND hInstance ;
                   hMenu ;
     HMENU
     switch (iMessage)
          case WM CREATE:
               hInstance = ((LPCREATESTRUCT) 1Param) ->hInstance ;
               lpfnAboutDlqProc = MakeProcInstance (AboutDlqProc, hInstance) ;
```

```
hMenu = GetSystemMenu (hWnd, FALSE) ;
               ChangeMenu (hMenu, 0, NULL, 0, MF APPEND) ;
               ChangeMenu (hMenu, 0, "A&bout About3...", IDM ABOUT, MF APPEND);
               break ;
         case WM SYSCOMMAND:
               switch (wParam)
                    case IDM ABOUT:
                         DialogBox (hInstance, "AboutBox", hWnd,
                                        lpfnAboutDlgProc) ;
                         break :
               return DefWindowProc (hWnd, iMessage, wParam, lParam) ;
          case WM DESTROY :
               PostQuitMessage (0) ;
               break ;
          default :
               return DefWindowProc (hWnd, iMessage, wParam, 1Param) ;
     return OL ;
long FAR PASCAL EllipPushWndProc (hWnd, iMessage, wParam, 1Param)
    HWND
               hWnd;
     unsigned
                iMessage:
     WORD
                wParam;
     LONG
                1Param:
    char
                szText [40] ;
    HBRUSH
                hBrush ;
    HDC
                hDC ;
     PAINTSTRUCT ps ;
    RECT
                rect :
    switch (iMessage)
         case WM PAINT:
               GetClientRect (hWnd, &rect) ;
               GetWindowText (hWnd, szText, sizeof szText) ;
              hDC = BeginPaint (hWnd, &ps) ;
              hBrush = CreateSolidBrush (GetSysColor (COLOR_WINDOW)) ;
              hBrush = SelectObject (hDC, hBrush) ;
              SetBkColor (hDC, GetSysColor (COLOR_WINDOW)) ;
              SetTextColor (hDC, GetSysColor (COLOR WINDOWTEXT)) ;
              Ellipse (hDC, rect.left, rect.top, rect.right, rect.bottom) ;
              DrawText (hDC, szText, -1, &rect,
                              DT SINGLELINE | DT CENTER | DT VCENTER) ;
              DeleteObject (SelectObject (hDC, hBrush)) ;
              EndPaint (hWnd, &ps) ;
              break ;
```

ABOUT3 -- CO



```
NAME
DESCRIPTION
               'About Box Demo No. 3 (C) Charles Petzold, 1987'
              'WINSTUB.EXE'
STUB
CODE
              MOVEABLE
DATA
              MOVEABLE MULTIPLE
HEAPSIZE
              1024
STACKSIZE
              4096
EXPORTS
               WndProc
               AboutDlgProc
               EllipPushWndProc
```

The window class we'll be registering is called "EllipPush" ("elliptical push button"). Rather than use a DEFPUSHBUTTON statement in the dialog box template, we use a CONTROL statement that specifies this window class:

```
CONTROL "OK" IDOK, "EllipPush", TABGRP, 64, 60, 32, 14
```

The dialog box manager uses this window class in a *CreateWindow* call when creating the child window control in the dialog box.

The ABOUT3.C program registers the "EllipPush" window class in WinMain:

The window class specifies that the window function is *EllipPushWndProc*, which is also in ABOUT3.C.

The EllipPushWndProc window function processes only three messages: WM_PAINT, WM_KEYUP, and WM_LBUTTONUP. During the WM_PAINT message, it obtains the size of its window from GetClientRect and obtains the text that appears in the push button from GetWindowText. It uses the Windows functions Ellipse and DrawText to draw the ellipse and the text.

The processing of the WM_KEYUP and WM_LBUTTONUP messages is very simple:

The window function obtains the handle of its parent window (the dialog box) using *Get-Parent* and sends a WM_COMMAND message with *wParam* equal to the control's ID. The ID is obtained using *GetWindowWord*. The dialog box window function then passes this message on to the dialog box function within ABOUT3. The result is a customized push button, as shown in Figure 11-6. You can use this same method to create other customized controls for dialog boxes.




Figure 11-6. A customized push button created by ABOUT3

Is that all there is to it? Well, not really. EllipPushWndProc is a bare-bones version of the logic generally involved in maintaining a child window control. For instance, the button doesn't flash like normal push buttons. To invert the colors on the interior of the push button, the window function would have to process WM_KEYDOWN (from the Spacebar) and WM_LBUTTONDOWN messages. The window function should also capture the mouse on a WM_LBUTTONDOWN message and release the mouse capture (and return the button's interior color to normal) if the mouse is moved outside the child window's client area while the button is still depressed. Only if the button is released while the mouse is captured should the child window send a WM_COMMAND message back to its parent.

EllipPushWndProc also does not process WM_ENABLE messages. As mentioned above, a dialog box function can disable a window using the EnableWindow function. The child window would then display gray rather than black text to indicate that it has been disabled and cannot receive messages.

If the window function for a child window control needs to store data that are different for each created window, then it can do so by using a positive value of cbWndExtra in the window class structure. This reserves space in the internal window structure that can be accessed using SetWindowWord, SetWindowLong, GetWindowWord, and GetWindowLong.

THE MESSAGE BOX

Let's take a breather here. We've been looking at ways to customize dialog boxes. Now let's look at an alternative to dialog boxes, which is the message box. We began using message boxes way back in Chapter 6, but we haven't yet examined them in detail.

The message box is an appropriate and easy-to-use alternative to a dialog box when you need a simple response from the user. The general syntax is:

```
nItem = MessageBox (hWndParent, lpszText, lpszCaption, nType) ;
```

The message box has a caption (the character string *lpszCaption*), one or more lines of text (*lpszText*), one or more buttons, and (optionally) a predefined icon. One of the buttons is a default. The *nItem* value returned from *MessageBox* indicates the button that was pressed.

The hWndParent parameter is generally the handle to the window that creates the message box. The input focus will be set to this window when the message box is destroyed. If you don't have a window handle available or you don't want the input focus to go to one of your windows, you can use NULL for the handle. If you use a message box within a dialog box, use the dialog box window handle (which we've been calling hDlg) for this parameter.

The *lpszText* parameter is a long pointer to NULL-terminated text that appears in the body of the message box. Windows breaks this text into several lines if necessary. You can also include tab characters in the text, and you can define your own line breaks using carriage returns or linefeeds or both. The *lpszCaption* string is generally the name of the application.

The nType parameter is a collection of flags joined by the C bitwise OR operator. The first group of flags specifies the push buttons to appear at the bottom of the message box: MB_OK (the default), MB_OKCANCEL, MB_YESNO, MB_YESNOCANCEL, MB_RETRYCANCEL, and MB_ABORTRETRYIGNORE. As you can see, these flags allow for a maximum of three buttons. The second group of flags specifies which of the buttons is the default: MB_DEFBUTTON1 (the default), MB_DEFBUTTON2, and MB_DEFBUTTON3.

The third group of flags specifies an icon to appear in the message box: MB_ICONASTERISK, MB_ICONEXCLAMATION, MB_ICONHAND, and MB_ICONQUESTION. There is no default. If you omit one of these flags, the message box has no icon. The Application Style Guide recommends that you use the asterisk icon for a status message, the exclamation point for a reminder, the question mark for a warning of the consequences of an action, and the hand icon for a signal of serious problems.

The fourth set of flags governs whether the message box is application modal, in which case the user can switch to another application without ending the message box, or system modal, which requires the user to end the message box before doing anything else. The flags are MB_APPLMODAL (the default) and MB_SYSTEMMODAL. Finally, you can use a fifth flag: MB_NOFOCUS, which displays the message box but does not give it the input focus.

Depending on which button is pressed, the message box returns one of the following identifiers: IDOK, IDCANCEL, IDYES, IDNO, IDRETRY, and IDABORT.

A familiar message box is the one that the MS-DOS Executive displays when you choose Close from its system menu. The message box logic in the MS-DOS program probably looks something like this:

The Assertion Message Box

Although message boxes are customarily used to convey messages and ask questions in finished programs, they are also helpful in debugging. For instance, you may be familiar with the *assert* macro included in the ASSERT.H header file with the Microsoft C Compiler. This macro is used for testing various conditions during a program's execution. If the condition does not hold, the macro displays the current source code filename and line number and terminates the program. You can create a similar macro for Windows:

You can then make various assertions in your code. For instance, to be sure that the value of hWnd in a certain section of your program is never NULL, you can do this:

```
WinAssert (hWnd != NULL) ;
```

If hWnd happens to be NULL when this statement is executed, the message box will be displayed to alert you to the problem. A macro is used rather than a function, because the predefined identifiers __FILE__ and __LINE__ must equal the source code filename and

line number where the assertion failed. If you used a function, these identifiers would always be set to the filename and line number where the function was located.

Unlike assert, the WinAssert macro shown above doesn't terminate the program if the assertion fails. If you use a debugging terminal, you can use a different version of this macro shown below. When you select the Abort button, the FatalExit function is called to display a stack trace on the debugging terminal.

Once you're finished debugging the program, you can compile with the identifier NDEBUG, defined by using the compiler switch -D NDEBUG. The WinAssert macro will then be defined as nothing.

Popup Information

Another handy use of a message box during program development is simply to provide some information to you while the program is executing. It would be ideal if you could use a message box much as you use *printf* in C programs for MS-DOS, with a formatting string and a variable number of arguments. And in fact, you can create a function that lets you do this:

```
void OkMsgBox (szCaption, szFormat)
    char *szCaption, *szFormat;
{
    char szBuffer [256];
    char *pArguments;

    pArguments = (char *) &szFormat + sizeof szFormat;
    vsprintf (szBuffer, szFormat, pArguments);
    MessageBox (NULL, szBuffer, szCaption, MB_OK);
}
```

The *vsprintf* function is similar to *sprintf* except that it uses a pointer to a series of arguments (*pArguments*) rather than the arguments themselves. *OkMsgBox* sets *pArguments* to the arguments on the stack when *OkMsgBox* is called. The first parameter to *OkMsgBox* is the message box caption, the second parameter is a format string, and the third and subsequent parameters are values to be displayed. Let's say you want a message box to appear every time the window function gets a WM_SIZE message. Your code might look like this:

This displays the values of wParam and lParam within the message box.

WORKING WITH FILES: POPPAD REVISITED

When we added a menu to POPPAD in Chapter 10, several menu options were left unimplemented. We are now almost ready to add logic to POPPAD to open files, read them in, and save the edited files to disk.

Working with files in Windows is no great joy, partly because Windows provides few functions for file I/O. Instead, one way or another, you must use MS-DOS function calls. Although the standard dialog box template to open a file is fairly simple, the dialog box function itself is one of the most difficult you'll encounter. Before tackling that function, let's investigate methods of file I/O in Windows programs.

The OpenFile Function Call

Although Windows does not officially include functions to read from, write to, or close files, it does include a function to open a file:

```
hFile = OpenFile (lpszFileName, &of, wFunction) ;
```

OpenFile returns a -1 if an error is encountered. For most uses of OpenFile, a return value other than -1 will be an MS-DOS file handle that you can use to read from and write to the file.

The *lpszFileName* parameter is a long (or far) pointer to the filename. A disk drive and subdirectory are optional. The *wFunction* parameter tells Windows what to do with this file (open it, create it, delete it, and so forth). I'll describe this parameter in more detail shortly.

The &of parameter is a far pointer to a structure of type OFSTRUCT ("open file structure"). You don't need to set any of the fields of this structure before calling OpenFile: They are filled in by the first OpenFile function call you make and are then used in subsequent OpenFile calls for the same file. The OFSTRUCT fields are shown below:

Field	Data Type	Description	
cBytes	BYTE	Length of structure in bytes	
fFixedDisk	BYTE	Nonzero for fixed-disk file	
nErrCode	WORD	MS-DOS error code	
reserved [4]	BYTE	File date and time	
szPathName [120]	BYTE	Fully qualified pathname and filename	

If the *OpenFile* call is successful, the *szPathName* field is filled with the fully qualified filename, including the current disk drive and subdirectory path. Under current versions of MS-DOS, the 120 characters allowed for this name are 40 more than needed. A fully qualified filename has 2 bytes for the drive letter and colon, up to 64 bytes for the directory path starting with the initial backslash, another byte for the backslash following the path, up to 12 bytes for the filename (8-character name, period, and 3-character extension), and a terminating 0.

The contents of the reserved field in OFSTRUCT are undocumented; currently, the OpenFile function obtains the file date and time from MS-DOS Interrupt 21H Function 57H. The first two bytes contain the date; the second 2 bytes contain the time. The OpenFile function has three advantages over opening a file by other means:

- The IpszFileName parameter is assumed to contain characters from the ANSI character set. OpenFile does an AnsiToOem conversion on the name before trying to open the file. You would have to convert the filename yourself if you opened the file by other means.
- If the file is not found in the current directory, OpenFile searches for the file on all
 directories listed in the MS-DOS environment PATH string.
- Windows determines the fully qualified filename and inserts it in the szPathName field of the structure.

This last item is the most important feature of *OpenFile*. Generally, the *lpszFileName* parameter you pass to *OpenFile* when first opening or creating a file is only a filename. When you use *OpenFile* subsequently to open the same file, Windows uses the fully qualified *szPathName* field of the OFSTRUCT structure.

Here's why that's important: Although each program instance in Windows has a current disk drive and subdirectory associated with it, the *DlgDirList* function (which we'll use later in this chapter) can change the current drive and subdirectory associated with a program instance. Let's say you use some means other than *OpenFile* to obtain a filename (without a drive or directory path) located in the current directory and that you successfully open and close the file. The user then uses the dialog box to get a new file. In the process, the dialog box calls *DlgDirList* to change the current drive or subdirectory. The user then cancels the dialog box, and your program tries to open the original file again. It's gone! Well, it's not gone, but the current drive or subdirectory is different, so your program can't find the file. You avoid this problem by using *OpenFile*.

The wFunction parameter of the OpenFile call comprises one or more flags joined by the C bitwise OR operator. First, you use one of the following four flags to open an existing file or create a new file:

OF_READ Opens an existing file for reading only
OF_WRITE Opens an existing file for writing only
OF_READWRITE Opens an existing file for reading and writing

OF_CREATE Creates a new file, or opens an existing file and truncates the size of the file to 0

Following the *OpenFile* call, the file is open and ready for reading and writing. The value returned from *OpenFile* is the MS-DOS file handle (unless this value is -1, in which case the file could not be opened or created).

If you prefer that the file be closed following the *OpenFile* call, you can add the flag OF_EXIST. This flag is generally used with OF_READ, OF_WRITE, or OF_READWRITE to see if the specified file exists. You can also use this flag with OF_CREATE to create the file and immediately close it. The file can be reopened later. When you use OF_EXIST, the value

returned from *OpenFile* is -1 if the file does not exist or (when used with OF_CREATE) if the file could not be created. Any file handle returned from *OpenFile* with an OF_EXIST flag should be ignored, because the file has been closed.

With OF_READ, OF_WRITE, or OF_READWRITE, you can also use the flag OF_PROMPT. If Windows cannot find the file in the current directory or one of the directories in the MS-DOS environment PATH string, this flag causes Windows to display the infamous "Insert [filename] disk in drive A:" message box. Windows users appreciate this message box about as much as MS-DOS users like the "Abort, Retry, Ignore" message, so use this flag with discretion. Also keep in mind that the OF_PROMPT message box has only an OK button, which means that fixed-disk users must scrounge up a disk to put in drive A before proceeding. If you must use the OF_PROMPT flag, also use the OF_CANCEL flag, which adds a Cancel button to the message box. If the user selects Cancel, the OpenFile function returns -1.

That's it for the flags to open a file for the first time. The file is open when the *OpenFile* function returns, unless you've included the OF_EXIST flag (in which case the file has been closed) or *OpenFile* returns a -1 (in which case an error occurred). You can now read from or write to this file and then close it. How you perform these actions is discussed in the next section.

When you want to reopen the file, you use the OF_READ, OF_WRITE, OF_READWRITE, or OF_CREATE flag in combination with the OF_REOPEN flag. The OF_REOPEN flag causes Windows to use the szPathName field in the OFSTRUCT structure to obtain the original disk drive, subdirectory, and filename of the file. Even if the current drive or subdirectory has changed since the file was first opened, this flag ensures that Windows will use the same drive and subdirectory as in the first OpenFile call. If you use OF_REOPEN with OF_CREATE, the size of the file will be truncated to 0.

When you use the OF_READ flag to open a file for reading only, you can also use the OF_VERIFY flag. This flag causes Windows to use the *reserved* field in the OFSTRUCT structure to verify that the date and time of the file being reopened are the same as those stored during the original *OpenFile* call. This works only for files opened with OF_READ, because the value for the file date and time is updated when a write-only or read-write file is closed.

Also available are two *OpenFile* flags that do not open files. The OF_DELETE flag deletes a file. If the file cannot be found in the current subdirectory, *OpenFile* uses the MS-DOS environment PATH string to search for a file to delete. Perhaps you're feeling cruel, in which case you can use the OF_PROMPT flag with OF_DELETE so that Windows also gets the chance to delete the file on drive A. *OpenFile* returns -1 if no file was deleted. If the file has previously been opened with *OpenFile* and then closed, you can use OF_DELETE in combination with OF_REOPEN.

The OF_PARSE flag does not open a file or even check for a file's existence. This flag is used by itself to parse the filename and fill in the *szPathName* field of the OFSTRUCT structure. *OpenFile* returns a -1 if the filename is invalid—for instance, if it contains illegal characters.

The Methods of File I/O

The main rule of file I/O in Windows is this: Do not keep files open for long periods of time. More specifically, that means you should not keep a file open between messages. You should open or create a file, read it or write to it in several large gulps, and then close it—all in the course of processing a single message.

Windows does not officially include functions to read, write, or close files. You have three options, none of them entirely satisfactory.

Use normal C functions for file I/O. The file handle returned from OpenFile can be
used directly with the "low-level" file I/O functions. The most important of these
functions are open, read, Iseek, close, create, write, and tell. We used the read and
close functions in the HEAD program in Chapter 7.

The problem with these functions is that you can't use far pointers with them unless your program is compact model or large model. As you know, compact model and large model are not recommended for Windows programs because their data segments must be fixed in memory. If you want to read part of a file into a global memory segment, you must first read the file into a local memory block and then transfer it to the global-memory block.

You can also use the normal C buffered file I/O functions such as *fopen*, fread, fwrite, and fclose. The MS-DOS file handle returned from OpenFile can be converted to a structure of type FILE using fdopen. The buffered file I/O functions are of less value in Windows than in other environments, because you need to read and write in large chunks, and buffering doesn't help unless you're reading small parts of a file.

- Write your own assembly-language routines that use the MS-DOS Interrupt 21H
 Functions 3CH (create a file), 3DH (open a file), 3EH (close), 3FH (read), 40H
 (write), and 42H (*Iseek*). Believe it or not, this is the officially recommended
 method for doing file I/O in a Windows program. It is obviously not very difficult,
 but one tends to rebel at the idea that it is necessary to write assembly-language
 routines simply to do file I/O in a system that is otherwise as sophisticated as
 Windows.
- Use file I/O routines that are included in the KERNEL module of Windows and can be imported to your program using the normal SLIBW.LIB import library, but that are undocumented in the Windows manuals.

This third method actually turns out to be the easiest when the file must be read into or written from buffer areas accessible only with far pointers. (The normal C low-level file I/O calls are preferable when you can use near pointers.)

Although the file I/O functions in KERNEL are undocumented and can thus be removed from future versions of Windows, they are nonetheless widely used. Of the nine programs supplied with Windows that do file I/O (CALENDAR, CARDFILE, CONTROL, MSDOS, NOTEPAD,

PAINT, SPOOLER, TERMINAL, and WRITE), all but one (WRITE) use one or more of these undocumented file I/O functions. One of the basic rules of Windows programming is that when in doubt, you should imitate existing programs. This rule forces us to use these undocumented file I/O functions. So be it.

The Undocumented File I/O Functions

The function templates for the undocumented file I/O functions are listed in the header file WINUNDOC.H, shown in Figure 11-7. We'll use this header file in the POPPAD program shown later in this chapter and the CLIPFILE program in Chapter 17.

```
/* Declarations for KERNEL File I/O and String Functions */
int FAR PASCAL lopen (LPSTR, int);
int FAR PASCAL lclose (int);
int FAR PASCAL lcreat (LPSTR, int);
LONG FAR PASCAL llseek (int, long, int);
WORD FAR PASCAL lread (int, LPSTR, int);
WORD FAR PASCAL lwrite (int, LPSTR, int);
#define READ 0
#define WRITE 1
#define READ_WRITE 2

int FAR PASCAL lstrlen (LPSTR);
LPSTR FAR PASCAL lstrcat (LPSTR, LPSTR);
int FAR PASCAL lstrcat (LPSTR, LPSTR);
int FAR PASCAL lstrcamp (LPSTR, LPSTR);
```

Figure 11-7. The header file WINUNDOC.H

You'll probably use *OpenFile* to open and create files, but you can also use *_lopen* and *_lcreat*. The *_lopen* function uses MS-DOS Interrupt 21H Function 3DH. The syntax is:

```
hFile = _lopen (lpszPathName, iReadWrite) ;
```

The *lpszPathName* parameter is a filename with an optional drive and subdirectory path. The *iReadWrite* parameter should be set to one of the following identifiers in WINUNDOC.H:

Identifier	Value	Purpose
READ	0	Opens an existing file for reading only
WRITE	1	Opens an existing file for writing only
READWRITE	2	Opens an existing file for reading and writing

These identifiers' values are the same as for their counterparts OF_READ, OF_WRITE, and OF_READWRITE, used with *OpenFile*. These values are used directly in the MS-DOS Function 3DH. The *hFile* value returned from *_lopen* is an MS-DOS file handle if the file is opened or -1 if the file cannot be opened.

The _lcreat function uses MS-DOS function 3CH. It looks similar to the _lopen call:

```
hFile = _lcreat (lpszPathName, iAttribute) ;
```

However, the second parameter is an MS-DOS file attribute. Use 0 for a normal (nonhidden, nonsystem, read-write) file. If the file already exists, the size is truncated to 0 and opened; if it doesn't exist, it is created and opened. Like the *_lopen* call, *_lcreat* returns an MS-DOS file handle if the function is successful or -1 if an error occurs.

After an _lopen or _lcreat call, the file pointer is set initially to the beginning of the file. Normally, all reading and writing is sequential. The file pointer is updated after each read or write. However, you can use _llseek (MS-DOS Function 42H) to change the file pointer:

```
1Position = _llseek (hFile, 1Position, iMethod) ;
```

The iMethod parameter should be set to one of the following values:

Value	Purpose
0	Move the file pointer IPosition bytes from the beginning of the file
1	Move the file pointer IPosition bytes from the current position of the file
2	Move the file pointer IPosition bytes from the end of the file

The value of *lPosition* returned from _*llseek* is the new position of the file pointer if the function is successful or -IL if an error occurs.

If you want to open an existing file and add data to it, you call:

```
_llseek (hFile, OL, 2);
```

This moves the file pointer to the end of the file. You can also use __llseek to determine the size of a file. You might want to define a function called FileLength to do this:

FileLength saves the current position of the file pointer, moves the file pointer to the end of the file, and then restores the file pointer to its original position.

To write to a file, use:

```
wBytesWritten = _lwrite (hFile, lpBuffer, wBytes) ;
```

The *lpBuffer* parameter is a far pointer to the data you want to write to the file, and *wBytes* is the number of bytes to write. The file buffer cannot extend past the end of a segment. The *wBytesWritten* value returned from the function is the number of bytes actually written. This can be less than *wBytes* if not enough disk space is available to write the entire buffer. Normally, the MS-DOS Function 40H allows you to write up to 65,535 bytes to a file, but *_lwrite* returns -1 to signal an error, so you'll want to restrict yourself to 65,534 bytes or less.

The function to read from a file is similar:

```
wBytesRead = _lread (hFile, lpBuffer, wBytes) ;
```

The *lpBuffer* parameter is a far pointer to an area that receives the data read from the file and *wBytes* is the number of bytes to read. The *wBytesRead* value returned can be less than *wBytes* if the end of the file is encountered before *wBytes* are read. A –1 return value signals an error.

```
Finally, to close a file, use:
_lclose (hFile);
```

The Undocumented String Functions

A discussion of helpful functions in the Windows KERNEL module would be incomplete if it didn't include the string functions also declared in WINUNDOC.H. The *Istrlen*, *Istrcpy*, *Istrcat*, and *Istrcmp* functions are equivalent to the normal C string functions *strlen*, *strcpy*, *strcat*, and *strcmp* except that they use far pointers. These functions are useful for moving data between two global memory blocks or between a global memory block and a local memory block. They are coded in assembly language and are thus much faster than equivalent C code. The *Istrcmp* function is a "Windows version" of the *strcmp* function: It is case insensitive for both the normal ASCII character codes and the ANSI character codes, and it can accommodate strings with multibyte character codes.

Dialog Boxes for Open and Save

With these preliminaries out of the way, we are now ready to create dialog box templates and dialog box functions to assist our Windows programs in opening and saving files. The FILEDLG.C source code file, FILEDLG.H header file, and FILEDLG.DLG dialog box template file, shown in Figure 11-8, will be used in both the revised POPPAD program in this chapter and the CLIPFILE program in Chapter 17. You can use these routines (or similar ones) in your own programs.

```
/* FILEDLG.C -- Open and Close File Dialog Boxes */
finclude <windows.h>
finclude <string.h>
finclude "filedlg.h"

BOOL FAR PASCAL FileOpenDlgProc (HWND, unsigned, WORD, LONG);
BOOL FAR PASCAL FileSaveDlgProc (HWND, unsigned, WORD, LONG);

static char szDefExt [5];
static char szFileName [96];
static char szFileName [96];
static POFSTRUCT pof;
static WORD wFileAttr, wStatus;
```

Figure 11-8. The FILEDLG files for the file I/O dialog boxes

```
int DoFileOpenDlg (hInst, hWnd, szFileSpecIn, szDefExtIn, wFileAttrIn,
                                szFileNameOut, pofIn)
               hInst ;
     HWND
               hWnd ;
               *szFileSpecIn, *szDefExtIn, *szFileNameOut;
     char
     WORD
               wFileAttrIn ;
     POFSTRUCT pofin ;
     FARPROC lpfnFileOpenDlgProc ;
     int
               iReturn ;
     strcpy (szFileSpec, szFileSpecIn) ;
     strcpy (szDefExt, szDefExtIn) ;
     wFileAttr = wFileAttrIn ;
     pof = pofIn ;
     lpfnFileOpenDlgProc = MakeProcInstance (FileOpenDlgProc, hInst) ;
     iReturn = DialogBox (hInst, "FileOpen", hWnd, lpfnFileOpenDlgProc) ;
     FreeProcInstance (lpfnFileOpenDlgProc) ;
     strcpy (szFileNameOut, szFileName) ;
     return iReturn ;
int DoFileSaveDlg (hInst, hWnd, szFileSpecIn, szDefExtIn, pwStatusOut,
                                szFileNameOut, pofIn)
               hInst ;
     HANDLE
     HWND
               hWnd ;
     char
               *szFileSpecIn, *szDefExtIn, *szFileNameOut ;
     WORD
               *pwStatusOut ;
     POFSTRUCT pofin ;
     FARPROC lpfnFileSaveDlgProc ;
               iReturn ;
     strcpy (szFileSpec, szFileSpecIn) ;
     strcpy (szDefExt, szDefExtIn) ;
     pof = pofIn ;
     lpfnFileSaveDlgProc = MakeProcInstance (FileSaveDlgProc, hInst) ;
     iReturn = DialogBox (hInst, "FileSave", hWnd, lpfnFileSaveDlgProc) ;
     FreeProcInstance (lpfnFileSaveDlgProc) ;
     strcpy (szFileNameOut, szFileName) ;
     *pwStatusOut = wStatus ;
     return iReturn ;
BOOL FAR PASCAL FileOpenDlgProc (hDlg, iMessage, wParam, 1Param)
     HWND hDlg;
unsigned iMessage;
WORD
               wParam ;
     LONG
               lParam ;
            cLastChar ;
nEditLen ;
     char
     short
```

```
switch (iMessage)
   case WM INITDIALOG:
      SendDlgItemMessage (hDlg, IDD FNAME, EM LIMITTEXT, 80, OL) ;
      DlgDirList (hDlg, szFileSpec, IDD FLIST, IDD FPATH, wFileAttr) ;
      SetDlgItemText (hDlg, IDD FNAME, szFileSpec) ;
      return TRUE ;
   case WM COMMAND:
      switch (wParam)
         case IDD FLIST:
             switch (HIWORD (1Param))
                case LBN SELCHANGE:
                   if (DIgDirSelect (hDlg, szFileName, IDD_FLIST))
                       strcat (szFileName, szFileSpec) ;
                   SetDlgItemText (hDlg, IDD FNAME, szFileName) ;
                   break :
                case LBN DBLCLK:
                   if (DIgDirSelect (hDlg, szFileName, IDD FLIST))
                       strcat (szFileName, szFileSpec) ;
                       DigDirList (hDlg, szFileName, IDD FLIST, IDD FPATH,
                                                              wFileAttr) ;
                       SetDlgItemText (hDlg, IDD FNAME, szFileSpec) ;
                   else
                       SetDlgItemText (hDlg, IDD_FNAME, szFileName) ;
SendMessage (hDlg, WM_COMMAND, IDOK, OL) ;
                    break ;
             break ;
          case IDD FNAME:
             if (HIWORD (1Param) == EN CHANGE)
                EnableWindow (GetDlgItem (hDlg, IDOK),
(BOOL) SendMessage (LOWORD (1Param)
                                            WM GETTEXTLENGTH, 0, OL));
             break :
          case IDOK:
             GetDlgItemText (hDlg, IDD_FNAME, szFileName, 80) ;
             nEditLen = strlen (szFileName) ;
             cLastChar = *AnsiPrev (szFileName, szFileName + nEditLen) ;
              if (cLastChar == '\\' || cLastChar == ':')
                 strcat (szFileName, szFileSpec) ;
              if (strchr (szFileName, '*') || strchr (szFileName, '?'))
                 if (DlgDirList (hDlg, szFileName, IDD FLIST,
                                                 IDD FPATH, wFileAttr))
```

```
stropy (szFileSpec, szFileName) ;
                       SetDlgItemText (hDlg, IDD_FNAME, szFileSpec) ;
                    else
                       MessageBeep (0) ;
                    break ;
                 strcat (strcat (szFileName, "\\"), szFileSpec) ;
                 if (DlgDirList (hDlg, szFileName, IDD FLIST,
                                                   IDD FPATH, wFileAttr))
                    strcpy (szFileSpec, szFileName) ;
                    SetDlgItemText (hDlg, IDD FNAME, szFileSpec) ;
                   break ;
                 szFileName [nEditLen] = '\0';
                 if (-1 == OpenFile (szFileName, pof, OF_READ | OF_EXIST))
                    strcat (szFileName, szDefExt) ;
                    if (-1 == OpenFile (szFileName, pof, OF READ | OF EXIST))
                       MessageBeep (0) ;
                       break ;
                    strcpy (szFileName,
                          (PSTR) AnsiNext (strrchr (pof->szPathName, '\\')));
                 OemToAnsi (szFileName, szFileName) ;
EndDialog (hDlg, TRUE) ;
                 break ;
              case IDCANCEL:
                EndDialog (hDlg, FALSE) ;
                 break ;
              default:
                 return FALSE :
       default:
          return FALSE ;
    return TRUE ;
BOOL FAR PASCAL FileSaveDlgProc (hDlg, iMessage, wParam, 1Param)
    HWND
             hDlg ;
    unsigned iMessage ;
    WORD
             wParam ;
    LONG
             lParam ;
    switch (iMessage)
       case WM INITDIALOG:
           SendDlgItemMessage (hDlg, IDD FNAME, EM LIMITTEXT, 80, OL) ;
```

```
DlgDirList (hDlg, szFileSpec, 0, IDD FPATH, 0) ;
SetDlgItemText (hDlg, IDD_FNAME, szFileSpec) ;
      return TRUE ;
  case WM COMMAND:
      switch (wParam)
         case IDD FNAME:
            if (HTWORD (1Param) == EN CHANGE)
               EnableWindow (GetDlgItem (hDlg, IDOK),
                   (BOOL) SendMessage (LOWORD (1Param),
                                          WM GETTEXTLENGTH, 0, 0L));
            break :
         case IDOK:
            GetDlgItemText (hDlg, IDD_FNAME, szFileName, 80) ;
            if (-1 == OpenFile (szFileName, pof, OF PARSE))
               MessageBeep (0) ;
               break ;
            if (!strchr ((PSTR) AnsiNext
                                (strrchr (pof->szPathName, '\\')), '.'))
               strcat (szFileName, szDefExt) ;
            if (-1 != OpenFile (szFileName, pof, OF WRITE | OF EXIST))
                wStatus = 1 ;
            else if (-1 != OpenFile (szFileName, pof,
                                               OF CREATE | OF EXIST))
               wStatus = 0 ;
            else
               MessageBeep (0) ;
               break ;
                strcpy (szFileName,
                     (PSTR) AnsiNext (strrchr (pof->szPathName, '\\')));
            OemToAnsi (szFileName, szFileName) ;
            EndDialog (hDlg, TRUE) ;
            break ;
         case IDCANCEL:
            EndDialog (hDlg, FALSE) ;
            break ;
         default:
            return FALSE ;
   default:
      return FALSE ;
return TRUE :
```

Figure 11-8. Continued

```
static char *strchr (str, ch)
     char *str ;
     int ch ;
     while (*str)
          if (ch == *str)
              return str ;
          str = (PSTR) AnsiNext (str) ;
     return NULL ;
static char *strrchr (str, ch)
     char *str ;
     int ch ;
     char *strl = str + strlen (str) ;
     do
          if (ch == *strl)
               return strl
          strl = (PSTR) AnsiPrev (str, strl) ;
     while (strl > str) ;
     return NULL ;
```

```
#define IDD_FNAME 0x10
#define IDD_FPATH 0x11
#define IDD_FLIST 0x12
```

```
FileOpen DIALOG 10, 10, 148, 116

STYLE WS POPUP | WS_DLGFRAME

BEGIN

LITEXT "Open File &Name:", -1, 2, 4, 76, 10

EDITTEXT IDD_FNAME, 2, 18, 100, 12, ES_AUTOHSCROLL

LITEXT "&Files in", -1, 2, 40, 38, 10

LITEXT ", IDD_FPATH, 44, 40, 98, 12

LISTBOX IDD_FLIST, 2, 54, 70, 58, WS_TABSTOP

DEFFUSHBUTTON "&Open", IDOK, 88, 62, 50, 14, WS_GROUP

PUSHBUTTON "Cancel", IDCANCEL, 88, 86, 50, 14, WS_GROUP

END
```

Figure 11-8. Continued

```
FileSave DIALOG 10, 10, 180, 54

STYLE WS_POPUP | WS_DLGFRAME

BEGIN

LITEXT "Save File &Name As:", -1, 6, 4, 84, 12

LITEXT "", IDD_FPATH, 90, 4, 78, 12

EDITTEXT IDD_FNAME, 6, 20, 104, 12, ES_AUTOHSCROLL

DEFPUSHBUTTON "OK", IDOK, 124, 20, 50, 14, WS_GROUP

PUSHBUTTON "Cancel", IDCANCEL, 124, 36, 50, 14, WS_GROUP

END
```

FILEDIG.DIG contains two dialog box templates named "FileOpen" and "FileSave." When displayed, these look very much like the dialog boxes used in the programs that come with Windows, so the operation of the two dialog boxes will be familiar to Windows users. FileOpen contains Open and Cancel push buttons, and FileSave contains OK and Cancel push buttons. The static text field with an ID of IDD_FPATH is used to display the current disk drive and directory path. The edit field with the ID of IDD_FNAME allows a user to type in a filename. The FileOpen dialog box also contains a list box that displays all the files matching a particular file specification (we'll use "*.TXT" with POPPAD), all valid disk drive letters, and all child subdirectories of the current drive and directory.

The FILEDLG.C file contains two functions named *DoFileOpenDlg* and *DoFileSaveDlg* that a program can call to invoke the dialog boxes. These functions are responsible for copying input parameters to variables within FILEDLG.C, calling *DialogBox*, and returning information obtained from the dialog box function to the program that called the FILEDLG.C functions. The parameters to the *DoFileOpenDlg* and *DoFileSaveDlg* functions include a default file specification (*szFileSpecIn*), a default filename extension (*szDefExtIn*), and a pointer to a structure of type OFSTRUCT (*pofIn*). The *DoFileOpenDlgProc* also requires a file attribute (*wFileAttrIn*) to be used when listing files in the list box.

The DoFileOpenDlg and DoFileSaveDlg functions return a 1 if the user ends the dialog box with Open or OK, and 0 if the user ends with Cancel. If the user ends with Open or OK, the OFSTRUCT structure passed to the functions will contain the fully qualified filename of the selected file in the szPathName field. The filename only (without a drive or directory) is copied to the szFileNameOut character array. For DoFileSaveDlg, the pwStatusOut parameter points to a word that is set to 1 if the file exists and to 0 if it does not.

The actual dialog box functions are FileOpenDlgProc and FileSaveDlgProc. These are relatively complex because they must deal with the interaction between the list box and the edit control and with the checking that must be performed on filenames and subdirectories entered by the user. To help with these areas, the dialog box functions extensively use the Windows functions DlgDirList and DlgDirSelect.

The DIgDirList and DIgDirSelect Functions

You'll recall from working with list boxes in Chapter 7 that you can fill a list box with a list of files, subdirectories, and disk drives by sending the list box a message:

```
SendMessage (hWndList, LB_DIR, wAttr, (LONG) lpszFileSpec);
```

The wAttr parameter is an MS-DOS file attribute (with some additional bits to indicate the listing of subdirectories and disk drives), and lpszFileSpec is a far pointer to a filename specification such as "*.*".

Although this list box message is quite convenient, within a dialog box you can use an even more sophisticated function:

```
iStatus = DlgDirList (hDlg, lpszFileSpec, nIDList, nIDStatic, wAttr) ;
```

The *nIDList* parameter is the ID of the list box, and *nIDStatic* is the ID of a static text field. *DlgDirList* parses the string pointed to by *lpszFileSpec* to extract any disk drive or subdirectory information from it. It then changes the current disk drive or subdirectory using MS-DOS function calls.

DlgDirList sends an LB_DIR message to the list box indicated by nIDList to fill it with filenames meeting the file specification and the file attribute word. The current disk drive and subdirectory path are then displayed in the static text field whose ID is nIDStatic. When DlgDirList returns, the string pointed to by lpszFileSpec contains only the file specification without any drive or subdirectory. The function returns nonzero if it is successful and 0 otherwise. A 0 value usually indicates that the string pointed to by lpszFileSpec does not contain a valid drive or subdirectory.

For example, suppose that drive C has a directory named WINDOWS and that your dialog box function contains this code:

When DlgDirList returns, the current disk drive and subdirectory for the instance of the program will have been changed to C:\WINDOWS. The list box whose ID is IDD_FLIST will list files with the extension .TXT, all subdirectories of the directory WINDOWS, and all valid disk drives. The static text field whose ID is IDD_FPATH will display the text C:\WINDOWS. The szFileSpec string array will contain "*.TXT". If either the nIDList or nIDStatic parameter is 0, however, DlgDirList will assume that the list box or static text field does not exist.

Both FileOpenDlgProc and FileSaveDlgProc use DlgDirList while processing the WM_INITDIALOG message. (In FileSaveDlgProc, DlgDirList is called with the nIDList parameter set to 0 because the dialog box does not contain a list box.)

SetDlgItemText is used to set the text of the edit control to the text file specification:

```
SetDlgItemText (hDlg, IDD_FNAME, szFileSpec);
```

This function does the same thing as the SetWindowText function or the WM_SETTEXT message. You can use the companion function GetDlgItemText to obtain the contents of the edit control.

FileOpenDlgProc also uses DlgDirSelect extensively. This function returns the currently selected string from a list box:

```
bDirectory = DlgDirSelect (hDlg, lpszString, nIDList) ;
```

The nIDList parameter is the ID of the list box. The currently selected string is copied to the character array pointed to by *lpszString*. If the return value is TRUE (nonzero), meaning that the string is either a disk drive or subdirectory name, *DlgDirSelect* removes the hyphens and brackets that appear when disk drive letters and subdirectory names are displayed in a list box. The function appends a colon to disk drive letters and a backslash to subdirectory names when copying them to the *lpszString* array.

If DlgDirSelect returns a disk drive or directory, you can then append the default file specification ("*.TXT", for instance) to the string and use that as the lpszFileSpec parameter to DlgDirList. DlgDirList will then change the drive or directory and update the static text field. The file specification pointed to by lpszFileSpec on return from DlgDirList can then be transferred to the edit control. If DlgDirSelect returns FALSE (0), meaning that lpszString contains a filename from the dialog box, then this filename can be transferred to the edit field directly.

Getting Valid Filenames

The dialog box to open a file would be much simpler if it did not contain an edit control. The edit control forces the dialog box function into doing some filename parsing. Much of this logic occurs when <code>FileOpenDlgProc</code> processes the WM_COMMAND message with <code>wParam</code> equal to IDOK. (When the user double-clicks a list box filename, the dialog function transfers the name to the edit box and then generates a WM_COMMAND message with <code>wParam</code> equal to IDOK. This avoids repeating the parsing logic for a list box double-click message.)

The dialog box function uses *GetDlgItemText* to obtain the string in the edit control. The parsing logic begins with a check to determine if the last character in this string is a backslash or colon. If it is, the user is requesting that the drive or directory be changed, so the current file specification must be appended to the string the user entered. If the resultant filename string contains a global character (*or?), the dialog box function calls *DlgDirList* with the new specification, and the dialog box function exits to wait for the next message.

If the character string entered by the user neither terminates with a backslash or colon nor contains a global character, it could be either a directory name or a filename. FileOpenDlgProc appends a backslash and the current file specification to it. If DlgDirList doesn't report an error, processing of the message is over. Otherwise, the entered text string is probably a filename, in which case FileOpenDlgProc strips off the previously appended file specification and calls OpenFile. If OpenFile does not find the file, then the default extension is added, and OpenFile tries again. If either one of these OpenFile calls is successful in opening the file for reading, then the szPathName field of the OFSTRUCT structure is used to obtain the filename without any drive or subdirectory, and the dialog box is terminated. Otherwise, the dialog function beeps to indicate an error in the filename.

The FILEDLG.C file contains alternate *strchr* and *strrchr* functions that search for characters when parsing filename strings. These alternate functions use *AnsiNext* and *AnsiPrev* to allow multibyte characters in the filename strings.

The New Version of POPPAD

The new version of POPPAD that uses these two dialog boxes is shown in Figure 11-9.

Figure 11-9. The POPPAD program

```
MSG
           msq;
               hwnd ;
     HWND
     HANDLE
               hAccel ;
     WNDCLASS wndclass ;
     if (!hPrevInstance)
                                     = CS HREDRAW | CS VREDRAW ;
           wndclass.style
           wndclass.lpfnWndProc = WndProc;
           wndclass.cbClsExtra = 0;
wndclass.cbWndExtra = 0;
wndclass.hInstance = hInstance;
           wndclass.hInstance = hInstance;
wndclass.hIcon = LoadIcon (hInstance, szAppName);
wndclass.hCursor = LoadCursor (NULL, IDC_ARROW);
           wndclass.hbrBackground = GetStockObject (WHITE BRUSH) ;
           wndclass.lpszMenuName = szAppName ;
wndclass.lpszClassName = szAppName ;
           if (!RegisterClass (&wndclass))
                 return FALSE;
     hWnd = CreateWindow (szAppName, NULL,
                             WS OVERLAPPEDWINDOW,
CW_USEDEFAULT, 0,
                             GetSystemMetrics (SM_CXSCREEN) / 2,
                             GetSystemMetrics (SM CYSCREEN) / 2,
                             NULL, NULL, hInstance, lpszCmdLine) ;
     ShowWindow (hWnd, nCmdShow) ;
     UpdateWindow (hWnd);
     hAccel = LoadAccelerators (hInstance, szAppName) ;
     while (GetMessage (&msg, NULL, 0, 0))
            if (!TranslateAccelerator (hWnd, hAccel, &msg))
                 TranslateMessage (&msg) 7
                  DispatchMessage (&msg) ;
      return msg.wParam ;
BOOL FAR PASCAL AboutDlgProc (hDlg, iMessage, wParam, 1Param)
     HWND
               hDlg ;
     unsigned iMessage ;
     WORD
                wParam ;
     LONG
                lParam ;
     switch (iMessage)
           case WM INITDIALOG:
                 break :
           case WM COMMAND:
                 switch (wParam)
```

```
case IDOK:
                         EndDialog (hDlg, 0) ;
                        break :
                   default:
                        return FALSE :
              break :
         default:
              return FALSE ;
    return TRUE :
void DoCaption (hWnd, szFileName)
    HWND hWnd
    char *szFileName ;
    char szCaption [40] ;
    sprintf (szCaption, "%s - %s", szAppName,
              szFileName [0] ? szFileName : szUntitled) ;
     SetWindowText (hWnd, szCaption) ;
short AskAboutSave (hWnd, szFileName)
    HWND hWnd;
char *szFileName;
     char szBuffer [40] ;
    short nReturn ;
    sprintf (szBuffer, "Save current changes: %s",
              szFileName [0] ? szFileName : szUntitled) ;
    if (!SendMessage (hWnd, WM COMMAND, IDM SAVE, OL))
              return IDCANCEL ;
    return nReturn ;
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
               hWnd;
iMessage;
    HWND
    unsigned
    WORD
                   wParam;
    LONG
                   1Param;
    static BOOL bNeedSave = FALSE;
static char szRealFileName [16];
    static FARPROC lpfnAboutDlgProc ;
    static HWND hInst, hWndEdit; char szFileName [16];
    LONG
                  1Select :
    OFSTRUCT
                   of :
    WORD
                   wEnable ;
```

```
switch (iMessage)
     case WM CREATE:
          hInst = ((LPCREATESTRUCT) 1Param) ->hInstance ;
          lpfnAboutDlgProc = MakeProcInstance (AboutDlgProc, hInst) ;
          ES AUTOHSCROLL | ES AUTOVSCROLL,
                    0, 0, 0, 0, hWnd, EDITID, hInst, NULL) ;
          SendMessage (hWndEdit, EM LIMITTEXT, 32000, OL) ;
          if (lstrlen (((LPCREATESTRUCT) lParam) -> lpCreateParams))
                OpenFile (((LPCREATESTRUCT) 1Param)->1pCreateParams,
                                    &of, OF PARSE) ;
                strcpy (szFileName, (PSTR)
                          AnsiNext (strrchr (of.szPathName, '\\'))) ;
                if (ReadFile (hInst, hWnd, hWndEdit, &of,
                     szFileName, FALSE))
strcpy (szRealFileName, szFileName);
           DoCaption (hWnd, szRealFileName) ;
           break ;
     case WM SETFOCUS:
           SetFocus (hWndEdit) ;
           break :
           MoveWindow (hWndEdit, 0, 0, LOWORD (lParam),
HIWORD (lParam), TRUE) ;
           break ;
     case WM INITMENUPOPUP:
           if (1Param == 1)
                EnableMenuItem (wParam, IDM UNDO,
                     SendMessage (hWndEdit, EM CANUNDO, 0, 0L) ?
MF ENABLED : MF GRAYED) ;
                EnableMenuItem (wParam, IDM PASTE,
                     IsClipboardFormatAvailable (CF TEXT) ?
                          MF ENABLED : MF GRAYED) ;
                1Select = SendMessage (hWndEdit, EM GETSEL, 0, 0L) :
                if (HIWORD (1Select) == LOWORD (1Select))
                     wEnable = MF GRAYED ;
                else
                     wEnable = MF_ENABLED ;
                EnableMenuItem (wParam, IDM CUT,
                                                    wEnable) ;
                EnableMenuItem (wParam, IDM_COPY, wEnable) ;
                EnableMenuItem (wParam, IDM_CLEAR, wEnable) ;
           break ;
```

```
case WM COMMAND :
     if (LOWORD (1Param) && wParam == EDITID)
           switch (HIWORD (1Param))
                case EN UPDATE:
                      bNeedSave = TRUE ;
                      break ;
                 case EN ERRSPACE:
                      MessageBox (hWnd, "Edit control out of space.",
                                 szAppName, MB_OK | MB_ICONHAND) ;
                      break ;
           break ;
     switch (wParam)
           case IDM NEW:
                if (bNeedSave && IDCANCEL ==
                           AskAboutSave (hWnd, szRealFileName))
                 SetWindowText (hWndEdit, "\0") ;
                szRealFileName [0] = '\0';
DoCaption (hWnd, szRealFileName);
                 bNeedSave = FALSE ;
                break ;
           case IDM OPEN:
                if (bNeedSave && IDCANCEL ==
                           AskAboutSave (hWnd, szRealFileName))
                      break ;
                 if (ReadFile (hInst, hWnd, hWndEdit, &of,
                                 szFileName, TRUE))
                      strcpy (szRealFileName, szFileName) ;
DoCaption (hWnd, szRealFileName) ;
                      bNeedSave = FALSE :
                break ;
           case IDM SAVE:
                 if (szRealFileName (0))
                      if (WriteFile (hInst, hWnd, hWndEdit, &of,
                                       szRealFileName, FALSE))
                           bNeedSave = FALSE ;
                            return 1 ;
                      break ;
                                            /* fall through */
           case IDM SAVEAS:
                if (WriteFile (hInst, hWnd, hWndEdit, &of, szFileName, TRUE))
```

```
strcpy (szRealFileName, szFileName) ;
                     DoCaption (hWnd, szFileName) ;
                     bNeedSave = FALSE ;
                     return 1 ;
               break ;
          case IDM PRINT:
               PrintFile (hInst, hWnd, hWndEdit, szRealFileName [0] ? szRealFileName :
                                           szUntitled) ;
               break :
          case IDM EXIT:
               SendMessage (hWnd, WM CLOSE, 0, 0L) ;
               break :
          case IDM ABOUT:
               DialogBox (hInst, "AboutBox", hWnd,
                          lpfnAboutDlgProc) ;
               break :
          case IDM UNDO:
                SendMessage (hWndEdit, WM UNDO, 0, 0L) ;
               break ;
          case IDM CUT:
                SendMessage (hWndEdit, WM CUT, 0, 0L) ;
               break ;
          case IDM COPY:
                SendMessage (hWndEdit, WM COPY, 0, 0L) ;
          case IDM PASTE:
                SendMessage (hWndEdit, WM PASTE, 0, OL) ;
                break ;
          case IDM CLEAR:
                SendMessage (hWndEdit, WM_CLEAR, 0, 0L) ;
                break :
          case IDM SELALL:
                SendMessage (hWndEdit, EM SETSEL, 0,
                               MAKELONG (0, 32767));
     break :
case WM CLOSE:
     if (!bNeedSave | IDCANCEL !=
               AskAboutSave (hWnd, szRealFileName))
          DestroyWindow (hWnd) ;
     break ;
case WM_QUERYENDSESSION:
   if (!bNeedSave || IDCANCEL !=
               AskAboutSave (hWnd, szRealFileName))
          return 1L ;
     break ;
```

```
/* POPPADF.C -- Popup Notepad File I/O */
#include <windows.h>
#include <stdio.h>
#include "winundoc.h"
                                             /* in FILEDLG.C */
int DoFileOpenDlg (HANDLE, WORD, char *, char *, WORD, char *, POFSTRUCT); int DoFileSaveDlg (HANDLE, WORD, char *, char *, WORD *, char *, POFSTRUCT);
extern char szAppName [];
                                            /* in POPPAD.C */
extern char szFileSpec [] ;
long FileLength (hFile)
     HANDLE hFile ;
             lCurrentPos = _llseek (hFile, OL, 1) ;
lFileLength = _llseek (hFile, OL, 2) ;
     long
     _llseek (hFile, lCurrentPos, 0) ;
     return lFileLength ;
void OkMessageBox (hWnd, szString, szFileName)
     HWND hWnd ;
     char *szString, *szFileName ;
     char szBuffer [40] ;
     sprintf (szBuffer, szString, szFileName) ;
     MessageBox (hWnd, szBuffer, szAppName, MB OK | MB ICONEXCLAMATION) ;
BOOL ReadFile (hInstance, hWnd, hWndEdit, pof, szFileName, bAskName)
     HANDLE hInstance, hWnd, hWndEdit;
     POFSTRUCT pof ;
     char
                *szFileName ;
     BOOL
               bAskName ;
     DWORD
                dwLength ;
     HANDLE
                hFile, hTextBuffer;
     LPSTR
               lpTextBuffer ;
     if (bAskName)
```

```
if (!DoFileOpenDlg (hInstance, hWnd, szFileSpec, szFileSpec + 1,
                                       0x4010, szFileName, pof))
              return FALSE ;
    if (-1 == (hFile = OpenFile (szFileName, pof, OF_READ | OF_REOPEN)))
         OkMessageBox (hWnd, "Cannot open file %s", szFileName) ;
         return FALSE ;
    if ((dwLength = FileLength (hFile)) >= 32000)
          lclose (hFile) ;
         OkMessageBox (hWnd, "File %s too large", szFileName) ;
         return FALSE ;
    if (NULL == (hTextBuffer = GlobalAlloc (GHND, (DWORD) dwLength + 1)))
          lclose (hFile) ;
         OkMessageBox (hWnd, "Cannot allocate memory for %s", szFileName) ;
         return FALSE ;
    lpTextBuffer = GlobalLock (hTextBuffer) ;
    lread (hFile, lpTextBuffer, (WORD) dwLength);
lclose (hFile);
    IpTextBuffer [(WORD) dwLength] = '\0';
    SetWindowText (hWndEdit, lpTextBuffer) ;
GlobalUnlock (hTextBuffer) ;
    GlobalFree (hTextBuffer) ;
    return TRUE ;
BOOL WriteFile (hInstance, hWnd, hWndEdit, pof, szFileName, bAskName)
    HANDLE hInstance, hWnd, hWndEdit;
     POFSTRUCT pof :
    char *szriichar baskName ;
              *szFileName ;
             szBuffer [40] ;
    char
              hFile, hTextBuffer ;
     HANDLE
             npTextBuffer ;
    NPSTR
    WORD
             wStatus, wLength ;
     if (bAskName)
          if (!DoFileSaveDlg (hInstance, hWnd, szFileSpec, szFileSpec + 1,
                                  &wStatus, szFileName, pof))
               return FALSE ;
          if (wStatus == 1)
               sprintf (szBuffer, "Replace existing %s", szFileName) ;
               return FALSE :
          )
```

```
else
    OpenFile (szFileName, pof, OF_PARSE) ;

if (-1 == (hFile = OpenFile (szFileName, pof, OF_CREATE | OF_REOPEN)))
    (
        OkMessageBox (hWnd, "Cannot create file %s", szFileName) ;
        return FALSE ;
    }

wLength = GetWindowTextLength (hWndEdit) ;
hTextBuffer = (HANDLE) SendMessage (hWndEdit, EM_GETHANDLE, 0, 0L) ;
npTextBuffer = LocalLock (hTextBuffer) ;

if (wLength != _lwrite (hFile, npTextBuffer, wLength))
    {
        lclose (hFile) ;
        OkMessageBox (hWnd, "Cannot write file %s to disk", szFileName) ;
        return FALSE ;
    }

lclose (hFile) ;
LocalUnlock (hTextBuffer) ;

return TRUE ;
}
```

```
/* POPPADP.C -- Popup Notepad Printing */
#include <windows.h>
extern char szappName [];
                                             /* in POPPAD.C */
BOOL FAR PASCAL PrintDlgProc (hDlg, iMessage, wParam, 1Param)
     HWND hDlg ;
     unsigned iMessage ;
     WORD
              wParam ;
               1Param :
     LONG
     return FALSE ;
BOOL FAR PASCAL AbortProc (hPrinterDC, nCode)
     HDC hPrinterDC :
     short nCode ;
     return FALSE ;
BOOL PrintFile (hInstance, hWnd, hWndEdit, szFileName)
HANDLE hInstance, hWnd, hWndEdit;
     char
                *szFileName ;
     MessageBox (hWnd, "Printing not yet implemented", szAppName, MB_OK | MB_ICONEXCLAMATION);
     return FALSE ;
```

```
#define IDM NEW 1
#define IDM OPEN 2
#define IDM_SAVE 3
#define IDM_SAVEAS 4


#define IDM_PRINT 5

#define IDM_EXIT 6
#define IDM_ABOUT 7

#define IDM_UNDO 8
#define IDM_CUT 9
#define IDM_COPY 10
#define IDM_COPY 10
#define IDM_PASTE 11
#define IDM_CLEAR 12
#define IDM_SELALL 13
```

```
#include "style.h"
#include "poppad.h"
#include "filedlg.h"
PopPad ICON "poppad.ico"
PopPad MENU
       BEGIN
               POPUP "&File"
                       BEGIN
                               MENUITEM "&New", IDM_NEW
MENUITEM "&Open...", IDM_OPEN
MENUITEM "&Save", IDM_SAVE
MENUITEM "Save &As...", IDM_SAVEAS
                               MENUITEM "&New",
                                MENUITEM SEPARATOR
                                MENUITEM "&Print ... ",
                                                                              IDM PRINT
                                MENUITEM SEPARATOR
                                MENUITEM "E&xit", IDM EXIT MENUITEM "A&bout PopPad...", IDM_ABOUT
                POPUP "&Edit"
                        BEGIN
                                MENUITEM "&Undo\tAlt+BkSp", IDM_UNDO
                                MENUITEM "Cu&t\tDel", IDM_CUT
MENUITEM "&Copy\tctrl+Ins", IDM_COPY
MENUITEM "&Faste\tShift+Ins", IDM_PASTE
MENUITEM "C&lear\tShift+Del", IDM_CLEAR
                                MENUITEM SEPARATOR
                                MENUITEM SEPARATOR
                                MENUITEM "&Select All", IDM SELALL
                        END
        END
PopPad ACCELERATORS
        BEGIN
                VK DELETE, IDM CUT, VIRTKEY
VK INSERT, IDM COPY, VIRTKEY, CONTROL
VK INSERT, IDM PASTE, VIRTKEY, SHIFT
VK DELETE, IDM_CLEAR, VIRTKEY, SHIFT
        END
```

Figure 11-9. Continued



```
NAME
              POPPAD
            'Popup Editor (C) Charles Petzold, 1987'
DESCRIPTION
STUB
              'WINSTUB.EXE'
CODE
               MOVEABLE
               MOVEABLE MULTIPLE
DATA
HEAPSIZE
               1024
STACKSIZE
               4096
               WndProc
EXPORTS
               AboutDlgProc
               FileOpenDlgProc
               FileSaveDlgProc
               PrintDlgProc
               AbortProc
```

Figure 11-9. Continued

poppad poppadf poppadp filedlg poppad /align:16 poppad /map mlibw poppad

As you'll recall, POPPAD uses a multiline edit control to do all the editing. The POP-PADEC file serves as an intermediary between the main POPPAD.C program and the functions in FILEDLG.C. The *ReadFile* function in POPPADEC calls *DoFileOpenDlgProc* and reads the file into a global memory block. *ReadFile* is responsible for reporting if the file is too large or if memory cannot be allocated for the file. When the file is read into a global memory block, it is transferred to the edit window using *SetWindowText*.

WriteFile calls DoFileSaveDlgProc to obtain the name of the file. This function is responsible for asking the user if it's acceptable to replace an existing file by that name. WriteFile obtains the handle to the edit control's buffer, locks it, and writes the file to the disk directly from that buffer.

This doesn't leave the POPPAD.C module much to do in the way of file I/O. But note these facts:

- In WinMain, the lpszCmdLine address is used as the last field of the
 CreateWindow call. This string might contain a filename that was entered as a
 parameter to POPPAD when the program was executed. During processing of the
 WM_CREATE message in WndProc, this filename is passed to ReadFile with the
 bAskName parameter set to FALSE so that ReadFile won't call DoFileOpenDlgProc.
- Much of the new logic in WndProc involves keeping track of changes to the text in the edit control. Whenever this text changes, the control sends an EN_UPDATE notification message to WndProc, which then sets bNeedSave to TRUE. When the user wants to open a new file or end the program, WndProc must check the bNeedSave variable. If it is TRUE, then the program calls AskAboutSave, which displays a message box that asks if the user wants to save the current changes. When a file is saved, bNeedSave is set to FALSE.
- POPPAD's caption displays the name of the currently loaded file. If no filename is available (for instance, when the program is first executed), then the *DoCaption* function in POPPAD causes the character string "(untitled)" to be displayed.

We are not yet finished with POPPAD. In Chapter 16 we'll add logic to let it print files, which will involve only a new version of the POPPADP.C file.

MODELESS DIALOG BOXES

At the beginning of this chapter, I explained that dialog boxes can be either "modal" or "modeless." So far we've been looking at modal dialog boxes, the more common of the two types. Modal dialog boxes (except for system modal dialog boxes) allow the user to switch between the dialog box and other programs. However, the user cannot switch to another window in the program until the modal dialog box is destroyed. Modeless dialog boxes allow the user to switch between the dialog box and the window that created it as well as between the dialog box and other programs. The modeless dialog box is thus more akin to the regular popup windows that your program might create.

Modeless dialog boxes are preferred when the user would find it convenient to keep the dialog box displayed for a while. For instance, Windows WRITE defines a total of 21 dialog boxes, of which 4 are modeless: those invoked by the menu options Find and Change on the Search menu and by Header and Footer on the Document menu. If the Find dialog box were modal, the user would have to choose Find; enter the string to be found; end the dialog box to return to the document; and then repeat the entire process to search for another occurrence of the same string. Allowing the user to switch between the document and the dialog box is much more convenient.

As you've seen, modal dialog boxes are created using <code>DialogBox</code>. The function returns only after the dialog box is destroyed. It returns the value specified in the second parameter of the <code>EndDialog</code> call that was used within the dialog box function to terminate the dialog box. Modeless dialog boxes are created using <code>CreateDialog</code>. This function takes the same parameters as <code>DialogBox</code>.

```
hDlgModeless = CreateDialog (hInstance, lpszTemplate, hWndParent, lpfnDialogProc);
```

The difference is that the *CreateDialog* function returns immediately with the window handle of the dialog box. Normally, you store this window handle in a global variable.

Although the use of the names *DialogBox* with modal dialog boxes and *CreateDialog* with modeless dialog boxes may seem arbitrary, you can remember which is which by keeping in mind that modeless dialog boxes are similar to normal windows. *CreateDialog* should remind you of the *CreateWindow* function, which creates normal windows.

Differences Between Modal and Modeless Dialog Boxes

Working with modeless dialog boxes is similar to working with modal dialog boxes, but there are several important differences:

 Modeless dialog boxes usually include a caption bar and a system menu box. The STYLE statement in the dialog box template for a modeless dialog box will look something like this:

STYLE WS POPUP | WS CAPTION | WS SYSMENU | WS VISIBLE

The caption bar and system menu allow the user to move the modeless dialog box to another area of the display using either the mouse or the keyboard. You don't normally provide a caption bar and system menu with a modal dialog box, because the user can't do anything in the underlying window anyway.

Note that the WS_VISIBLE style is included in our sample STYLE statement. If you
omit WS_VISIBLE, you must call ShowWindow after the CreateDialog call:

```
hDlgModeless = CreateDialog ( .... );
ShowWindow (hDlgModeless, SW_SHOW);
```

If you neither include WS_VISIBLE nor call *ShowWindow*, the modeless dialog box will not be displayed. In overlooking this fact, programmers who have mastered modal dialog boxes often experience difficulties when they first try to create a modeless dialog box.

Unlike messages to modal dialog boxes and message boxes, messages to modeless
dialog boxes come through your program's message queue. The message queue
must be altered to pass these messages to the dialog box window function. Here's
how you do it: When you use CreateDialog to create a modeless dialog box, you
should save the dialog box handle returned from the call in a global variable (for
instance, hDlgModeless). Change your message loop to look like this:

If the message is intended for the modeless dialog box, then *IsDialogMessage* sends it to the dialog box window function and returns TRUE (nonzero); otherwise, it returns FALSE (0). The *TranslateMessage* and *DispatchMessage* functions should be called only if *hDlgModeless* is 0 or if the message is not for the dialog box.

If you use keyboard accelerators for your program's window, then the message loop looks like this:

Because global variables are initialized to 0, hDlgModeless will be 0 until the dialog box is created, thus ensuring that IsDialogMessage is not called with an invalid window handle. You must take the same precaution when you destroy the modeless dialog box as explained below.

The hDlgModeless variable can also be used by other parts of the program as a test of the existence of the modeless dialog box. Other windows in the program can send messages to the dialog box while hDlgModeless is not equal to 0.

Use DestroyWindow rather than EndDialog to end a modeless dialog box. When
you call DestroyWindow, set the hDlgModeless global variable to 0.

The user customarily terminates a modeless dialog box by choosing Close from the system menu. Although the Close option is enabled, the dialog box window function within Windows does not process the WM_CLOSE message. You must do this yourself in the dialog box function:

```
case WM_CLOSE:
    DestroyWindow (hDlg) ;
    hDlgModeless =0 ;
    break ;
```

Note the difference between these two window handles: The hDlg parameter to DestroyWindow is the parameter passed to the dialog box function; hDlgModeless is the global variable returned from CreateDialog that you test within the message loop.

You can also allow a user to close a modeless dialog box using push buttons. Use the same logic as for the WM_CLOSE message. Any information that the dialog box must "return" to the window that created it can be stored in global variables.

The New COLORSCR Program

The COLORSCR program described in Chapter 7 created nine child windows to display three scroll bars and six text items. At that time, the program was one of the more complex we had developed. Converting COLORSCR to use a modeless dialog box makes the program—and particularly its *WndProc* function—almost ridiculously simple. The revised COLORSCR program is shown in Figure 11-10.

```
colorscr.obj : colorscr.c
    cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp colorscr.c

colorscr.res : colorscr.rc
    rc -r colorscr.rc

colorscr.exe : colorscr.obj colorscr.def colorscr.res
    link4 colorscr, /align:16, /map, slibw, colorscr
    rc colorscr.res
```

Figure 11-10. The COLORSCR program

```
/* COLORSCR.C -- Modeless Dialog Box Version */
#include <windows.h>
long FAR PASCAL WndProc
                           (HWND, unsigned, WORD, LONG) ;
BOOL FAR PASCAL ColorScrDlg (HWND, unsigned, WORD, LONG) ;
HWND hDlgModeless ;
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
    HANDLE hInstance, hPrevInstance;
     LPSTR
                 lpszCmdLine;
     int
                 nCmdShow;
     static char szAppName[] = "ColorScr" ;
    HWND
                hWnd ;
     MSG
                 msg;
    WNDCLASS
                wndclass ;
    if (hPrevInstance)
         return FALSE ;
     wndclass.style
                           = CS HREDRAW | CS VREDRAW ;
    wndclass.lpfnWndProc = WndProc ;
    wndclass.cbClsExtra = 0;
wndclass.cbWndExtra = 0;
    wndclass.hInstance = hInsta
wndclass.hIcon = NULL ;
                           = hInstance ;
     wndclass.hCursor
                            = LoadCursor (NULL, IDC ARROW) ;
    wndclass.hbrBackground = CreateSolidBrush (OL) ;
    wndclass.lpszMenuName = NULL ;
    wndclass.lpszClassName = szAppName ;
     if (!RegisterClass (&wndclass))
          return FALSE:
    hWnd = CreateWindow (szAppName, "Color Scroll",
                         WS OVERLAPPEDWINDOW | WS CLIPCHILDREN,
                         CW USEDEFAULT, 0,
                         CW USEDEFAULT, 0,
                         NULL, NULL, hInstance, NULL) ;
     ShowWindow (hWnd, nCmdShow) ;
    UpdateWindow (hWnd);
    hDlgModeless = CreateDialog (hInstance, "ColorScrDlg", hWnd,
                         MakeProcInstance (ColorScrDlg, hInstance)) ;
    while (GetMessage (&msg, NULL, 0, 0))
          if (hDlgModeless == 0 | | !IsDialogMessage (hDlgModeless, &msg))
               TranslateMessage (&msg) ;
               DispatchMessage (&msg) ;
    return msq.wParam ;
```

```
BOOL FAR PASCAL ColorScrDlg (hDlg, iMessage, wParam, 1Param)
    HWND hDlg;
     unsigned
                  iMessage ;
     WORD
                  wParam ;
     LONG
                 lParam ;
     static short color [3] ;
             hWndParent, hCtrl ;
     HWND
                  nCtrlID, nIndex ;
     switch (iMessage)
          case WM INITDIALOG:
               for (nCtrlID = 10 ; nCtrlID < 13 ; nCtrlID++)
                    hCtrl = GetDlgItem (hDlg, nCtrlID) ;
                    SetScrollRange (hCtrl, SB_CTL, 0, 255, FALSE) ;
                    SetScrollPos (hCtrl, SB_CTL, 0, FALSE) ;
               break ;
          case WM VSCROLL :
               hCtrl = HIWORD (1Param) ;
               nCtrlID = GetWindowWord (hCtrl, GWW ID) ;
               nIndex = nCtrlID - 10
               hWndParent = GetParent (hDlg) ;
               switch (wParam)
                    case SB PAGEDOWN :
                         color [nIndex] += 15; /* fall through */
                    case SB LINEDOWN :
                          color [nIndex] = min (255, color [nIndex] + 1) ;
                          break
                    case SB PAGEUP :
                                                        /* fall through */
                         color [nIndex] -= 15 ;
                    case SB LINEUP :
                          color [nIndex] = max (0, color [nIndex] - 1) ;
                          break
                    case SB TOP:
                         color [nIndex] = 0 ;
                          break
                     case SB BOTTOM :
                         color [nIndex] = 255 ;
                         break :
                    case SB_THUMBPOSITION : case SB_THUMBTRACK :
                         color [nIndex] = LOWORD (1Param) ;
                          break ;
                     default :
                          return FALSE ;
               SetScrollPos (hCtrl, SB_CTL, color [nIndex], TRUE);
SetDlgItemInt (hDlg, nCtrlID + 3, color [nIndex], FALSE);
               DeleteObject (GetClassWord (hWndParent, GCW_HBRBACKGROUND)) ;
               SetClassWord (hWndParent, GCW_HBRBACKGROUND,
                    CreateSolidBrush (RGB (color [0], color [1], color [2])));
               InvalidateRect (hWndParent, NULL, TRUE) ;
               break ;
```

```
default:
             return FALSE ;
     return TRUE ;
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
            hWnd;
     unsigned iMessage;
     WORD
             wParam;
     LONG
              lParam;
     switch (iMessage)
          case WM DESTROY:
               DeleteObject (GetClassWord (hWnd, GCW_HBRBACKGROUND)) ;
               PostQuitMessage (0) ;
               break ;
          default :
               return DefWindowProc (hWnd, iMessage, wParam, 1Param) ;
     return OL ;
```

```
NAME
             COLORSCR
DESCRIPTION
              'Color Scroll with Dialog Box (C) Charles Petzold, 1987'
STUB
              'WINSTUB.EXE'
CODE
              MOVEABLE
              MOVEABLE MULTIPLE
DATA
HEAPSIZE
             1024
STACKSIZE
              4096
EXPORTS
              WndProc
              ColorScrDlq
```

Although the original COLORSCR program displayed scroll bars that were based on the size of the window, the new version keeps them at a constant size within the modeless dialog box, as shown in Figure 11-11.




Figure 11-11. The COLORSCR display

The dialog box template in COLORSCR.RC uses CONTROL statements for all nine child windows in the dialog box. The modeless dialog box is created in COLORSCR's WinMain function following the ShowWindow call for the program's main window. Note that the window style for the main window includes WS_CLIPCHILDREN, which allows the program to repaint the main window without erasing the dialog box.

The dialog box window handle returned from CreateDialog is stored in the global variable hDlgModeless and tested during the message loop, as described above. In this program, however, it isn't really necessary to store the handle in a global variable or to test the value before calling IsDialogMessage. The message loop could have been written like this:

```
while (GetMessage (&msg, NULL, 0, 0))

if (!IsDialogMessage (hDlgModeless, &msg))

{
    TranslateMessage (&msg);
    DispatchMessage (&msg);
  }
}
return msg.wParam;
```

Because the dialog box is created before the program enters the message loop and the dialog box is not destroyed until the program terminates, the value of hDlgModeless will always be valid. I included the logic just in case you want to add some code to the dialog box window function to destroy the dialog box:

```
case WM_CLOSE:
    DestroyWindow (hDlg) ;
    hDlgModeless = 0 ;
    break ;
```

In the original COLORSCR program, SetWindowText set the values of the three numeric labels after converting the integers to text with itoa. The code looked like this:

```
SetWindowText (hChValue[n], itoa (color[n], szBuffer, 10));
```

The value of *n* was the ID number of the current scroll bar being processed, and *hChValue* was an array containing the window handles of the three static text child windows for the numeric values of the colors.

The new version uses SetDlgItemInt to set each text field of each child window to a number:

```
SetDlgItemInt (hDlg, nCtrlID + 3, color [nCtrlID], FALSE) ;
```

(Although SetDlgItemInt and its companion, GetDlgItemInt, are most often used with edit controls, they can also be used to set the text field of other controls, such as static text controls.) The nCtrIID variable is the ID number of the scroll bar; adding 3 to the number converts it to the ID for the corresponding numeric label. The third parameter is the color value. Normally, the fourth parameter would be set to TRUE to indicate that numbers greater than 32,767 should be displayed as negatives. For this program, however, the values range from 0 to 255, so the parameter has no effect.

In the process of converting COLORSCR from the original version to the new version, we passed more and more of the work to Windows. The earlier version called *CreateWindow* 10 times; the new version calls *CreateWindow* once and *CreateDialog* once. But if you think that we've reduced our *CreateWindow* calls to a minimum, get a load of this next program.

HEXCALC: Window or Dialog Box?

Perhaps the epitome of lazy programming is the HEXCALC program, shown in Figure 11-12. This program doesn't call *CreateWindow* at all, never processes WM_PAINT messages, never obtains a device context, and never processes mouse messages. Yet it manages to incorporate a 10-function hexadecimal calculator with a full keyboard and mouse interface in fewer than 160 lines of source code. The calculator is shown in Figure 11-13 (on page 491).

```
hexcalc.obj: hexcalc.c
cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp hexcalc.c

hexcalc.res : hexcalc.rc hexcalc.ico
rc -r hexcalc.rc

hexcalc.exe: hexcalc.obj hexcalc.def hexcalc.res
link4 hexcalc, /align:16, /map, slibw, hexcalc
rc hexcalc.res
```

```
/* HEXCALC.C -- Hexadecimal Calculator */
#include <windows.h>
#include <limits.h>
#include <stdlib.h>
#include <string.h>
#include <ctype.h>
long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG) ;
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
     HANDLE
              hInstance, hPrevInstance;
     LPSTR
                 lpszCmdLine;
     int
                 nCmdShow:
     static char szAppName [] = "HexCalc" ;
                 hWnd ;
     MSG
                 msq:
     WNDCLASS
                 wndclass :
     if (!hPrevInstance)
                                  = CS_HREDRAW | CS_VREDRAW;
          wndclass.style
          wndclass.lpfnWndProc = WndProc;
wndclass.cbClsExtra = 0;
          wndclass.cbWndExtra
                                   = 0 ;
          wndclass.hInstance
                                 = hInstance ;
          wndclass.hIcon
                                   = LoadIcon (hInstance, szAppName) ;
          wndclass.hCursor
                                   = LoadCursor (NULL, IDC_ARROW) ;
          wndclass.hbrBackground = COLOR WINDOW + 1 ;
wndclass.lpszMenuName = NULL ;
          wndclass.lpszClassName = szAppName ;
          if (!RegisterClass (&wndclass))
               return FALSE ;
     hWnd = CreateDialog (hInstance, szAppName, 0, NULL) :
     ShowWindow (hWnd, nCmdShow) ;
     while (GetMessage (&msg, NULL, 0, 0))
          TranslateMessage (&msg) ;
          DispatchMessage (&msg) ;
     return msg.wParam ;
     1
```

Figure 11-12. The HEXCALC program

```
void ShowNumber (hWnd, dwNumber)
     HWND hWnd ;
     DWORD dwNumber ;
     char szBuffer [20] ;
     SetDlgItemText (hWnd, VK ESCAPE, strupr (ltoa (dwNumber, szBuffer, 16))) ;
DWORD CalcIt (dwFirstNum, nOperation, dwNum)
     DWORD dwFirstNum, dwNum ;
     short noperation ;
     switch (nOperation)
           case '=' : return dwNum ;
          case '+' : return dwFirstNum + dwNum ;
          case '-' : return dwFirstNum - dwNum :
          case '*' : return dwFirstNum * dwNum ;
          case '&' : return dwFirstNum & dwNum ;
          case '|' : return dwFirstNum | dwNum ; case '' : return dwFirstNum | dwNum ;
          case '<' : return dwFirstNum << dwNum ;
          case '>' : return dwFirstNum >> dwNum ;
          case '/' : return dwNum ? dwFirstNum / dwNum : ULONG MAX ; case '%' : return dwNum ? dwFirstNum % dwNum : ULONG MAX ;
          default : return OL ;
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
                 hWnd;
     unsigned
                    iMessage;
     WORD
                    wParam;
     LONG
                    lParam;
     static BOOL bNewNumber = TRUE ;
     static DWORD dwNumber, dwFirstNum ;
     static short nOperation = '=' ;
                   hButton ;
     switch (iMessage)
           case WM KEYDOWN:
                                                  /* left arrow --> backspace */
                if (wParam != VK LEFT)
                      break ;
                wParam = VK BACK ;
                                                  /* fall through */
           case WM CHAR:
                if ((wParam = toupper (wParam)) == VK_RETURN)
                      wParam = '=' ;
                if (hButton = GetDlgItem (hWnd, wParam))
                      SendMessage (hButton, BM_SETSTATE, 1, 0L) ; SendMessage (hButton, BM_SETSTATE, 0, 0L) ;
                else
                      MessageBeep (0) ;
                      break ;
                      1
                                                  /* fall through */
```

```
case WM COMMAND:
          SetFocus (hWnd) ;
                ShowNumber (hWnd, dwNumber /= 16); /* backspace */
          if (wParam == VK_BACK)
                                                     /* escape */
          else if (wParam == VK_ESCAPE)
                ShowNumber (hWnd, dwNumber = OL) ;
                                                     /* hex digit */
          else if (isxdigit (wParam))
                if (bNewNumber)
                     dwFirstNum = dwNumber ;
                     dwNumber = OL ;
                bNewNumber = FALSE ;
                if (dwNumber <= ULONG MAX >> 4)
                     ShowNumber (hWnd, dwNumber = 16 * dwNumber + wParam - (isdigit (wParam) ? '0' : 'A' - 10));
                     MessageBeep (0) ;
          else
                                                      /* operation */
                if (!bNewNumber)
                     ShowNumber (hWnd, dwNumber =
                         CalcIt (dwFirstNum, nOperation, dwNumber));
                bNewNumber = TRUE ;
nOperation = wParam ;
          break ;
     case WM DESTROY:
          PostQuitMessage (0) ;
          break ;
     default :
          return DefWindowProc (hWnd, iMessage, wParam, 1Param) ;
return OL ;
```

```
#include <windows.h>

HexCalc ICON hexcalc.ico

HexCalc DIALOG 32768, 0, 102, 122

STYLE WS OVERLAPPED | WS_CAPTION | WS_SYSMENU | WS_MINIMIZEBOX CLASS "HexCalc"

CAPTION "Hex Calculator"

BEGIN

PUSHBUTTON "D", 68, 8, 24, 14, 14

PUSHBUTTON "A". 65, 8, 40, 14, 14
```

Figure 11-12. Continued

```
55, 8, 56, 14, 14
52, 8, 72, 14, 14
49, 8, 88, 14, 14
48, 8, 104, 14, 14
27, 26, 4, 50, 14
              PUSHBUTTON "7",
              PUSHBUTTON "4",
              PUSHBUTTON "1",
              PUSHBUTTON "O",
              PUSHBUTTON "O",
             PUSHBUTTON "O",
PUSHBUTTON "E",
PUSHBUTTON "B",
PUSHBUTTON "8",
                                                                          69, 26,
                                                                                                   24, 14, 14
                                                                         66, 26, 40, 14, 14
56, 26, 56, 14, 14
53, 26, 72, 14, 14
             PUSHBUTTON "5",
PUSHBUTTON "5",
                                                                   50, 26, 88, 14, 14
8, 26, 104, 32, 14
67, 44, 40, 14, 14
70, 44, 24, 14, 14
              PUSHBUTTON "Back",
              PUSHBUTTON "C",
PUSHBUTTON "F",
             PUSHBUTTON "F", 70, 44, 24, 14, 14
PUSHBUTTON "9", 57, 44, 56, 14, 14
PUSHBUTTON "6", 54, 44, 72, 14, 14
PUSHBUTTON "3", 51, 44, 88, 14, 14
PUSHBUTTON "+", 43, 62, 24, 14, 14
PUSHBUTTON "-", 45, 62, 40, 14, 14
PUSHBUTTON "*", 42, 62, 56, 14, 14
PUSHBUTTON "7", 47, 62, 72, 14, 14
PUSHBUTTON "8", 37, 62, 88, 14, 14
PUSHBUTTON "Equals", 61, 62, 104, 32, 14
PUSHBUTTON "85", 38, 80, 24, 14, 14
              PUSHBUTTON "&&", 38, 80, 24, 14, 14
              PUSHBUTTON "\", 124, 80, 40, 14, 14

PUSHBUTTON "\", 94, 80, 56, 14, 14

PUSHBUTTON "<", 60, 80, 72, 14, 14

PUSHBUTTON ">", 62, 80, 88, 14, 14
END
```

HEXCALC-CO



NAME DESCRIPTION STUB CODE DATA HEAPSIZE STACKSIZE EXPORTS HexCalc
'Hexadecimal Calculator (C) Charles Petzold 1987'
'WINSTUB.EXE'
MOVEABLE
MOVEABLE MULTIPLE
1024
4096
WndProc




Figure 11-13. The HEXCALC display

HEXCALC is a normal infix notation calculator that uses C notation for the operations. It works with unsigned 32-bit integers and does addition, subtraction, multiplication, division, and remainders; bitwise AND, OR, and exclusive OR operations; and left and right bit shifts. Division by 0 causes the result to be set to FFFFFFFF.

You can use either the mouse or keyboard with HEXCALC. You begin by "clicking in" or typing the first number (up to eight hexadecimal digits), then the operation, and then the second number. You can then show the result by clicking the Equals button or by pressing either the Equals key or Enter key. To correct your entries, you use the Back button or the Backspace or Left Arrow key. Click the "display" box or press the Esc key to clear the current entry.

What's so strange about HEXCALC is that the window displayed on the screen seems to be a hybrid of a normal overlapped window and a modeless dialog box. On the one hand, all the messages to HEXCALC are processed in a function called *WndProc* that appears to be a normal window function. The function returns a long, it processes the WM_DESTROY message, and it calls *DefWindowProc* just like a normal window function. On the other hand, the window is created in *WinMain* with a call to *CreateDialog* using a dialog box template from HEXCALC.RC. So is HEXCALC a normal overlapped window or a modeless dialog box?

The simple answer is that a dialog box is a window. Normally, Windows uses its own internal window function to process messages to a dialog box popup window. Windows then passes these messages to a dialog box function within the program that creates the dialog box. In HEXCALC we are forcing Windows to use the dialog box template to create a popup window, but we're processing messages to that window ourselves.

A closer look at HEXCALC.RC will reveal how this is done. The top of the dialog box template looks like this:

```
HexCalc DIALOG 32768, 0, 102, 122
STYLE WS_OVERLAPPED | WS_CAPTION | WS_SYSMENU | WS_MINIMIZEBOX CLASS "HexCalc"
CAPTION "Hex Calculator"
```

Notice the identifiers such as WS_OVERLAPPED and WS_MINIMIZEBOX, which we might use to create a normal window using a *CreateWindow* call. The CLASS statement is the crucial difference between this dialog box and the others we've created so far. When we omitted this statement in previous dialog box templates, Windows registered a window class for the dialog box and used its own window function to process the dialog box messages. The inclusion of a CLASS statement here tells Windows instead to send the messages someplace else—specifically, to the window function specified in the "HexCalc" window class.

The "HexCalc" window class is registered in the WinMain function of HEXCALC, just like a window class for a normal window. Then WinMain calls CreateDialog:

```
hWnd = CreateDialog (hInstance, szAppName, 0, NULL) ;
```

The second parameter (the string "HexCalc") is the name of the dialog box template. The third parameter, which is normally the window handle of the parent window, is set to 0 because the window has no parent. The last parameter, which is normally the address of the dialog function, isn't required because Windows will not be processing the messages and hence can't send them to a dialog function.

This CreateDialog call in conjunction with the dialog box template is effectively translated by Windows into a CreateWindow call that does the equivalent of this:

The xChar and yChar variables are the width and height of a system font character.

We reap an enormous benefit from letting Windows make this *CreateWindow* call: Windows will not stop at creating the 1 popup window but will also call *CreateWindow* for all 29 child window push button controls defined in the dialog box template. All these controls send WM_COMMAND messages to the window function of the parent window, which is none other than *WndProc*. This is an excellent technique for creating a window that must contain a collection of child windows. The PIFEDIT program included with Windows uses this technique to create an overlapped window that contains various static text, edit, and check box controls.

Creatively Using Control IDs

HEXCALC contains no header file with identifiers for all the ID numbers of the child window controls in the dialog box template. We can dispense with this file because the ID number for each of the push button controls is set to the ASCII code of the text that appears in the control. This means that <code>WndProc</code> can treat WM_COMMAND messages and WM_CHAR messages in much the same way. In each case, <code>wParam</code> is the ASCII code of the button.

Of course, a little massaging of the keyboard messages is necessary. WndProc traps WM_KEYDOWN messages to translate the Left Arrow key to a Backspace key. During processing of WM_CHAR messages, WndProc converts the character code to uppercase and the Enter key to the ASCII code for the Equals key.

The validity of a WM_CHAR message is checked by calling *GetDlgItem*. If the *GetDlgItem* function returns 0, then the keyboard character is not one of the ID numbers defined in the dialog box template. If the character is one of the IDs, however, the appropriate button is flashed by sending it a couple of BM_SETSTATE messages:

```
if (hButton = GetDlgItem (hWnd, wParam))
    (
    SendMessage (hButton, BM_SETSTATE, 1, 0L);
    SendMessage (hButton, BM_SETSTATE, 0, 0L);
}
```

This adds a nice touch to HEXCALC's keyboard interface, and with a minimum of effort.

When WndProc processes WM_COMMAND messages, it always sets the input focus to the parent window:

```
case WM_COMMAND:
SetFocus (hWnd);
```

Otherwise, the input focus would be shifted to one of the buttons whenever it was clicked with the mouse.

USING THE DLGBOX UTILITY

When you sit down to create a dialog box template, you'll discover that it's not quite as easy as it looks. Dialog boxes are an important part of your program, and the controls should be clearly and logically organized. But the process of placing and sizing these controls is mostly a matter of trial and error. You'll save yourself a lot of time and frustration by using the DLGBOX program included with the Windows Software Development Kit. This program allows you to use the mouse to place controls within a dialog box frame, to move and resize them, and to give them various attributes.

Before you start haphazardly designing your dialog box in DLGBOX, you should spend a little time in preparation. Although you can create a header file containing identifiers for the dialog box IDs, it's easier to create and edit the header file in a normal text editor. You should also have a general idea of how the controls will be arranged in the dialog box.

DLGBOX can read .RES files (the binary compiled resource file, not the ASCII .RC resource script) and header files. DLGBOX will prompt for the name of both a .RES file and a .H file when you choose Open from the File menu. Alternatively, you can read in a header file by using Open from the Include menu.

The names of all the dialog boxes currently stored in the .RES file are displayed when you choose View Dialog from the File menu. You can then pick one to edit. Thus, even if you begin by attempting to manually create a dialog box template in a .RC file and then give up in frustration, you can switch to DLGBOX to get all the coordinates and sizes correct. Remember to compile the resource script before running DLGBOX, however, as noted above, DLGBOX cannot read .RC files, only compiled .RES files. Alternatively, you can begin a new dialog box by choosing New Dialog from the Edit menu.

You can fill up the dialog box with controls by choosing from the Control menu, which lists 12 basic types of controls such as Check Box, Radio Button, and Push Button. You then click the mouse where you want the control to be placed. If the control uses text, it will initially show only the string "Text." You can select the control for editing merely by clicking on it. You can stretch or size it by hooking the little boxes on the sides or corners, and you can move it around by hooking the center.

The process of placing and sizing controls becomes a little easier if you first choose Grid from the Options menu and change both numbers to 2, thus forcing all dialog box coordinates and sizes to be in even numbers of units. Otherwise, you'll continually be wondering whether a particular control in a group is really one or two pixels off or whether you've just been looking at the screen too long. And try to create the controls in the order that you'll want them to appear in the dialog box template, because this in turn governs the order of tab stops and groups. Don't worry inordinately about getting it precisely right the first time through, however; as you'll see below, you can always change the order later.

One by one, select each control in the dialog box, choose Styles from the Edit menu, and enter the text of the control and the ID number in the Styles dialog box. If you've read in a header file, you can use the defined names rather than numbers for the IDs. You can also use the Styles dialog box to change the window style of the control. For instance, if you created a push button control by choosing Push Button from the Control menu, you can make it a default push button by checking the Def Push Button box.

The dialog box you're creating is initially shown with a simple frame. To add a caption bar and a system menu box, select the dialog box itself with the mouse, and then choose Styles from the Edit menu. As you've seen, controls in a Windows dialog box are organized by "groups" and "tab stops." You use the Tab key to move between controls marked as tab stops, and the arrow keys to move between controls within a group.

You can reorder the controls and select groups and tab stops through the Order Groups option of the Options menu, which displays a list of all the controls you've created. You can move a control by selecting it with the mouse and placing the horizontal black bar cursor in a new location. To define a group, you mark the first and last control of the group. You would also usually flag the first control of the group as a tab stop, but you can pick another control as the tab stop if you would like the cursor to jump to the middle of a group.

The best part of DLGBOX is that you can try out these tab stops and groups to see if they work right. Simply choose Test Mode from the Options menu. You can use both the keyboard and mouse to test how the input focus shifts between controls. (Don't expect radio buttons to work, however; they require some cooperation from a dialog box function.)

Once you're done, you can save the file. DLGBOX will actually save two files: a new .RES binary file containing the new dialog boxes and any changes to existing dialog boxes, and an ASCII file with the extension .DLG. The .DLG file contains the human-readable (well, almost readable) dialog box templates. All the controls will be expressed as CONTROL statements that include window style identifiers from WINDOWS.H. If you used names from a header file for the IDs, these names will be used in the .DLG file.

If you've changed the header file, you'll want to save that also. But beware: DLGBOX will strip comments from it. For that reason, it's better to maintain the header file outside DLGBOX and read it into DLGBOX, rather than to save it from DLGBOX.

DLGBOX can't read or alter the ASCII .RC resource script file; it can't read .DLG files, either. DLGBOX can read only the binary .RES file, which it saves in both the .RES and .DLG formats. If you create a dialog box in DLGBOX and save it as MYPROG.RES and MYPROG.DLG (for instance), you should later edit the MYPROG.RC resource script and include the line:

rcinclude myprog.dlg

This allows the RC.EXE resource compiler to add the contents of the MYPROG.DLG file to the other resources included in MYPROG.RC. Do not use #include for the .DLG file. The RC.EXE resource compiler interprets only #define statements in any file included with #include. And if you started out by creating a dialog box in the MYPROG.RC resource script file and then edited it in DLGBOX, you must also delete the original dialog box template from MYPROG.RC. Otherwise, you'll have two definitions for the same dialog box.

DLGBOX is not perfect, and there are a few quirks you should watch out for. If you want to delete a specific control from the dialog box, first select it and then choose Clear Control from the Edit menu. Avoid the Cut Dialog option, which deletes the whole dialog box and everything in it! (After you've picked yourself up from the floor, you can get everything back by choosing Restore Dialog from the Edit menu.) DLGBOX also doesn't let you do some of the more offbeat things we've done in this chapter, such as use our own class name for a control or for a dialog box itself.

If you edit a .DLG file with a text editor, and your text editor adds an ASCII end-of-file character to the .DLG file, the RC.EXE resource compiler might have a problem reading the

remainder of the resource script after processing the *rcinclude* statements. Putting the *rcinclude* statement at the end of the resource script (as I did in POPPAD.RC) usually circumvents this problem.

Finally, I have a confession to make. Although none of the dialog box templates in this chapter appear to be output from DLGBOX, I originally created all of them in DLGBOX. I later edited the .DLG files (and in many cases merged them into the .RC files) for the sole purpose of making them readable and presentable. DLGBOX is almost essential when creating dialog boxes. Don't waste your time doing it any other way.

SECTION IV

THE GRAPHICS DEVICE INTERFACE



Chapter 12

An Introduction to GDI

We have been using Graphics Device Interface (GDI) functions since Chapter 3, when we first started writing to the client area of our windows. Now it's time for a more formal coverage of the subject. This chapter discusses the preliminaries of GDI but stops short of drawing graphics, which is the subject of Chapter 13. Chapter 14 covers bitmaps and metafiles, which are means of storing graphical information; Chapter 15 discusses text and fonts; and Chapter 16 deals with printers and plotters.

THE GDI PHILOSOPHY

Graphics in Windows are handled largely by functions exported from the GDLEXE module (although some drawing functions actually have entry points in the USER.EXE file). The GDLEXE module calls routines in the various driver files—DISPLAY.DRV for the video display screen and possibly one or more other driver files that control printers or plotters. The driver files access the hardware of the video display or printer. Different video display adapters and printers require different driver files.

The GDI system is constructed so that Windows can determine from the driver what the driver can handle itself and what it needs assistance with. For instance, if the video hardware includes a graphics coprocessor that can draw ellipses, then GDI can take advantage of that; otherwise, the GDI module must itself calculate the points of the ellipse and pass the points to the driver.

Because a large number of different display devices can be attached to the IBM PC and compatibles, one of the primary goals of GDI is to support device-independent graphics on output devices such as video displays, printers, and plotters. Windows programs should be able to run without problems on any graphics output device that Windows supports. GDI accomplishes this goal by providing facilities to insulate your programs from the particular characteristics of different output devices. In this way it is like other device-independent graphics programming languages. But where Windows GDI is different is in its strong support of pixel-level manipulation.

The world of graphics output devices is divided into two broad groups: raster devices and vector devices. Most PC output devices are raster devices, which means that they represent images through the use of dots. This category includes video display adapters, dot-matrix printers, and laser printers. Vector devices, which draw images in lines, are generally limited to plotters.

Although most video display adapters and printers are raster devices, most graphics interface languages are based solely on vectors. This means that a program using one of these graphics languages is a level of abstraction away from the hardware. The output device is using pixels for a graphics representation, but the program is not talking to the interface in terms of pixels. While you can certainly use Windows GDI as a high-level vector drawing system, you can also use it for relatively low-level pixel manipulation.

In this respect, Windows GDI is to other graphics interface languages what C is to other programming languages. C is well known for its high degree of portability among different operating systems and environments. Yet C is also well known for allowing a programmer to perform low-level system functions that are often impossible in other high-level languages. Just as C is sometimes thought of as a "high-level assembly language," you can think of GDI as a high-level interface to the hardware of the graphics device.

As you've seen, by default Windows uses a coordinate system based on pixels. Most other graphics languages use a "virtual" coordinate system with horizontal and vertical axes that range (for instance) from 0 to 32,767. But although some other graphics languages don't let you use pixel coordinates, Windows GDI lets you use either system (as well as additional coordinate systems based on physical measurements). You can use a virtual coordinate system and keep your program distanced from the hardware, or you can use the device coordinate system and snuggle right up the hardware.

Some programmers think that once you start working in terms of pixels, you've abandoned device independence. We've already seen that this is not necessarily true. The trick is to use the pixels in a device-independent fashion. This requires that the graphics interface language provide facilities for a program to determine the hardware characteristics of the device and make appropriate adjustments. For instance, we've frequently used the pixel size of a standard system font character to space text on the screen. This approach allows our programs to adjust to different display adapters with different resolutions, text sizes, and aspect ratios. You'll see other methods for determining display sizes in this chapter.

Windows can run on either a monochrome display or a color display. If you choose, you can write a program without worrying very much about color. If you use color in your program and the program later runs on a monochrome display adapter, Windows will use a shade of gray to represent the color. However, you can also determine from your program how many colors are available on the particular display device and take best advantage of the hardware.

Of course, just as you can write C programs that have subtle portability problems when they run on other computers, you can also inadvertently let device dependencies creep into your Windows programs. That's part of the price of not being fully insulated from the hardware. We'll examine many of the device-dependent traps in the next few chapters.

You should also be aware of the limitations of Windows GDI. GDI is not (at this time) capable of doing everything you may want a graphics interface to do. Although you can move graphics objects around the display, GDI is generally a static display system with no real animation support. GDI provides no direct support for three-dimensional representations or for rotations of objects. For instance, when you draw an ellipse, the ellipse axes must be parallel to the horizontal and vertical coordinates. Although some graphics languages use floating-point numbers for virtual coordinates, Windows—for performance reasons—always uses 16-bit signed integers.

THE DEVICE CONTEXT

When you want to draw on a graphics output device (such as the screen or a printer), you must first obtain a handle to a device context (or DC). In giving your program this handle, Windows is giving you permission to use the device. You then include the handle as a parameter in the GDI functions to identify to Windows the device you want to draw on.

The device context contains many current "attributes" that determine how the GDI functions work on the device. These attributes allow the parameters to the GDI functions to include only starting coordinates or sizes and not everything else that Windows needs to display the object on the device. For example, when you call <code>TextOut</code>, you need specify in the function only the device context handle, the starting coordinates, the text, and the length of the text. You don't need to specify the font, the color of the text, the color of the background behind the text, and the intercharacter spacing, because these attributes are part of the device context. When you want to change one of these attributes, you call a function that changes the attribute in the device context. Subsequent <code>TextOut</code> calls use the changed attribute.

Getting the Handle to the Device Context

Windows provides several methods for obtaining a device context handle. When you obtain a device context handle while processing a message, you should release it (or delete it) before exiting the window function. After you release the handle, it is no longer valid.

The most common method for obtaining and then releasing a device context handle involves using the *BeginPaint* and *EndPaint* calls when processing the WM_PAINT message:

```
hDC = BeginPaint (hWnd, &ps);

lother program lines/

EndPaint (hWnd, &ps);
```

The variable ps is a structure of type PAINTSTRUCT. The hdc field of this structure is the handle to the device context that BeginPaint returns. The PAINTSTRUCT structure also contains a RECT (rectangle) structure named rcPaint that contains a clipping rectangle indicating the invalid region of the window's client area. With the device context handle obtained from BeginPaint, you can draw only within this rectangle. The EndPaint call validates this region.

Windows programs can also obtain a handle to a device context during processing of messages other than WM_PAINT:

This device context applies to the client area of the window whose handle is hWnd. The primary difference between the use of these calls and of the BeginPaint and EndPaint combination is that you can draw on your entire client area with the handle returned from GetDC. However, ReleaseDC doesn't validate any possibly invalid regions of the client area.

A Windows program can also obtain a handle to a device context that applies to the entire window and not only to the window's client area:

This device context includes the window caption bar, menu, scroll bars, and frame rather than only the client area. The <code>GetWindowDC</code> function is rarely used. If you want to experiment with it, you should trap WM_NCPAINT ("nonclient paint") messages, which prevents Windows from drawing the nonclient area of the window.

The BeginPaint, GetDC, and GetWindowDC calls obtain a device context associated with a particular window. You can also obtain a device context for the entire display by calling CreateDC:

In the BLOWUP program in Chapter 5 we used this function to obtain a device context handle that allowed us to write outside our window's client area:

```
hDC = CreateDC ("DISPLAY", NULL, NULL, NULL) ;
```

Writing outside your windows is generally impolite, but it's convenient for some unusual applications. (Although this fact is undocumented, you can also retrieve a device context for the entire screen by calling *GetDC* with a NULL parameter.)

In Chapter 16 we'll use the CreateDC function to obtain a handle to a printer device context:

```
hPrinterDC = CreateDC ("IBMGRX", "IBM Graphics", "LPT1:", NULL) ;
```

Of course, we won't include the names of specific printers in our programs. Programs can instead obtain this information from WIN.INI.

Sometimes you need only to obtain some information about a device context and not to do any drawing. In these cases, you can obtain a handle to an "information context" using CreateIC. The parameters are the same as for the CreateDC function:

You can't write to the device using this information context handle. We'll use this function in the DEVCAPS program shown later in this chapter to obtain an information context for the display and the printer.

In the GRAFMENU program in Chapter 10, we obtained a memory device context to manipulate some bitmaps. A memory device context is always created to be compatible with an existing device context:

```
hMemDC = CreateCompatibleDC (hDC);

[other program lines]

DeleteDC (hMemDC);
```

When you first obtain a memory device context, the display surface that it represents contains exactly 1 pixel. We'll work more with memory device contexts in Chapters 14 and 16.

In Chapter 14 we'll also work with "metafiles." A metafile is a collection of GDI calls encoded in binary form. You can create a metafile by obtaining a metafile device context:

During the time that the metafile device context is valid, any GDI calls you make using hMetaDC become part of the metafile. When you call CloseMetaFile, the device context handle becomes invalid. The function returns a handle to the metafile.

Getting Device Context Information

A device context usually refers to a physical display device such as a video display or a printer. Often, you need to obtain information about this device, including the size of the display (in terms of both pixels and physical dimensions) and its color capabilities. You can get this information by calling the <code>GetDeviceCaps</code> ("get device capabilities") function:

```
nValue = GetDeviceCaps (hDC, nIndex) ;
```

The nIndex parameter is 1 of 25 identifiers defined in WINDOWS.H. For instance, the nIndex HORZRES causes GetDeviceCaps to return the width of the device in pixels; a VERTRES parameter returns the height of the device in pixels. If hDC is a handle to a screen device context, that's the same information you can get from GetSystemMetrics. If hDC is a handle to a printer device context, then GetDeviceCaps returns the height and width of the printer display area in pixels.

You can also use GetDeviceCaps to determine the device's capabilities of processing various types of graphics. This is unimportant for the video display, but it becomes very important when working with printers. For instance, most plotters can't draw bitmapped images; GetDeviceCaps can tell you that.

The DEVCAPS Program

The DEVCAPS program, shown in Figure 12-1, displays all the information available from the GetDeviceCaps function for either the video display or the currently selected printer. If you change the current printer using the Windows CONTROL program, DEVCAPS updates the printer information.

```
/* DEVCAPS.C -- Displays Device Capability Information (Version 1) */
#include <windows.h>
#include <string.h>
#include "devcaps.h"
```

Figure 12-1. The DEVCAPS program

(continued)

Figure 12-1. Continued

```
/* in DEVCAPS2.C */
void DoBasicInfo (HDC, HDC, short, short) ;
void DoOtherInfo (HDC, HDC, short, short) ;
void DoBitCodedCaps (HDC, HDC, short, short, short);
long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG) ;
 int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
                                         hInstance, hPrevInstance ;
              HANDLE
                                               lpszCmdLine :
              LPSTR
              int
                                               nCmdShow ;
              static char szAppName [] = "DevCaps" ;
                                      hWnd ;
              HWND
              MSG
                                               msg ;
              WNDCLASS
                                              wndclass ;
              if (!hPrevInstance)
                           wndclass.style = CS_NREDRAW | C
                            wndclass.style
                                                                                           = CS HREDRAW | CS VREDRAW:
                            wndclass.hIcon = LoadIcon (NULL, IDI APPLICATIO
wndclass.hCursor = LoadCursor (NULL, IDC ARROW);
                            wndclass.hbrBackground = GetStockObject (WHITE BRUSH) ;
                            wndclass.lpszMenuName = szAppName ;
wndclass.lpszClassName = szAppName ;
                            if (!RegisterClass (&wndclass))
                                          return FALSE :
              hWnd = CreateWindow (szAppName, "Device Capabilities",
                                                                      WS OVERLAPPEDWINDOW,
                                                                      CW_USEDEFAULT, 0,
CW_USEDEFAULT, 0,
                                                                      NULL, NULL, hInstance, NULL) ;
              ShowWindow (hWnd, nCmdShow) ;
              UpdateWindow (hWnd) ;
              while (GetMessage (&msg, NULL, 0, 0))
                            TranslateMessage (&msg) ;
                            DispatchMessage (&msg) ;
              return msg.wParam ;
HDC GetPrinterIC ()
              char szPrinter [64] ;
              char *szDevice, *szDriver, *szOutput ;
              GetProfileString ("windows", "device", "", szPrinter, 64) ;
```

(continued)

Figure 12-1. Continued

```
return CreateIC (szDriver, szDevice, szOutput, NULL) ;
     return NULL ;
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
                  hWnd ;
     HWND
     unsigned
                   iMessage ;
     WORD
                   wParam :
     LONG
                  1Param ;
     static short xChar, yChar, nCurrentDevice = IDM SCREEN,
                                 nCurrentInfo = IDM BASIC ;
     HDC
                   hDC, hIC ;
     HMENU
                   hMenu ;
     PAINTSTRUCT
                   ps ;
     TEXTMETRIC
                   tm :
     switch (iMessage)
          case WM CREATE:
               hDC = GetDC (hWnd) ;
               GetTextMetrics (hDC, &tm) ;
                xChar = tm.tmAveCharWidth ;
                yChar = tm.tmHeight + tm.tmExternalLeading ;
                ReleaseDC (hWnd, hDC) ;
               break ;
          case WM COMMAND:
               hMenu = GetMenu (hWnd) ;
                switch (wParam)
                     case IDM SCREEN:
                     case IDM PRINTER:
                          CheckMenuItem (hMenu, nCurrentDevice, MF UNCHECKED) ;
                          nCurrentDevice = wParam ;
                          CheckMenuItem (hMenu, nCurrentDevice, MF_CHECKED) ;
                          InvalidateRect (hWnd, NULL, TRUE) ;
                          break ;
                     case IDM BASIC:
                     case IDM OTHER:
                     case IDM CURVE:
                     case IDM LINE:
                     case IDM POLY:
                     case IDM TEXT:
                          CheckMenuItem (hMenu, nCurrentInfo, MF UNCHECKED) ;
                          nCurrentInfo = wParam ;
                          CheckMenuItem (hMenu, nCurrentInfo, MF_CHECKED) ;
InvalidateRect (hWnd, NULL, TRUE) ;
                          break ;
                break ;
           case WM DEVMODECHANGE:
                InvalidateRect (hWnd, NULL, TRUE) ;
                break ;
           case WM PAINT:
                hDC = BeginPaint (hWnd, &ps) ;
```

Figure 12-1. Continued

```
if (nCurrentDevice == IDM SCREEN)
              hIC = CreateIC ("DISPLAY", NULL, NULL, NULL) ;
          else
              hIC = GetPrinterIC () ;
         if (hIC)
               switch (nCurrentInfo)
                    case IDM BASIC:
                         DoBasicInfo (hDC, hIC, xChar, yChar) ;
                         break ;
                    case IDM OTHER:
                         DoOtherInfo (hDC, hIC, xChar, yChar) ;
                         break ;
                    case IDM CURVE:
                    case IDM LINE:
                    case IDM_POLY:
                    case IDM TEXT:
                         DoBitCodedCaps (hDC, hIC, xChar, yChar,
                              nCurrentInfo - IDM CURVE) ;
                         break ;
               DeleteDC (hIC) ;
          EndPaint (hWnd, &ps) ;
          break ;
    case WM DESTROY:
          PostQuitMessage (0) ;
          break ;
     default:
          return DefWindowProc (hWnd, iMessage, wParam, 1Param) ;
return OL ;
```

```
/* DEVCAPS2.C -- Display routines for DEVCAPS */

#include <windows.h>
#include <string.h>
#include <stdio.h>

typedef struct

(
    short nMask ;
    char *szMask ;
    char *szDesc ;
    }
    BITS ;
```

(continued)

Figure 12-1. Continued

```
void DoBasicInfo (hDC, hIC, xChar, yChar)
      HDC hDC, hIC;
short xChar, yChar;
      static struct
            short nIndex ;
            char *szDesc :
            info [] =
            HORZSIZE,
                               "HORZSIZE
                                                Width in millimeters:",
                               "VERTSIZE
                                            Width in pixels:"
            VERTSIZE,
                                                Height in millimeters:",
            HORZRES,
                               "HORZRES
                                            Height in raster lines:",
            VERTRES,
                               "VERTRES
                               "BITSPIXEL Color bits per pixel:",
"PLANES Number of color planes:",
"NUMBRUSHES Number of device brushes:",
            BITSPIXEL,
            PLANES.
            NUMBRUSHES,
                               "NUMPENS
            NUMPENS,
                                               Number of device pens:",
                              "NUMMARKERS Number of device markers:",
"NUMFONTS Number of device fonts:",
"NUMCOLORS Number of device colors:",
            NUMMARKERS,
            NUMFONTS,
            NUMCOLORS,
                                                Number of device colors:"
            PDEVICESIZE, "PDEVICESIZE Size of device structure:",
            ASPECTX, "ASPECTX Relative width of pixel:",
ASPECTY, "ASPECTY Relative height of pixel:"
                             "ASPECTY Relative height of pixel:",
"ASPECTXY Relative diagonal of pixel:",
            ASPECTXY,
            LOGPIXELSX, "LOGPIXELSX Horizontal dots per inch:", LOGPIXELSY, "LOGPIXELSY Vertical dots per inch:"
      char szBuffer [80] ;
      short i, nLine ;
      for (i = 0 ; i < sizeof info / sizeof info [0] ; i++)
            TextOut (hDC, xChar, (i + 1) * yChar, szBuffer,
sprintf (szBuffer, "%-40s%8d", info[i].szDesc,
                         GetDeviceCaps (hIC, info[i].nIndex)));
void DoOtherInfo (hDC, hIC, xChar, yChar)
              hDC, hIC;
      short
                   xChar, yChar;
      static BITS clip [] =
                                                      "Can Clip To Rectangle:"
            CP RECTANGLE, "CP RECTANGLE",
      static PITS raster [] =
                            "RC_BITBLT",
"RC_BANDING",
"RC_SCALING",
            RC BITBLT,
                                                        "Capable of simple BitBlt:",
            RC BANDING,
                                                        "Requires banding support:",
            RC SCALING,
                                                       "Requires scaling support:",
            RC BITMAP64, "RC BITMAP64",
                                                       "Supports bitmaps >64K:"
      static char *szTech [] = ( "DT_PLOTTER (Vector plotter)",
                                        "DT_RASDISPLAY (Raster display)",
                                       "DT RASPRINTER (Raster printer)",
"DT RASCAMERA (Raster camera)",
"DT CHARSTREAM (Character-stream, PLP)",
                                        "DT_METAFILE (Metafile, VDM)",
                                        "DT DISPFILE (Display-file)" ) ;
```

Figure 12-1. Continued

```
char
               szBuffer [80] ;
    short
    "DRIVERVERSION:", GetDeviceCaps (hIC, DRIVERVERSION)));
    for (i = 0 ; i < sizeof clip / sizeof clip [0] ; i++)
         clip[i].szMask, clip[i].szDesc,
                  GetDeviceCaps (hIC, CLIPCAPS) & clip[i].nMask ?
                      "Yes" : "No")) ;
    raster[i].szMask, raster[i].szDesc,
                 GetDeviceCaps (hIC, RASTERCAPS) & raster[i].nMask ?
   "Yes" : "No")) ;
xChar, yChar, nType ;
    short
    static BITS curves [] =
                      "CC CIRCLES",
                                     "circles:",
        CC CIRCLES,
         CC PIE,
                      "CC PIE",
                                    "pie wedges:",
        CC_CHORD,
CC_ELLIPSES,
CC_WIDE,
                     "CC_CHORD",
"CC_ELLIPSES",
                                    "chord arcs:",
                                    "ellipses:",
                      "CC WIDE", "wide borders:",
                     "CC STYLED",
                                    "styled borders:"
         CC STYLED,
        CC_WIDESTYLED, "CC_WIDESTYLED", "wide and styled borders:", CC_INTERIORS, "CC_INTERIORS", "interiors:"
    static BITS lines [] =
                     "LC POLYLINE",
                                    "polyline:",
         LC POLYLINE,
                     "LC MARKER".
                                    "markers:",
         LC MARKER.
         LC POLYMARKER, "LC POLYMARKER", "polymarkers", LC WIDE, "LC WIDE", "wide lines:",
        LC WIDE, "LC WIDE", "wide lines:",
LC STYLED, "LC STYLED", "styled lines:",
LC WIDESTYLED, "LC WIDESTYLED", "wide and styled lines:",
LC INTERIORS, "LC INTERIORS", "interiors:"
```

(continued)

Figure 12-1. Continued

```
static BITS poly [] =
                           "PC POLYGON",
                                                 "alternate fill polygon:",
       PC POLYGON,
                           "PC_RECTANGLE",
"PC_TRAPEZOID",
       PC RECTANGLE,
PC TRAPEZOID,
                                                  "rectangle:"
                                                  "winding number fill polygon:",
       PC SCANLINE,
                           "PC SCANLINE",
                                                 "scanlines:",
                           "PC WIDE",
                                                  "wide borders:"
       PC WIDE,
       PC STYLED, "PC STYLED", "styled borders:",
PC WIDESTYLED, "PC WIDESTYLED", "wide and styled borders:",
       PC_INTERIORS, "PC_INTERIORS", "interiors:"
static BITS text [] =
      TC OP CHARACTER, "TC OP CHARACTER", "character output precision:",
TC OP STROKE, "TC OP STROKE", "stroke output precision:",
TC CP STROKE, "TC CP STROKE", "stroke clip precision:",
TC CR 90, "TC CP 90", "90 degree character rotation:
                                                       "90 degree character rotation:",
                             "TC CR ANY",
                                                      "any character rotation:",
       TC CR ANY,
      TC SF X YINDEP,
TC SA DOUBLE,
TC SA INTEGER,
                             "TC SF X YINDEP", "scaling independent of X and Y:"
"TC SA DOUBLE", "doubled character for scaling:",
"TC SA INTEGER", "integer multiples for scaling:",
       TC SA CONTIN,
                             "TC_SA_CONTIN", "any multiples for exact scaling:",
       TC EA DOUBLE,
                             "TC EA DOUBLE",
                                                    "double weight characters:",
                             "TC IA ABLE",
      TC IA ABLE,
                                                    "italicizing:",
                                                    "underlining:"
                             "TC SO ABLE",
       TC SO ABLE,
                                                    "strikeouts:",
                             "TC RA ABLE",
      TC RA ABLE,
                                                   "raster fonts:",
                                                   "vector fonts:"
      TC VA ABLE,
       ) :
static struct
       short nIndex :
       char *szTitle;
BITS (*pbits)[];
       short nSize ;
      bitinfo [] =
       CURVECAPS.
                       "CURVCAPS (Curve Capabilities)",
                       (BITS (*)[]) curves, sizeof curves / sizeof curves [0],
                       "LINECAPS (Line Capabilities)",
(BITS (*)[]) lines, sizeof lines / sizeof lines [0],
       LINECAPS,
       POLYGONALCAPS, "POLYGONALCAPS (Polygonal Capabilities)",
                       (BITS (*)[]) poly, sizeof poly / sizeof poly [0],
                       "TEXTCAPS (Text Capabilities)",
(BITS (*)[]) text, sizeof text / sizeof text [0]
       TEXTCAPS,
static char szBuffer [80] ;
               (*pbits) [] = bitinfo [nType].pbits ;
                nDevCaps = GetDeviceCaps (hIC, bitinfo [nType].nIndex) ;
short
                1 7
short
TextOut (hDC, xChar, yChar, bitinfo [nType].szTitle,
                    strlen (bitinfo [nType].szTitle)) ;
for (i = 0 ; i < bitinfo [nType].nSize ; i++)
       TextOut (hDC, xChar, (i + 3) * yChar, szBuffer, sprintf (szBuffer, "%-16s %s %-32s %3s",
                    (*pbits)[i].szMask, "Can do", (*pbits)[i].szDesc, nDevCaps & (*pbits)[i].nMask ? "Yes" : "No")) ;
```

Figure 12-1. Continued

```
#define IDM_SCREEN 1
#define IDM_PRINTER 2

#define IDM_BASIC 3
#define IDM_OTHER 4
#define IDM_CURVE 5
#define IDM_LINE 6
#define IDM_POLY 7
#define IDM_TEXT 8
```

```
#include "devcaps.h"
DevCaps MENU
    BEGIN
          POPUP "&Device"
               BEGIN
                    MENUITEM "&Screen"
                                                        IDM SCREEN, CHECKED
                    MENUITEM "&Printer",
                                                        IDM PRINTER
          POPUP "&Capabilities"
               BEGIN
                    MENUITEM "&Basic Information",
                                                        IDM BASIC, CHECKED
                    MENUITEM "&Other Information"
                                                        IDM OTHER
                    MENUITEM "&Curve Capabilities",
                                                     IDM_CURVE
                    MENUITEM "&Line Capabilities",
                                                        IDM_LINE
                    MENUITEM "&Polygonal Capabilities", IDM_POLY
                                                        IDM TEXT
                    MENUITEM "&Text Capabilities",
               END
     END
```

```
NAME DEVCAPS
DESCRIPTION 'Displays Device Capability Info (C) Charles Petzold, 1987'
STUB 'WINSTUB.EXE'
CODE MOVEABLE
DATA MOVEABLE MULTIPLE
HEAPSIZE 1024
STACKSIZE 4096
EXPORTS WndProc
```

The DEVCAPS Device menu lets you select either the screen or the printer. Because DEVCAPS needs only to obtain information about this device, it gets a handle to an information context using the *CreateIC* function rather than to a device context. Getting an information context handle for the video device is easy:

```
hIC = CreateIC ("DISPLAY", NULL, NULL, NULL) ;
```

However, an information context handle for the printer requires more complex code:

```
HDC GetPrinterIC ()
{
    char szPrinter [64] ;
    char *szDevice, *szDriver, *szOutput ;

GetProfileString ("windows", "device", "", szPrinter, 64) ;

if ((szDevice = strtok (szPrinter, "," )) &&
        (szDriver = strtok (NULL, ", ")) &&
        (szOutput = strtok (NULL, ", ")))

        return CreateIC (szDriver, szDevice, szOutput, NULL) ;
    return NULL;
}
```

The currently selected printer is listed in the [windows] section of the WIN.INI file in the following format:

```
device device name, driver filename, port
```

For an IBM Graphics printer connected to the LPT1 printer port, the WIN.INI line is:

```
device=IBM Graphics, IBMGRX, LPT1:
```

IBM Graphics is the name of the printer, and IBMGRX.DRV is the name of the driver file.

To get an information context (or device context) for the current printer, you must first obtain the character string following *device*= in WIN.INI by using the *GetProfileString* function. You must then parse this string into the three components: the device name, the driver filename, and the port. There are various ways of doing this. I happened to use the C *strtok* function, which is designed for parsing character strings separated by delimiters such as commas and spaces. Note that the device name itself can have embedded blanks,

If you'd like to use DEVCAPS to examine the device capabilities of other printers, you can add printer driver files to your Windows subdirectory using the CONTROL program and then choose each of these printers, one by one, as the current printer. Specify that the port the printer is connected to is "NONE." An advantage of *CreateIC* over *CreateDC* is that *CreateDC* returns a device context handle only if the printer is attached to a port, whereas *CreateIC* doesn't care whether the printer is attached. To get an idea of the range of devices you'll be dealing with, you might want to obtain the *GetDeviceCaps* information for a few different types of printers, such as a simple nongraphics printer (the "Generic/Text Only" printer), a sophisticated laser printer (the Apple LaserWriter Plus), and a plotter (the Hewlett-Packard 7550A). DEVCAPS intercepts the WM_DEVMODECHANGE message that CONTROL sends to all applications to signal that the current printer has been changed.

The Capabilities menu in DEVCAPS lets you display one of six screens that show the GetDeviceCaps information. Much of the DEVCAPS code is dedicated to formatting this information. When you choose the Basic Information option from the Capabilities menu, the most important information is displayed, including the size of the display, the number of pure colors it can display, and the organization of display memory into color planes and color bits per pixel. Figure 12-2 shows this basic information for an EGA using a monochrome driver; Figure 12-3 shows the information for an IBM Graphics printer.




Figure 12-2. The DEVCAPS display invoked by choosing Basic Information from the Capabilities menu when the specified device is an EGA using a monochrome driver




Figure 12-3. The DEVCAPS display invoked by choosing Basic Information from the Capabilities menu when the specified device is an IBM Graphics printer

When you choose the Other Information option from the Capabilities menu, the program displays the type of device (usually "Raster device," "Raster printer," or "Vector plotter") and gives some information that is crucial for using printers, as you'll discover when you come to Chapter 16. Figure 12-4 shows this display for an IBM Graphics printer. The RC_BITBLT identifier indicates that this printer can accept bitmaps; text-only printers and plotters cannot, however, which means that some GDI functions won't work on them. The RC_BANDING identifier indicates that this IBM printer, like many printers, requires "banding" support, which means that the GDI module must print to the printer in segments, each occupying a small section of the page. Again, we'll explore these issues further in Chapter 16.




Figure 12-4. The DEVCAPS display invoked by choosing Other Information from the Capabilities menu when the specified device is an IBM Graphics printer

The other menu options in DEVCAPS display curve, line, polygon, and text capabilities. The information displayed indicates the type of graphics and text manipulation that the device driver can handle. However, this information is much more important to Windows itself than to application programs—if the driver lacks one of these capabilities and a program demands it, then the GDI module must assume the task. For instance, you don't have to check to see if your printer is capable of drawing ellipses before you draw an ellipse.

The information you can obtain from *GetDeviceCaps* using the CURVECAPS, LINECAPS, POLYGONALCAPS, and TEXTCAPS parameters is encoded in bits in the return value. Although the Programmer's Reference doesn't indicate it, WINDOWS.H includes identifiers beginning with the letters CC, LC, PC, and TC to help you mask out the bits you want.

The Size of the Device

The most important information that your Windows program can obtain about the video device from *GetDeviceCaps* is the size of the display (in both millimeters and pixels) and the display's pixel aspect ratio. These dimensions can help in scaling images to be displayed. To give you some idea of what these numbers look like, the table below presents information from *GetDeviceCaps* for the IBM Color/Graphics Adapter (CGA), the Hercules Graphics Card, the IBM Enhanced Graphics Adapter (EGA), and the IBM-PS/2 Video Graphics Array (VGA):

GetDeviceCaps Index	IBM CGA	Hercules	IBM EGA	IBM VGA
HORZSIZE (width in mm)	240	225	240	240
VERTSIZE (height in mm)	180	145	175	180
HORZRES (pixel width)	640	720	640	640
VERTRES (pixel height)	200	348	350	480
ASPECTX (horizontal)	5	11	38	36
ASPECTY (vertical)	12	16	48	36
ASPECTXY (diagonal)	13	19	61	51
LOGPIXELSX (x pixels/inch)	96	96	96	96
LOGPIXELSY (y pixels/inch)	48	72	72	96

The HORZSIZE and VERTSIZE values are the width and height of the display area in millimeters. Of course, the Windows driver doesn't really know the size of the display you have attached to your video adapter. These dimensions are based on standard display sizes for the adapters.

The HORZRES and VERTRES values are the width and height of the display area in pixels. For a device context for a video display, these are the same values as those returned from GetSystemMetrics.

The ASPECTY, ASPECTY, and ASPECTXY values are the relative width, height, and diagonal size of each pixel. ASPECTXY equals the square root of the sum of ASPECTX squared and ASPECTY squared.

The LOGPIXELSX and LOGPIXELSY values are the number of pixels per a horizontal and a vertical "logical inch." A logical inch is not a real inch (25.4 mm), as you can easily determine by performing a few calculations using the HORZSIZE, VERTSIZE, HORZRES, and VERTRES values.

Before you go mad trying to reconcile some of the other numbers, let me point out that the Windows display drivers apparently contain some errors. The HORZSIZE and VERTSIZE values for an EGA should be 240 and 180; the monochrome display normally used with a Hercules Graphics Card is 200 by 150 mm. IBM's displays have always had a 4:3 aspect ratio, but I'll let that one go for the moment and assume that GetDeviceCaps is correct. If it is, the number:

GetDeviceCaps (HORZRES)

GetDeviceCaps (HORZSIZE)

GetDeviceCaps (ASPECTX)

should equal:

```
GetDeviceCaps (VERTRES)
GetDeviceCaps (VERTSIZE)

• GetDeviceCaps (ASPECTY)
```

This doesn't work for the EGA and the Hercules. I believe the ASPECTX number is in error for these adapters. Assuming that my HORZSIZE and VERTSIZE numbers are correct, ASPECTX should be 36 for the EGA and 12 for the Hercules.

After removing common multiples, this part of the table becomes much simpler:

GetDeviceCaps Index	IBM CGA	Hercules	IBM EGA	IBM VGA
ASPECTX (horizontal)	5	3	3	11
ASPECTY (vertical)	12	4	4	11
ASPECTXY (diagonal)	13	5	5	17

The EGA and Hercules aspect values are also now consistent with the LOGPIXELSX and LOGPIXELSY values. (However, the CGA aspect values are not.)

The LOGPIXELSX and LOGPIXELSY values require a little more explanation. You may have noticed that the WRITE program and some other Windows programs display a ruler that isn't quite right: If you measure the ruler as displayed on an EGA, you'll find that what it declares as 1 inch is really more like 1½ inches. These programs are using the LOGPIXELSX and LOGPIXELSY values for the ruler. If WRITE used actual physical dimensions, normal 10-point or 12-point text would be so small as to be nearly illegible. These logical dimensions in effect blow up the display to allow an adequate size for displaying text. When we start working with text and fonts in Chapter 15, we'll wrestle again with this problem. It affects only video displays—for printers, all the dimensions returned from GetDeviceCaps are consistent.

Finding Out About Color

During the discussion of bitmaps in Chapter 9, I noted the two ways in which memory in a video display adapter can be organized for color. In some video adapters, memory is organized into a number of color planes. Within a plane, each bit corresponds to a single pixel and represents a particular primary color (such as red, green, or blue). Other video adapters have a single color plane, in which a number of adjacent bits represent the color of each pixel.

GetDeviceCaps lets you determine the organization of memory in the video adapter and the number of colors it can represent. This call returns the number of color planes:

```
nPlanes = GetDeviceCaps (hDC, PLANES) ;
```

This call returns the number of color bits per pixel:

```
nBitsPixel = GetDeviceCaps (hDC, BITSPIXEL) ;
```

Most graphics display devices that are capable of color use either multiple color planes or multiple color bits per pixel, but not both; in other words, one of these calls will return a value of 1. The number of colors can be calculated by the formula:

```
nColors = 1 << (nPlanes * nBitsPixel) ;
```

You can also get the number of colors directly:

```
nColors = GetDeviceCaps (hDC, NUMCOLORS) ;
```

These two numbers are the same for video displays but different for most plotters. For a plotter, both the PLANES and BITSPIXEL values will equal 1, but the NUMCOLORS value will reflect the number of colored pens that the plotter has. For monochrome devices, *GetDeviceCaps* returns a 2 for the NUMCOLORS parameter.

You might be interested in customizing parts of your program to take advantage of color capabilities. You will also need this information when working with color bitmaps. The organization of memory in a color bitmap is the same as the organization of video adapter memory, which means that color bitmaps are device dependent. (Even monochrome bitmaps are device dependent because they imply a particular aspect ratio.)

The number of colors returned from GetDeviceCaps is the number of pure colors that the device can display. Windows can use dithering (which involves a pixel pattern that combines pixels of different colors) to represent colors in addition to the pure colors.

A color is usually represented by an unsigned long integer with 3 bytes, one each for the intensity of red, green, and blue. (Chapter 7 discusses this subject in more detail.) You can determine the closest pure color of a particular color value by calling <code>GetNearestColor</code>:

```
rgbPureColor = GetNearestColor (hDC, rgbColor) ;
```

The Device Context Attributes

As I noted above, Windows uses the device context to store "attributes" that govern how the GDI functions operate on the display. For instance, when you display some text using the *TextOut* function, you don't have to specify the color of the text or the font. Windows uses the device context to obtain this information.

When a program obtains a handle to a device context, Windows creates a device context with default values for all the attributes. The device context attributes are shown in the following table. A program can change or obtain any of the attributes.

Device Context Attribute	Default	Function(s) to Change	Function to Get
Mapping mode	MM_TEXT	SetMapMode	GetMapMode
Window origin	(0, 0)	SetWindowOrg	GetWindowOrg
Viewport origin	(0, 0)	SetViewportOrg	GetViewportOrg
Window extents	(1, 1)	SetWindowExt SetMapMode	GetWindowExt
Viewport extents	(1, 1)	SetViewportExt SetMapMode	GetViewportExt
Pen	BLACK_PEN	SelectObject	SelectObject
Brush	WHITE_BRUSH	SelectObject	SelectObject
Font	SYSTEM_FONT	SelectObject	SelectObject
Bitmap	None	SelectObject	SelectObject
Current pen position	(0, 0)	MoveTo LineTo	GetCurrentPosition
Background mode	OPAQUE	SetBkMode	GetBkMode
Background color	White	SetBkColor	GetBkColor
Text color	Black	SetTextColor	GetTextColor
Drawing mode	R2_COPYPEN	SetROP2	GetROP2
Stretching mode	BLACKONWHITE	SetPolyFillMode	GetPolyFillMode
Polygon filling mode	ALTERNATE	SetPolyFillMode	GetPolyFillMode
Intercharacter spacing	0	SetTextCharacterExtra	GetTextCharacterExtra
Brush origin	(0, 0) in screen coordinates	SetBrushOrg	GetBrushOrg
Clipping region		SelectObject	SelectObject
FEERWAY ALL		SelectClipRgn	GetClipBox
		IntersectClipRect	ST100238-020500
		OffsetClipRgn	
		ExcludeClipRect	

Saving Device Contexts

Throughout Section IV, you'll encounter various functions to change the device context attributes. Normally, Windows creates a new device context with default values when you call GetDC or BeginPaint. All changes you make to the attributes are lost when the device context is released with the ReleaseDC or EndPaint calls. If your program needs to use non-default device context attributes, you'll have to initialize the device context every time you obtain a device context handle:

Although this approach is generally satisfactory, you might prefer that changes you make to the device context attributes are saved when you release the device context, so that they will be in effect the next time you call <code>GetDC</code> or <code>BeginPaint</code>. You can accomplish this by including the CS_OWNDC flag as part of the window class when you register the window class:

```
wndclass.style = CS_HREDRAW | CS_VREDRAW | CS_OWNDC ;
```

Now each window that you create based on this window class will have its own private device context that exists until the window is destroyed. When you use the CS_OWNDC style, you need to initialize the device context attributes only once, perhaps during processing of the WM_CREATE message:

The attributes continue to be valid until you change them.

The CS_OWNDC style affects only the device contexts retrieved from GetDC and BeginPaint and not device contexts obtained from the other functions (such as GetWindowDC).

The CS_OWNDC class style is not without its cost: Windows requires about 800 bytes to store the device context for each window created with this style. Even if you use CS_OWNDC, you must still release the device context before exiting the window function.

You can also use the CS_CLASSDC style:

```
wndclass.style = CS_HREDRAW | CS_VREDRAW | CS_CLASSDC ;
```

This causes each window class to have its own device context that is shared by all windows created based on that class—even by windows created in other instances of the same program. Now you can initialize the device context attributes once in *WinMain* following creation of the first window based on that window class:

In general, the CS_CLASSDC type of device context is more difficult to use than the CS_OWNDC type, because any changes you make to the device context attributes affect all windows in all instances based on the same window class. This could have some strange

effects, particularly if you use a customized mapping mode (a subject coming up shortly) based on the size of the window.

In some cases you might want to change certain device context attributes, do some painting using the changed attributes, and then revert to the original device context. To simplify this process, you save the state of a device context by calling:

```
nSavedID = SaveDC (hDC) ;
```

Now you change some attributes. When you want to return to the device context as it existed before the SaveDC call, you use:

```
RestoreDC (hDC, nSavedID) ;
```

You can call SaveDC any number of times before calling RestoreDC. If you want to revert to the device context as it existed before the last SaveDC call, you call:

```
RestoreDC (hDC, -1);
```

THE MAPPING MODE

One device context attribute that affects virtually all the drawing you do on the client area is the "mapping mode." Four other device context attributes—the window origin, the viewport origin, the window extents, and the viewport extents—are closely related to the mapping mode attribute.

Most of the GDI drawing functions require coordinate values or sizes. For instance, this is the TextOut function:

```
TextOut (hDC, x, y, szBuffer, nLength) ;
```

The x and y parameters indicate the starting position of the text. The x parameter is the position on the horizontal axis, and the y parameter is the position on the vertical axis. Often the notation (x, y) is used to indicate this point.

In *TextOut*, as in virtually all GDI functions, these coordinate values are in terms of "logical units." Windows must translate the logical units into "device units," or pixels. This translation is governed by the mapping mode, the window and viewport origins, and the window and viewport extents. The mapping mode also implies an origin and orientation of the x axis and the y axis; that is, it determines whether values of x increase as you move toward the left or right side of the display and whether values of y increase as you move up or down the display.

Windows defines eight mapping modes. These are listed in the following table using the WINDOWH identifiers.

	Increasing Values			
Mapping Mode	Logical Units	XAxis	YAxis	
MM_TEXT	Pixels	Right	Down	
MM_LOMETRIC	0.1 mm	Right	Up	
MM_HIMETRIC	0.01 mm	Right	Up	
MM_LOENGLISH	0.01 in.	Right	Up	
MM_HIENGLISH	0.001 in.	Right	Up	
MM_TWIPS	1/1440 in.	Right	Up	
MM_ISOTROPIC	Arbitrary $(x = y)$	Selectable	Selectable	
MM_ANISOTROPIC	Arbitrary (x!= y)	Selectable	Selectable	

(Twip is a fabricated word meaning "twentieth of a point." A point, which is a unit of measurement for type, is approximately 1/72 in.)

You can set the mapping mode by:

```
SetMapMode (hDC, nMapMode) ;
```

where *nMapMode* is one of the eight mapping mode identifiers. You can obtain the current mapping mode by calling:

```
nMapMode = GetMapMode (hDC) ;
```

The default mapping mode is MM_TEXT. In this mapping mode, logical units are the same as physical units, which allows us (or, depending on your perspective, forces us) to work directly in terms of pixels. In a *TextOut* call that looks like this:

```
TextOut (hDC, 8, 16, szBuffer, nLength);
```

the text begins 8 pixels from the left of the client area and 16 pixels from the top.

If the mapping mode is set to MM_LOENGLISH, then logical units are in terms of hundredths of an inch:

```
SetMapMode (hDC, MM_LOENGLISH) ;
```

Now the TextOut function call might look like this:

```
TextOut (hDC, 50, -100, szBuffer, nLength) ;
```

The text begins 0.5 in. from the left and 1 in. from the top of the client area. (The reason for the negative sign in front of the y coordinate will become clear as we discuss the mapping modes in more detail.) Other mapping modes allow programs to specify coordinates in terms of millimeters, a printer's point size, or an arbitrarily scaled axis.

If you feel comfortable working in terms of pixels, you don't need to use any mapping modes except the default MM_TEXT mode. If you need to display an image in actual inch or

millimeter dimensions, you can obtain the information you need from GetDeviceCaps and do your own scaling. The other mapping modes are simply a convenient way to avoid doing your own scaling.

Regardless of the mapping mode, all coordinates you specify in Windows functions must be signed short integers in the range 32,767 to -32,768. Some Windows functions that use coordinates for the starting point and ending point of a rectangle also require that the width and height of the rectangle be 32,767 or less.

Device Coordinates and Logical Coordinates

You may ask: If I use the MM_LOENGLISH mapping mode, will I start getting WM_SIZE messages in terms of hundredths of an inch? Absolutely not. Windows continues to use device coordinates for all messages (such as WM_MOVE, WM_SIZE, and WM_MOUSEMOVE), for all non-GDI functions, and even for some GDI functions. Think of it this way: The mapping mode is an attribute of the device context, so the only time the mapping mode comes into play is when you use GDI functions that require a handle to the device context as one of the parameters. GetSystemMetrics is not a GDI function, so it will continue to return sizes in terms of device units, which are pixels. And although GetDeviceCaps is a GDI function that requires a handle to a device context, Windows continues to return device units for the HORZRES and VERTRES indexes, because one of the purposes of this function is to provide a program with the size of the device in pixels.

However, the values in the TEXTMETRIC structure that you obtain from the GetText-Metrics call are in terms of logical units. If the mapping mode is MM_LOENGLISH at the time the call is made, GetTextMetrics provides character widths and heights in terms of hundredths of an inch. When you call GetTextMetrics for information about the height and width of characters, the mapping mode should be set to the same mapping mode that you'll be using when you draw text based on these sizes. As we cover the various GDI functions, I'll note whether they use device coordinates or logical coordinates.

The Device Coordinate Systems

Windows maps logical coordinates specified in GDI functions to device coordinates. Before we discuss the logical coordinate systems used with the various mapping modes, let's examine the different device coordinate systems that Windows defines for the video display area. Although we have been working mostly within the client area of our window, Windows uses two other device coordinate areas at various times. In all device coordinate systems, units are in terms of pixels. Values on the horizontal, or x, axis increase from left to right, and values on the vertical, or y, axis increase from top to bottom.

When we use the entire screen, we are working in terms of "screen coordinates." The upper left corner of the screen is the point (0, 0). Screen coordinates are used in the WM_MOVE message (for nonchild windows) and in the following Windows functions:

CreateWindow and MoveWindow (both for nonchild windows), GetMessagePos, GetCursorPos, SetCursorPos, GetWindowRect, WindowFromPoint, and SetBrushOrg. These are generally either functions that don't have a window associated with them (such as the two cursor functions) or functions that must move (or find) a window based on a screen point. If you use CreateDC with a "DISPLAY" parameter to obtain a device context for the entire screen, then logical coordinates specified in GDI calls will be mapped to screen coordinates.

"Whole window coordinates" refer to a program's entire window, including the caption bar, menu, scroll bars, and window frame. For an overlapped window with a caption bar and system menu box, the point (0, 0) is the upper left corner of the system menu box. Whole window coordinates are rare in Windows, but if you obtain a device context from GetWindowDC, logical coordinates in GDI functions will be mapped to whole window coordinates.

The third device coordinate system—the one we've been working with the most—uses "client-area coordinates." The point (0, 0) is the upper left corner of the client area. When you obtain a device context using *GetDC* or *BeginPaint*, logical coordinates in GDI functions are translated to client-area coordinates.

You can convert client-area coordinates to screen coordinates and vice versa using the functions *ClientToScreen* and *ScreenToClient*. You can also obtain the position and size of the whole window in terms of screen coordinates using the *GetWindowRect* function. These three functions provide enough information to translate from any one device coordinate system to any other.

The Viewport and the Window

The mapping mode defines how Windows maps logical coordinates that are specified in GDI functions to device coordinates, where the particular device coordinate system depends on the function you use to obtain the device context. To continue our discussion of the mapping mode, we need some additional terminology: The mapping mode is said to define the mapping of the "window" (logical coordinates) to the "viewport" (device coordinates).

The use of the words window and viewport is unfortunate. In other graphics interface languages, viewport often implies a clipping region. We've been using the word window to talk about the area that a program occupies on the screen. We'll have to put aside our preconceptions about these words during this discussion.

The "viewport" is in terms of device coordinates (pixels). Most often, the viewport is the same as the client area, but it can also refer to whole window coordinates or screen coordinates if you've obtained a device context from GetWindowDC or CreateDC. The point (0,0) is the upper left corner of the client area (or the whole window or the screen). Values of x increase to the right and of y increase going down.

The "window" is in terms of logical coordinates, which may be pixels, millimeters, inches, or anything you want. You specify logical window coordinates in the GDI functions.

For all mapping modes, Windows translates window (logical) coordinates to viewport (device) coordinates by the use of two formulas:

$$xViewport = (xWindow - xWinOrg) \cdot \frac{xViewExt}{xWinExt} + xViewOrg$$

$$yViewport = (yWindow - yWinOrg) \cdot \frac{yViewExt}{yWinExt} + yViewOrg$$

where (xWindow, yWindow) is a logical point to be translated, and (xViewport, yViewport) is the translated point in device coordinates. If the device coordinates are client-area coordinates or whole window coordinates, then Windows must also translate these device coordinates to screen coordinates before drawing an object.

These formulas use two points that specify an "origin" of the window and the viewport: (xWinOrg, yWinOrg) is the window origin in logical coordinates; (xViewOrg, yViewOrg) is the viewport origin in device coordinates. In the default device context, these two points are set to (0, 0), but they can be changed. The formulas imply that the logical point (xWinOrg, yWinOrg) is always mapped to the device point (xViewOrg, yViewOrg).

The formulas also use two points that specify "extents": (xWinExt, yWinExt) is the window extent in logical coordinates; (xViewExt, yViewExt) is the viewport extent in device coordinates. In most mapping modes, the extents are implied by the mapping mode and cannot be changed. Each extent means nothing by itself, but the ratio of the viewport extent to the window extent is a scaling factor for converting logical units to device units. The extents can be negative: This implies that values on the logical x axis don't necessarily have to increase to the right and that values on the logical y axis don't necessarily have to increase going down.

Windows can also translate from viewport (device) coordinates to window (logical) coordinates:

$$xWindow = (xViewport - xViewOrg)$$
 * $\frac{xWinExt}{xViewExt}$ + $xWinOrg$
 $yWindow = (yViewport - yViewOrg)$ * $\frac{yWinExt}{yViewExt}$ + $yWinOrg$

Windows provides two functions that let you convert device points to logical points and vice versa within a program. This function converts device points to logical points:

```
DPtoLP (hDC, lpPoints, nNumber) ;
```

The variable *lpPoints* is a long pointer to an array of POINT structures, and *nNumber* is the number of points to be converted. You'll find this function useful for converting the size of the client area obtained from *GetClientRect* (which is always in terms of device units) to logical coordinates:

```
GetClientRect (hWnd, &rect);
DPtoLP (hDC, (LPPOINT) &rect, 2);
```

This function converts logical points to device points:

```
LPtoDP (hDC, lpPoints, nNumber) ;
```

Working with MM_TEXT

For the MM_TEXT mapping mode, the default origins and extents are shown below:


Window origin:	(0, 0)	Can be changed
Viewport origin:	(0, 0)	Can be changed
Window extent:	(1, 1)	Cannot be changed
Viewport extent:	(1, 1)	Cannot be changed

The ratio of the viewport extent to the window extent is 1, so no scaling is performed between logical coordinates and device coordinates. The formulas shown on the preceding page reduce to these:

```
xViewport = xWindow - xWinOrg + xViewOrg

yViewport = yWindow - yWinOrg + yViewOrg
```

This mapping mode is called a "text" mapping mode not because it's most suitable for text but because of the orientation of the axes. We read text from left to right and top to bottom, and MM_TEXT defines values on the axes to increase the same way:



Windows provides the functions SetViewportOrg and SetWindowOrg for changing the viewport and window origins. These functions have the effect of shifting the axis so that the logical point (0, 0) no longer refers to the upper left corner. Generally, you'll use either SetViewportOrg or SetWindowOrg but not both.


Here's how these functions work: If you change the viewport origin to (xViewOrg, yViewOrg), then the logical point (0, 0) will be mapped to the device point (xViewOrg, yViewOrg). If you change the window origin to (xWinOrg, yWinOrg), the logical point (xWinOrg, yWinOrg) will be mapped to the device point (0, 0), which is the upper left

corner. Regardless of any changes you make to the window and viewport origins, the device point (0, 0) is always the upper left corner of the client area.

For instance, suppose your client area is xClient pixels wide and yClient pixels high. If you want to define the logical point (0, 0) to be the center of the client area, you can do so by calling:

```
SetViewportOrg (hDC, xClient / 2, yClient / 2) ;
```

The arguments to SetViewportOrg are always in terms of device units. The logical point (0, 0) will now be mapped to the device point (xClient / 2, yClient / 2). Now you use your client area as if it had the following coordinate system:



The logical x axis ranges from -xClient/2 to +xClient/2, and the logical y axis ranges from -yClient/2 to +yClient/2. The lower right corner of the client area is the logical point (xClient/2, yClient/2). If you want to display text starting at the upper left corner of the client area, which is the device point (0, 0), you need to use negative coordinates:

```
TextOut (hDC, -xClient / 2, -yClient / 2, "Hello", 5);
```

You can achieve the same result with SetWindowOrg as you did with SetViewportOrg:


```
SetWindowOrg (hDC, -xClient / 2, -yClient / 2);
```

The arguments to SetWindowOrg are always in terms of logical units. After this call, the logical point (-xClient/2, -yClient/2) is mapped to the device point (0, 0), the upper left corner of the client area.

What you probably don't want to do (unless you know what's going to happen) is to use both functions together:

```
SetViewportOrg (hDC, xClient / 2, yClient / 2);
SetWindowOrg (hDC, -xClient / 2, -yClient / 2);
```

This means that the logical point (-xClient/2, -yClient/2) is mapped to the device point (xClient/2, yClient/2), giving you a coordinate system that looks like this:



You can obtain the current viewport and window origins from these functions:

```
dwViewOrigin = GetViewportOrg (hDC) ;
dwWindOrigin = GetWindowOrg (hDC) ;
```

Both functions return DWORDs (unsigned longs). You can then use the MAKEPOINT macro to convert the return values to a structure of type POINT. The point returned from GetViewport-Org is in device coordinates; the point returned from GetWindowOrg is in logical coordinates.

You might want to change the viewport or window origin to shift display output within the client area of your window—for instance, in response to scroll bar input from the user. Changing the viewport or window origin doesn't shift the display output immediately, of course. You change the origin and then repaint the display.

For instance, in the SYSMETS2 program in Chapter 3, we used the *nVscrollPos* value (the current position of the vertical scroll bar) to adjust the beginning of the display output:

We can achieve the same result using SetWindowOrg:

Now the *TextOut* statement doesn't require the *nVscrollPos* value. This means you can put the output function in a subroutine and not have to pass the *nVscrollPos* value to the subroutine, because we adjust the display of the text by changing the window origin.

If you have some experience working with rectangular (or Cartesian) coordinate systems, moving the logical point (0, 0) to the center of the client area as we did earlier may have seemed a reasonable action. However, there's a slight problem with the MM_TEXT mapping mode: A Cartesian coordinate system defines values on the yaxis to increase as you move up the axis, whereas MM_TEXT defines the values to increase as you move down. In this sense, MM_TEXT is an oddity, and these next five mapping modes do it right.

The "Metric" Mapping Modes

Windows includes five mapping modes that express logical coordinates in physical measurements. Because logical coordinates on the xaxis and yaxis are mapped to identical physical units, these mapping modes help you in drawing round circles and square squares.

The five "metric" mapping modes are arranged below in order of lowest precision to highest precision. The two columns at the right show the size of the logical units in terms of inches and millimeters for comparison:

	1 Logical Unit	Inch	Millimeter
MM_LOENGLISH	0.01 in.	0.01	0.254
MM_LOMETRIC	0.1 mm	0.00394	0.1
MM_HIENGLISH	0.001 in.	0.001	0.0254
MM_TWIPS	1/1440 in.	0.000694	0.0176
MM_HIMETRIC	0.01 mm	0.000394	0.01

As I noted earlier, a "twip" equals 1/20 of a point, which itself equals 1/72 in.

To give you an idea of how the MM_TEXT mode fits in with these resolutions, on a standard EGA display each pixel is 0.375 mm wide and 0.5 mm tall, so EGA device coordinates are coarser than the logical coordinates for any of the metric mapping modes. On a 300-dots-per-inch laser printer, each pixel is 0.0033 in.—a higher resolution than MM_LOENGLISH and MM_LOMETRIC but not as high as MM_HIENGLISH, MM_TWIPS, or MM_HIMETRIC.

The default origins and extents are shown below:

Window origin:	(0, 0)	Can be changed
Viewport origin:	(0, 0)	Can be changed
Window extent:	(?,?)	Cannot be changed
Viewport extent:	(?,?)	Cannot be changed

The window and viewport extents depend on the mapping mode and the aspect ratio of the device. As I mentioned earlier, the extents aren't important by themselves but take on meaning only when expressed as ratios. Here are the translation formulas again:

$$xViewport = (xWindow - xWinOrg) * \frac{xViewExt}{xWinExt} + xViewOrg$$

$$yViewport = (yWindow - yWinOrg) * \frac{yViewExt}{yWinExt} + yViewOrg$$


For MM_LOENGLISH, for instance, Windows calculates the extents to be the following:

$$\frac{xViewExt}{xWinExt} = number of horizontal pixels in 0.01 in.$$

$$-\frac{yViewExt}{yWinExt} = number of vertical pixels in 0.01 in.$$

For many display devices (such as the EGA), this ratio will be less than 1. Because Windows works entirely with integers, the use of a ratio rather than an absolute scaling factor is necessary to reduce loss of precision when converting logical and device coordinates.

Notice the negative sign in front of the ratio of extents for the vertical axis. This negative sign changes the orientation of the y axis. For these five mapping modes, y values increase as you move up the device. The default window and viewport origins are (0,0). This fact has an interesting implication. When you first change to one of these five mapping modes, the coordinate system looks like this:



The only way you can display anything in the client area is to use negative values of y. For instance, this code:


```
SetMapMode (hDC, MM_LOENGLISH);
TextOut (hDC, 100, -100, "Hello", 5);
```

displays "Hello" 1 in. from the top and left of the client area.

To preserve your sanity, you'll probably want to avoid this. One solution is to set the logical (0, 0) point to be the lower left corner of the client area. Assuming that yClient is the height of the client area in pixels, you can do this by calling SetViewportOrg:

```
SetViewportOrg (hDC, 0, yClient);
```


Now the coordinate system looks like this:



Alternatively, you can set the logical (0, 0) point to the center of the client area:

```
SetViewportOrg (hDC, xClient / 2, yClient / 2) ;
```

The coordinate system looks like this:



Now we have a real four-quadrant Cartesian coordinate system with equal logical units on the x axis and y axis in terms of inches, millimeters, or twips.

You can also use the SetWindowOrg function to change the logical (0, 0) point, but the task is a little more difficult because the parameters to SetWindowOrg have to be in logical coordinates. You would first need to convert yClient to a logical coordinate using the DPtoLP function. Assuming that the variable pt is a structure of type POINT, this code changes the logical (0, 0) point to the center of the client area:

```
pt.x = xClient;
pt.y = yClient;
DPtoLP (hDC, &pt, 1);
SetWindowOrg (hDC, -pt.x, -pt.y);
```

The "Roll Your Own" Mapping Modes

The two remaining mapping modes are called MM_ISOTROPIC and MM_ANISOTROPIC. These are the only two mapping modes for which Windows lets you change the viewport and window extents, which means that you can change the scaling factor that Windows uses to translate logical and device coordinates. The word *isotropic* means "equal in all directions"; *anisotropic* is the opposite—"not equal." Like the metric mapping modes shown above, MM_ISOTROPIC uses equally scaled axes. Logical units on the x axis have the same physical dimensions as logical units on the y axis. This helps when you need to create images that retain the correct aspect ratio regardless of the aspect ratio of the display device.

The difference between MM_ISOTROPIC and the metric mapping modes is that with MM_ISOTROPIC you can control the physical size of the logical unit. If you want, you can adjust the physical size of the logical unit based on the size of the client area so that the images you draw are always contained within the client area, shrinking and expanding appropriately. For instance, the CLOCK and REVERSI programs included with Windows are examples of isotropic images. The clock is always round, and the Reversi playing board is always square. As you size the window, the image is resized appropriately. A Windows program can handle the resizing of an image entirely through adjusting the viewport and windows extents. The program can then use the same logical units in the drawing functions regardless of the size of the window.

Sometimes the MM_TEXT and the "metric" mapping modes are called "fully constrained" mapping modes. This means that you cannot change the window and viewport extents and the way that Windows scales logical coordinates to device coordinates. MM_ISOTROPIC is a "partly constrained" mapping mode. Windows allows you to change the window and viewport extents, but it adjusts them so that x and y logical units represent the same physical dimensions. The MM_ANISOTROPIC mapping mode is "unconstrained." You can change the window and viewport extents, and Windows doesn't adjust the values.

The MM_ISOTROPIC mapping mode

The MM_ISOTROPIC mapping mode is ideal for using arbitrary axes while preserving equal logical units on the two axes. Rectangles with equal logical widths and heights are displayed as squares. Ellipses with equal logical widths and heights are displayed as circles.

When you first set the mapping mode to MM_ISOTROPIC, Windows uses the same window and viewport extents that it uses with MM_LOMETRIC. (Don't rely on this fact, however.) The difference is that you can now change the extents to suit your preferences by calling Set-WindowExt and SetViewportExt. Windows will then adjust the extents so that the logical units on both axes represent equal physical distances.


Generally, you'll use parameters to SetWindowExt with the desired logical size of the logical window and parameters to SetViewportExt with the actual height and width of the client area. When Windows adjusts these extents, it has to fit the logical window within the physical viewport, which can result in a section of the client area falling outside the logical window. You'll find that Windows makes the most efficient use of space in the client area if you call SetVindowExt before you call SetViewportExt.

For instance, suppose you want a "traditional" one-quadrant virtual coordinate system where (0,0) is at the lower left corner of the client area and the width ranges from 0 to 32,767 and the height from 0 to 32,767. You want the x and y units to have the same physical dimensions. Here's what you need to do:

```
SetMapMode (hDC, MM_ISOTROPIC);
SetWindowExt (hDC, 32767, 32767);
SetViewportExt (hDC, xClient, -yClient);
SetViewportOrg (hDC, 0, yClient);
```


If you then obtain the window and viewport extents using GetWindowExt and GetViewport-Ext, you'll find that they are not the values you specified. Windows adjusts the extents based on the aspect ratio of the display device so that logical units on the two axes represent the same physical dimensions.

If the client area is wider than it is high (in physical dimensions), Windows adjusts the x extents so that the logical window is narrower than the client-area viewport. The logical window will be positioned at the left of the client area:



You can't display anything on the right side of the client area, beyond the range of the x axis, because that requires a logical x coordinate greater than 32,767.

If the client area is higher than it is wide (in physical dimensions), Windows adjusts the y extents. The logical window will be positioned at the bottom of the client area:




Now you can't display anything at the top of the client area, because you need a logical y coordinate greater than 32,767.

If you prefer that the logical window always be positioned at the left and top of the client area, you can change the code above to the following:

```
SetMapMode (hDC, MM_ISOTROPIC);
SetWindowExt (hDC, 32767, 32767);
SetViewportExt (hDC, xClient, -yClient);
SetWindowOrg (hDC, 0, 32767);
```


In the SetWindowOrg call we're saying that we want the logical point (0, 32,767) to be mapped to the device point (0, 0). Now if the client area is higher than it is wide, the coordinates are arranged like this:




For a CLOCK-like image, you might want to use a four-quadrant Cartesian coordinate system with arbitrarily scaled axes in four directions where the logical point (0, 0) is in the center of the client area. If you want each axis to range from 0 to 1000 (for instance), you use this code:

```
SetMapMode (hDC, MM_ISOTROPIC);
SetWindowExt (hDC, 1000, 1000);
SetViewportExt (hDC, xClient/2, -yClient/2);
SetViewportOrg (hDC, xClient/2, yClient/2);
```

The logical coordinates look like this if the client area is wider than it is high:



The logical coordinates are also centered if the client area is higher than it is wide:



Keep in mind that no clipping is implied in window or viewport extents. When calling GDI functions, you are still free to use logical x and y values less than -1000 and greater than +1000. Depending on the shape of the client area, these points may or may not be visible.

With the MM_ISOTROPIC mapping mode, you can make logical units larger than pixels. For instance, suppose you want a mapping mode with the point (0,0) at the upper left corner of the display and values of y increasing as you move down (like MM_TEXT) but with logical

coordinates in sixteenths of an inch. This mapping mode would let you draw a ruler starting at the top and left side of the client area with divisions of sixteenths of an inch:

In this code, the viewport extents are set to the pixel dimensions of the entire screen. The window extents must be set to the dimensions of the entire screen in units of sixteenths of an inch. The HORZSIZE and VERTSIZE indexes to *GetDeviceCaps* return the dimensions of the device in millimeters. If we were working with floating-point numbers, we would convert the millimeters to inches by dividing by 25.4 and then convert inches to sixteenths of an inch by multiplying by 16. However, because we're working with integers, we must multiply by 160 and divide by 254. The calculation is done in long integers to prevent overflow.

For most output devices, this code makes the logical unit much larger than the physical unit. Everything you draw on the device will have coordinate values that map to an increment of a sixteenth of an inch. You cannot draw two horizontal lines that are a thirty-second of an inch apart, however, because that would require a fractional logical coordinate.

MM_ANISOTROPIC: Stretching the image to fit

When you set the viewport and window extents in the MM_ISOTROPIC mapping mode, Windows adjusts the values so that logical units on the two axes have the same physical dimensions. In the MM_ANISOTROPIC mapping mode, Windows makes no adjustments to the values you set. This means that MM_ANISOTROPIC does not necessarily maintain the correct aspect ratio.

One way you can use MM_ANISOTROPIC is to have arbitrary coordinates for the client area, as we did with MM_ISOTROPIC. This code sets the point (0, 0) at the lower left corner of the client area with both the x and y axes ranging from 0 to 32,767:

```
SetMapMode (hDC, MM_ANISOTROPIC);
SetWindowExt (hDC, 32767, 32767);
SetViewportExt (hDC, xClient, -yClient);
SetViewportOrg (hDC, 0, yClient);
```

With MM_ISOTROPIC, similar code caused part of the client area to be beyond the range of the axes. With MM_ANISOTROPIC, the upper right corner of the client area is always the point (32767, 32767) regardless of its dimensions. If the client area is not square, then logical x and y units will be different physical dimensions.

In the section above on the MM_ISOTROPIC mapping mode, I discussed drawing a CLOCK-like image in the client area where both the x and y axes ranged from -1000 to 1000. You can do something similar with MM_ANISOTROPIC:

```
SetMapMode (hDC, MM_ANISOTROPIC);
SetWindowExt (hDC, 1000, 1000);
SetViewportExt (hDC, xClient / 2, -yClient / 2);
SetViewportOrg (hDC, xClient / 2, yClient / 2);
```

The difference with MM_ANISOTROPIC is that in general the clock would be drawn as an ellipse rather than a circle.

Another way to use MM_ANISOTROPIC is to set x and y units to fixed but unequal values. For instance, if you have a program that displays only text, you may want to set coarse coordinates based on the height and width of a single character:

```
SetMapMode (hDC, MM_ANISOTROPIC) ;
SetWindowExt (hDC, 1, 1) ;
SetViewportExt (hDC, xChar, yChar) ;
```

(This assumes that xChar and yChar are the width and height of a character in pixels,) Now you can specify character row and column coordinates in the TextOut call rather than pixel coordinates. For instance, the following statement displays the text "Hello" three character spaces from the left and two character rows from the top:

```
TextOut (hDC, 3, 2, "Hello", 5);
```

This is almost like working in text mode in the non-Windows MS-DOS environment!

When you first set the MM_ANISOTROPIC mapping mode, it always inherits the extents of the previously set mapping mode, which can be very convenient. One way of thinking about MM_ANISOTROPIC is that it "unlocks" the extents; that is, it allows you to change the extents of an otherwise fully constrained mapping mode. For instance, suppose you want to use the MM_LOENGLISH mapping mode because you want logical units to be 0.01 in. But you don't want the y axis to increase as you move up the screen—you prefer the MM_TEXT orientation, where y values increase moving down. Here's the code:

We first set the mapping mode to MM_LOENGLISH. Then we liberate the extents by setting the mapping mode to MM_ANISOTROPIC. The viewport extent is saved in a doubleword variable and converted to a POINT structure using the MAKEPOINT macro. Then we call <code>SetViewportExt</code> with the same extents, except that we make the <code>y</code> extent negative.

The WHATSIZE Program

We'll use various mapping modes as we explore the GDI functions in the next four chapters. Right now, let's simply look at the size of a client area in terms of inches and millimeters. The WHATSIZE program, shown in Figure 12-5, displays the size of the client area in terms of units associated with the six fully constrained mapping modes: MM_TEXT, MM_LOMETRIC, MM_HIMETRIC, MM_LOENGLISH, MM_HIENGLISH, and MM_TWIPS.

```
whatsize.obj : whatsize.c
    cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp whatsize.c

whatsize.exe : whatsize.obj whatsize.def
    link4 whatsize, /align:16, /map, slibw, whatsize
```

```
/* WHATSIZE.C -- What Size is the Window? */
#include <windows.h>
#include <stdio.h>
long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG) :
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
     HANDLE hInstance, hPrevInstance;
     LPSTR
                   lpszCmdLine ;
                 nCmdShow ;
     int
     static char szAppName [] = "WhatSize" ;
     HWND hWnd ;
     MSG
                   msq ;
     WNDCLASS wndclass;
     if (!hPrevInstance)
           wndclass.style
                                    = CS HREDRAW | CS VREDRAW;
          wndclass.lpfnWndProc = wndFloc ,
wndclass.cbClsExtra = 0 ;
wndclass.cbWndExtra = 0 ;
wndclass.hInstance = hInstance ;
wndclass.hIcon = LoadIcon (NULL, IDI_APPLICATION) ;
wndclass.hCursor = LoadCursor (NULL, IDC_ARROW) ;
           wndclass.lpfnWndProc = WndProc ;
           wndclass.hbrBackground = GetStockObject (WHITE BRUSH) ;
           wndclass.lpszMenuName = NULL ;
           wndclass.lpszClassName = szAppName ;
           if (!RegisterClass (&wndclass))
                 return FALSE ;
     hWnd = CreateWindow (szAppName, "What Size is the Window?",
                            WS OVERLAPPEDWINDOW,
                             CW USEDEFAULT, 0,
                             CW USEDEFAULT, 0,
                             NULL, NULL, hInstance, NULL) ;
```

Figure 12-5. The WHATSIZE program

(continued)

Figure 12-5. Continued

```
ShowWindow (hWnd, nCmdShow) ;
     UpdateWindow (hWnd) ;
     while (GetMessage (&msg, NULL, 0, 0))
          TranslateMessage (&msg) ;
          DispatchMessage (&msg) ;
     return msg.wParam ;
void Show (hWnd, hDC, xText, yText, nMapMode, szMapMode)
     HWND hWnd ;
     HDC hDC :
     short xText, yText, nMapMode;
    char *szMapMode;
    RECT rect ;
    char szBuffer [60] ;
    SaveDC (hDC) ;
    SetMapMode (hDC, nMapMode) ;
    GetClientRect (hWnd, &rect) ;
    DPtoLP (hDC, (LPPOINT) &rect, 2) ;
    RestoreDC (hDC, -1) ;
    TextOut (hDC, xText, yText, szBuffer, sprintf (szBuffer, "%-20s %7d %7d %7d %7d", szMapMode,
                   rect.left, rect.right, rect.top, rect.bottom)) ;
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
     HWND
                  hWnd ;
     unsigned
                  iMessage ;
     WORD
                  wParam ;
     LONG
                  lParam ;
     static char szHeading [] =
                                                               Top Bottom" ;
                    "Mapping Mode
                                          Left
                                                     Right
     static char szUndLine [] =
                                                               --- ----- ;
     static short xChar, yChar;
                  hDC ;
     PAINTSTRUCT ps ;
                  tm ;
     TEXTMETRIC
     switch (iMessage)
          case WM CREATE:
               hDC = GetDC (hWnd) ;
               GetTextMetrics (hDC, &tm) ;
               xChar = tm.tmAveCharWidth ;
               yChar = tm.tmHeight + tm.tmExternalLeading ;
               ReleaseDC (hWnd, hDC) ;
               break ;
```

(continued)

Figure 12-5. Continued

```
case WM PAINT:
               hDC = BeginPaint (hWnd, &ps) ;
               SetMapMode (hDC, MM_ANISOTROPIC) ;
               SetWindowExt (hDC, \(\bar{1}\), 1) ;
SetViewportExt (hDC, xChar, yChar) ;
               TextOut (hDC, 1, 1, szHeading, sizeof szHeading - 1);
TextOut (hDC, 1, 2, szUndLine, sizeof szUndLine - 1);
               Show (hWnd, hDC, 1, 3, MM_TEXT,
                                                                        "TEXT (pixels)") ;
               Show (hWnd, hDC, 1, 4, MM_LOMETRIC, "LOMETRIC (.1 mm)");
Show (hWnd, hDC, 1, 5, MM_HIMETRIC, "HIMETRIC (.01 mm)");
Show (hWnd, hDC, 1, 6, MM_LOENGLISH, "LOENGLISH (.01 in)");
Show (hWnd, hDC, 1, 7, MM_HIENGLISH, "HIENGLISH (.001 in)");
                                                                        "TWIPS (1/1440 in)");
               Show (hWnd, hDC, 1, 8, MM TWIPS,
               EndPaint (hWnd, &ps) ;
               break ;
       case WM DESTROY:
               PostQuitMessage (0) ;
               break ;
       default:
               return DefWindowProc (hWnd, iMessage, wParam, 1Param) ;
return OL ;
```

```
WHATSIZE
NAME
DESCRIPTION
               'What Size is the Window? (C) Charles Petzold, 1987'
STUB
               'WINSTUB. EXE'
               MOVEABLE
CODE
DATA
               MOVEABLE MULTIPLE
HEAPSIZE
               1024
STACKSIZE
               4096
EXPORTS
               WndProc
```

For ease in displaying the information using the *TextOut* function, WHATSIZE uses the MM_ANISOTROPIC mapping mode with logical units set to character dimensions:

```
SetMapMode (hDC, MM_ANISOTROPIC) ;
SetWindowExt (hDC, 1, 1) ;
SetViewportExt (hDC, xChar, yChar) ;
```

The program can then specify logical coordinates to *TextOut* in character row and character column coordinates.

When WHATSIZE needs to obtain the size of the client area for one of the six mapping modes, it saves the current device context, sets a new mapping mode, obtains the client-area coordinates, converts them to logical coordinates, and then restores the original mapping mode before displaying the information. This code is in WHATSIZE's Show function:

```
SaveDC (hDC) ;
SetMapMode (hDC, nMapMode) ;
GetClientRect (hWnd, &rect) ;
DPtoLP (hDC, (LPPOINT) &rect, 2) ;
RestoreDC (hDC, -1) ;
```

Figure 12-6 shows a typical display from WHATSIZE.

Mapping Mode	Left	Right	Top	Bottom	- 8
TEXT (pixels) LOMETRIC (.1 mm) HIMETRIC (.01 mm) LOENGLISH (.01 in) HIENGLISH (.001 in) TWIPS (1/1440 in)	0 0 0 0 0	488 1830 18300 720 7205 10375	0 0 0	267 -1335 -13350 -526 -5256 -7569	Market School Services
					-
- I				A COLUMN	۵

Figure 12-6. A typical WHATSIZE display

Now that we have the preliminaries down, we're ready to start drawing.

Chapter 13

Drawing Graphics

Some theoretical discussions of computer graphics assume that you are supplied with only two graphics primitives—a "write pixel" routine and a "read pixel" routine. In theory, you can do anything you want with these two functions. Drawing a line, for instance, simply requires that you call the "write pixel" routine numerous times, adjusting the x and y coordinates appropriately.

In reality, you can indeed do anything you want with only "write pixel" and "read pixel" routines—if you don't mind waiting for the results. It is much more efficient for a graphics system to do line drawing and other complex graphics operations at the level of the device driver, which can have its own optimized code to perform the operations. Moreover, as video display technology becomes more sophisticated, the adapter boards will contain graphics coprocessors that allow the video hardware itself to draw the figures.

But of course, no graphics language would be complete without routines to draw one pixel at a time, and that's where we'll begin. From there we'll proceed to drawing lines, and then we'll tackle bounded areas.

DRAWING POINTS

You can draw a pixel of a particular color with the GDI SetPixel function:

rgbActualColor = SetPixel (hDC, x, y, rgbColor) ;

The rgbColor parameter is an unsigned long integer (32 bits) where the lowest 3 bytes represent the density of red, green, and blue. You can construct this color value using the RGB macro:

```
rqbColor = RGB (byRed, byGreen, byBlue) ;
```

(Chapter 7 contains a more extensive discussion of Windows' use of color.)

Although x and y are logical coordinates, SetPixel colors only a single physical pixel regardless of the mapping mode. Because SetPixel draws only a single pixel, the use of a dithered color (a color that combines pixels of various pure colors) is meaningless. For this reason, Windows translates the rgbColor parameter to a pure nondithered color and returns that color.

SetPixel is almost never used in Windows programs, but that didn't prevent us from using it in the CONNECT program in Chapter 5. You can obtain the color of a particular pixel this way:

```
rgbColor = GetPixel (hDC, x, y) ;
```

DRAWING LINES

After drawing points, the next step up is drawing lines. Windows can draw straight lines and elliptical lines. An elliptical line is a curved line on the circumference of an ellipse. The three functions that draw lines are *LineTo* (straight lines), *PolyLine* (series of connected lines), and *Arc* (elliptical lines). Five attributes of the device context affect the appearance of lines that you draw using these functions: current pen position (for *LineTo* only), pen, background mode (for nonsolid pens), background color (for the OPAQUE background mode), and drawing mode.

The LineTo function is one of the few GDI functions that does not include the full dimensions of the object to be drawn. Instead, LineTo draws a line from the current pen position defined in the device context up to (but not including) the logical point specified in the LineTo function. In the default device context, the current pen position is initially set at the logical point (0, 0). If you call LineTo without first setting the current pen position (or the viewport or window origin), it draws a line starting at the upper left corner of the client area.

To draw a line from the logical point (xStart, yStart) to the logical point (xEnd, yEnd), you first must use MoveTo to set the current pen position to the point (xStart, yStart):

```
MoveTo (hDC, xStart, yStart) ;
```

MoveTo doesn't draw anything. It simply changes the current pen position. You can then use LineTo to draw the line:

```
LineTo (hDC, xEnd, yEnd) ;
```

This draws the line up to (but not including) the point (xEnd, yEnd). Following the LineTo call, the current pen position is set to (xEnd, yEnd).

LineTo is the only Windows function that uses the current pen position. MoveTo and LineTo are the only functions that change it. You can obtain the current pen position by calling:

```
dwPoint = GetCurrentPosition (hDC) ;
```

The *dwPoint* return value is an unsigned long (or doubleword) that contains the x coordinate in the low word and the y coordinate in the high word. You can use the LOWORD and HIWORD macros to extract the two coordinates, or you can convert the value of *dwPoint* to a POINT structure using the MAKEPOINT macro:

```
point = MAKEPOINT (dwPoint) ;
```

The following code draws a grid in the client area of a window where the lines are spaced 1 in. apart starting from the upper left corner. The variable hWnd is assumed to be a handle to the window, hDC is a handle to the device context, rect is a structure of type RECT, and x and y are short integers:

The dimensions of the client area are saved in the RECT structure called *rect* and converted to logical points with *DPtoLP*. After the *DPtoLP* conversion, *rect.right* is the width of the client area in units of 0.01 in., and *rect.bottom* is the negative height of the client area. Notice that *y* is decremented rather than incremented in the second *for* loop because the MM_LOENGLISH mapping mode uses decreasing values of *y* as you move down the display.

Although it may seem like a nuisance to be forced to use two functions to draw a single line, the current pen position attribute comes in handy when you want to draw a series of connected lines. For instance, you might want to define an array of 5 points (10 values) that draw the outline of a rectangle:

Notice that the last point is the same as the first. Now you need only use *MoveTo* for the first point and *LineTo* for the successive points:

```
MoveTo (hDC, pt[0].x, pt[0].y);

for (i = 1 ; i < 5 ; i++)
    LineTo (hDC, pt[i].x, pt[i].y);
```

Because *LineTo* draws from the current point up to (but not including) the point in the *LineTo* function, no coordinate gets written twice by this code. While overwriting points is not a problem with a display, it might not look good on a plotter.

When you have an array of points that you want connected with lines, you can draw the lines more easily using the *PolyLine* function. This statement draws the same rectangle as in the code shown above:

```
PolyLine (hDC, &pt, 5) ;
```

The last parameter is the number of points. We could also have represented this value by (sizeof pt / sizeof (POINT)). PolyLine has the same effect as an initial MoveTo function followed by multiple LineTo functions. However, PolyLine doesn't use or change the current pen position.

The Arc function is a little more complex. Here's the general syntax:

The Arc function draws a line on the circumference of an ellipse that is bounded by a rectangle with the upper left corner at (xLeft, yTop) and the lower right corner at (xRight, yBottom). The arc starts at the intersection of the ellipse and the line connecting (xStart, yStart) with the center of the ellipse. The arc is drawn counterclockwise around the circumference of the ellipse and ends at the intersection of the ellipse and the line connecting point (xEnd, yEnd) with the center of the ellipse. If you're having trouble visualizing this, don't worry about it—I'll discuss the Arc function in much more detail after we've covered rectangles and ellipses.

Using Stock Pens

When you call *LineTo*, *PolyLine*, or *Arc*, Windows uses the "pen" currently selected in the device context to draw the line. The pen determines the line's color, its width, and its style, which can be solid, dotted, or dashed. The pen in the default device context is called BLACK_PEN. This pen draws a solid black line with a width of one physical pixel regardless of the mapping mode. BLACK_PEN is one of three "stock pens" that Windows provides. The other two are WHITE_PEN and NULL_PEN. NULL_PEN is a pen that doesn't draw. You can also create your own customized pens.

In your Windows programs, you refer to pens with a handle. WINDOWS.H includes a type definition named HPEN, a handle to a pen. You can define a variable (for instance, hPen) using this type definition:

```
HPEN hPen ;
```

You obtain the handle to one of the stock pens by a call to GetStockObject. For instance, suppose you want to use the stock pen called WHITE_PEN. You get the pen handle like this:

```
hPen = GetStockObject (WHITE_PEN) ;
```

Now you must make that pen the currently selected pen in the device context, which requires a call to SelectObject:

```
SelectObject (hDC, hPen) ;
```

After this call, the lines you draw using *LineTo*, *PolyLine*, or *Arc* will use WHITE_PEN until you select another pen into the device context or release the device context.

Rather than explicitly defining an hPen variable, you can instead combine the GetStockObject and SelectObject calls in one statement:

```
SelectObject (hDC, GetStockObject (WHITE_PEN));
```

If you then want to return to using BLACK_PEN, you can get the handle to that stock object and select it into the device context in one statement:

```
SelectObject (hDC, GetStockObject (BLACK_PEN));
```

SelectObject returns the handle to the pen that had been previously selected into the device context. If you start off with a fresh device context and call:

```
hPen = SelectObject (hDC, GetStockObject (WHITE_PEN)) ;
```

then the current pen in the device context will be WHITE_PEN, and the variable hPen will be the handle to BLACK_PEN. You can then select BLACK_PEN into the device context by calling:

```
SelectObject (hDC, hPen) ;
```

Creating, Selecting, and Deleting Pens

Although the pens defined as stock objects are certainly convenient, you are limited to only a solid black pen, a solid white pen, or no pen at all. If you want to get fancier than that, you must create your own pens. Here's the general procedure: You create a "logical pen," which is merely the description of a pen, using the function CreatePen or CreatePenIndirect. These functions return a handle to the logical pen. You select the pen into the device context by calling SelectObject. You can then draw lines with this new pen. Only one pen can be selected into the device context at any one time. After you release the device context (or after

you select another pen into the device context), you can delete the logical pen you've created by calling *DeleteObject*. When you do so, the handle to the pen is no longer valid.

A logical pen is a "GDI object." You create and use the pen, but the pen doesn't belong to your program. The pen really belongs to the GDI module. A pen is one of five GDI objects that you can create. The other four are brushes, bitmaps, regions, and fonts.

This brings me to a very important point: Normally, Windows cleans up thoroughly when a program terminates. The one big exception is for GDI objects. When a program terminates, Windows doesn't automatically delete GDI objects that the program has created. The program itself is responsible for deleting GDI objects.

Three rules govern the use of GDI objects such as pens:

- Delete all GDI objects that you create.
- Don't delete GDI objects while they are selected in a valid device context.
- Don't delete stock objects.

These are not unreasonable rules, but they can be a little tricky sometimes. We'll run through some examples to get the hang of how the rules work.

The general syntax for the CreatePen function looks like this:

```
hPen = CreatePen (nPenStyle, nWidth, rgbColor) ;
```

The *nPenStyle* parameter determines whether the pen draws a solid line or a line made up of dots or dashes. The parameter can be one of the following identifiers defined in WINDOWS.H: PS_SOLID, PS_DASH, PS_DOT, PS_DASHDOT, PS_DASHDOTDOT, and PS_NULL. Figure 13-1 shows the kind of line that each of these styles produces.

PS_SOLID	
PS_DASH	
PS_DOT	******
PS_DASHDOT	
PS_DASHDOTDOT	
PS_NULL	

Figure 13-1. The six pen styles

For the PS_SOLID and PS_NULL styles, the nWidth parameter is the width of the pen in logical units. For instance, if the mapping mode is MM_LOENGLISH, a pen with an nWidth of 10 will be 0.1 in. wide. When you draw a line with this pen, the width of the pen will extend 0.05 in. on either side of the line. For the MM_ANISOTROPIC mapping mode, Windows uses logical units on the x axis to determine the physical width of the pen. An nWidth value of 0 directs Windows to use one physical unit (1 pixel) for the pen width. The stock pens are 1 pixel wide. If you specify a dotted or dashed pen style with a physical width greater than 1, Windows will use a solid pen instead.

The *rgbColor* parameter to *CreatePen* is an unsigned long integer specifying the color of the pen. When you select the pen into the device context, Windows converts this parameter to the nearest pure color that the device can represent. Pens cannot use dithered colors. (On most displays, this means that pens cannot be gray.)

You can also create a pen by setting up a structure of type LOGPEN ("logical pen") and calling *CreatePenIndirect*. If your program uses a lot of different pens that you can initialize in your source code, this method is more efficient. First you define a structure variable of type LOGPEN—for instance, *logpen*:

```
LOGPEN logpen ;
```

This structure has three members: lopnStyle (WORD) is the pen style, lopnWidth (POINT) is the pen width in logical units, and lopnColor(DWORD) is the pen color. The lopnWidth member is a structure of type POINT, but Windows uses only the lopnWidth.x value for the pen width and ignores lopnWidth.y. Then you create the pen by passing the address of the structure to CreatePenIndirect:

```
hPen = CreatePenIndirect (&logpen) ;
```

You can also obtain the logical pen information for an existing pen. If you already have a handle to a pen, you can copy the data that defines the logical pen into a structure of type LOGPEN by using the *GetObject* call:

```
GetObject (hPen, sizeof (LOGPEN), (LPSTR) &logpen) ;
```

Note that the *CreatePen* and *CreatePenIndirect* functions do not require a handle to a device context. These functions create logical pens that have no connection with a device context until you call *SelectObject*. For instance, you can use the same logical pen for several different devices, such as the screen and a printer. Logical pens with a nonzero *nWidth* have a logical width; they have a physical width only when you select the pen into a device context, and then the physical width depends on the device context's mapping mode.

Here's one method for creating, selecting, and deleting pens. Suppose your program uses three pens, a black pen of width 1, a red pen of width 3, and a black dotted pen. You can first define variables for storing the handles to these pens:

```
static HPEN hPen1, hPen2, hPen2;
```

During processing of WM_CREATE, you can create the three pens:

```
hPen1 = CreatePen (PS_SOLID, 1, 0L);
hPen2 = CreatePen (PS_SOLID, 3, RGB (255, 0, 0));
hPen2 = CreatePen (PS_DOT, 0, 0L);
```

During processing of WM_PAINT (or any other time you have a valid handle to a device context), you can select one of these pens into the device context and draw with it:

```
SelectObject (hDC, hPen2);

[LineTo, PolyLine, or Arc calls]

SelectObject (hDC, hPen1);

[other LineTo, PolyLine, or Arc calls]
```

During processing of WM_DESTROY, you can delete the three pens you created:

```
DeleteObject (hPen1);
DeleteObject (hPen2);
DeleteObject (hPen3);
```

This is the most straightforward method for creating, selecting, and deleting pens, but it requires that the logical pens take up memory space during the entire time your program is running. You might instead want to create the pens during each WM_PAINT message and delete them after you call *EndPaint*. (You can delete them before calling *EndPaint*, but you have to be careful not to delete the pen currently selected in the device context.)

You might also want to create pens on the fly and combine the CreatePen and Select-Object calls in the same statement:

```
SelectObject (hDC, CreatePen (PS_DASH, 0, RGB (255, 0, 0)));
```

Now when you draw lines, you'll be using a red dashed pen. When you're finished drawing the red dashed lines, you can delete the pen. Whoops! How can you delete this pen when you haven't saved the pen handle? Recall that SelectObject returns the handle to the pen previously selected in the device context. So you can delete the pen by selecting the stock BLACK_PEN into the device context and deleting the value returned from SelectObject:

```
DeleteObject (SelectObject (hDC, GetStockObject (BLACK_PEN))) ;
```

Here's another method. When you select a newly created pen into the device context, save the handle to the pen that SelectObject returns:

```
hPen = SelectObject (hDC, CreatePen (PS_DASH, 0, RGB (255, 0, 0)));
```

What is hPen? If this is the first SelectObject call you've made since obtaining the device context, hPen is a handle to the BLACK_PEN stock object. You can now select that pen into the device context and delete the pen you created (the handle returned from this second Select-Object call) in one statement:

```
DeleteObject (SelectObject (hDC, hPen));
```

If you delete a GDI object while it is selected in a device context and then try to draw lines, Windows will respond with a fatal error because the device context doesn't contain a valid pen. This is a fairly obvious bug to track down. Failing to delete GDI objects that you create can be a more difficult bug to discover, because the program will appear to work fine. If your program creates the same logical pen for every WM_PAINT message, you might want to cause the client area to be repainted over and over and check to see if free memory starts to drop. The FREEMEM program shown in Chapter 6 can identify problems related to dropping memory. If HEAPWALK shows a lot of small GDI segments after your program has terminated, some of them may be GDI objects you have failed to delete properly.

Avoiding Device Dependencies

Pen widths will vary according to the resolution of the display. The stock pens (and any pen created with a width of 0) are 1 pixel wide, which on a high-resolution display can result in very thin lines. If you're working in MM_TEXT, you might want to obtain the width of the single-line window border by calling GetSystemMetrics with the SM_CXBORDER and SM_CYBORDER indexes. These values are appropriate for pen widths. You can also use one of the metric mapping modes and set specific physical widths for the pens your program needs to create.

Pen colors are also susceptible to device dependencies. If you develop a program on a color display and then run the program on a monochrome display, you can be in for some unpleasant surprises. Windows always uses pure colors for pens, and on a monochrome system, pens are either black or white. For instance, on your color EGA, you might be fond of magenta pens on a white background:

```
hPen = CreatePen (PS_SOLID, 1, RGB (255, 0, 255));
```

But on a monochrome system, the pure color that is closest to magenta is white, so the pen will be invisible. If you want to use colored pens, be sure the sum of the red, green, and blue values is less than 384 (half the maximum sum of the three primaries) for any pen that should default to black and greater than 384 for any pen that should default to white.

Filling in the Gaps

The use of dotted and dashed pens raises an interesting question: What happens to the gaps between the dots and the dashes? The coloring of the gaps depends on both the background mode and the background color attributes defined in the device context. The default background mode is OPAQUE, which means that Windows fills in the gaps with the background color, which by default is white. This is consistent with the WHITE_BRUSH that many programs use in the window class for erasing the background of the window.

You can change the background color that Windows uses to fill in the gaps by calling:

```
SetBkColor (hDC, rgbColor) ;
```

As with the *rgbColor* value used for the pen color, Windows converts this background color to a pure color. You can obtain the current background color defined in the device context by calling *GetBkColor*.

You can also prevent Windows from filling in the gaps by changing the background mode to TRANSPARENT:

SetBkMode (hDC, TRANSPARENT) ;

Windows will ignore the background color and will not fill in the gaps. You can obtain the current background mode (either TRANSPARENT or OPAQUE) by calling GetBkMode.

Drawing Modes

The appearance of lines drawn on the display is also affected by the drawing mode defined in the device context. Imagine drawing a line that has a color based not only on the color of the pen but also on the original color of the display area where the line is drawn. Imagine a way in which you could use the same pen to draw a black line on a white surface and a white line on a black surface without knowing what color the surface is. Could such a facility be useful to you? It's made possible by the drawing mode.

When Windows uses a pen to draw a line, it actually performs a logical (Boolean) operation between the pixels of the pen and the pixels of the destination display surface. Performing a logical operation with pixels is called a "raster operation," or "ROP." Because drawing a line involves only two pixel patterns (the pen and the destination), the logical operation is called a "binary raster operation," or "ROP2." Windows defines 16 ROP2 codes that indicate how Windows logically combines the pen pixels and the destination pixels. In the default device context, the drawing mode is defined as R2_COPYPEN, which means that Windows simply copies the pixels of the pen to the destination, which is how we normally think about pens. There are 15 other ROP2 codes.

Where do these 16 different ROP2 codes come from? For illustration purposes, I'll use a monochrome system. Let's assume that the destination color (the color of the window's client area) can be either black (which we'll represent by a 0) or white (1). The pen also can be either black or white. There are four combinations of using a black or white pen to draw on a black or white destination: a white pen on a white destination, a white pen on a black destination, a black pen on a white destination.

What happens to the destination after you draw with the pen? One possibility is that the line is always drawn as black regardless of the pen or destination color: This drawing mode is indicated by the ROP2 code R2_BLACK. Another possibility is that the line is drawn as black except when both the pen and destination are black, in which case the line is drawn as white. Although this might be a little strange, Windows has a name for it: The drawing mode is called R2_NOTMERGEPEN. Windows performs a logical OR operation on the destination pixels and the pen pixels and then inverts that result.

The following table shows all 16 ROP2 drawing modes. The table indicates how the original pen (P) and destination (D) colors are combined for the resultant destination color.

The column labeled "Boolean Operation"	uses C notation to show how the destination pix-
els and pen pixels are combined.	

Pen (P): Destination (D):	1 1	0	0	0	Boolean Operation	Drawing Mode
Results:	0	0	0	0	0	R2_BLACK
	0	0	0	1	-(P D)	R2_NOTMERGEPEN
	0	0	1	0	~P & D	R2_MASKNOTPEN
	0	0	1	1	~p	R2_NOTCOPYPEN
	0	1	0	0	P & -D	R2_MASKPENNOT
	0	1	0	1	-D	R2_NOT
	0	1	1	0	$P \wedge D$	R2_XORPEN
	0	1	1	1	-(P & D)	R2_NOTMASKPEN
	1	0	0	0	P & D	R2_MASKPEN
	1	0	0	1	~(P ^ D)	R2_NOTXORPEN
	1	0	1	0	D	R2_NOP
	1	0	1	1	~P D	R2_MERGENOTPEN
	1	1	0	0	P	R2_COPYPEN (default)
	1	1	0	1	P -D	R2_MERGEPENNOT
	1	1	1	0	PD	R2_MERGEPEN
	1	1	1	1	1	R2_WHITE

You can set a new drawing mode in the device context by:

SetROP2 (hDC, nDrawMode) ;

The *nDrawMode* parameter is one of the values listed in the "Drawing Mode" column of the table. You can obtain the current drawing mode using the function:

```
nDrawMode = GetROP2 (hDC) ;
```

The device context default is R2_COPYPEN, which simply transfers the pen color to the destination. The R2_NOTCOPYPEN mode draws white if the pen color is black and black if the pen color is white. The R2_BLACK mode always draws black, regardless of the color of the pen or the background. Likewise, the R2_WHITE mode always draws white. The R2_NOP mode is a "no operation": It leaves the destination unchanged.

We started out using an example of a pure monochrome system. In reality, Windows can simulate various shades of gray by dithering black and white pixels. When drawing a pen on a dithered background, Windows simply performs the logical operation on a pixel-by-pixel basis. The R2_NOT mode always inverts the destination, again regardless of the color of the pen. This mode is useful when you don't know the color of the background, because it guarantees that the pen will be visible. (Well, *almost* guarantees—if the background is a 50 percent gray, then the pen will be invisible.)

The ROP2LOOK Program

The ROP2LOOK program, shown in Figure 13-2, lets you experiment with these 16 ROP2 codes.

```
rop2look.obj : rop2look.c
    cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp rop2look.c

rop2look.res : rop2look.rc
    rc -r rop2look.rc

rop2look.exe : rop2look.obj rop2look.def rop2look.res
    link4 rop2look, /align:16, /map, slibw, rop2look
    rc rop2look.res
```

```
/* ROP2LOOK.C -- ROP2 Demonstration Program */
#include <windows.h>
long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG) ;
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
    HANDLE hInstance, hPrevInstance;
                lpszCmdLine ;
     LPSTR
                nCmdShow ;
     static char szAppName [] = "Rop2Look" ;
                hWnd ;
     HWND
     MSG
                msg ;
     WNDCLASS
                wndclass ;
     if (!hPrevInstance)
         wndclass.style
                                = CS HREDRAW | CS VREDRAW ;
         wndclass.lpfnWndProc = WndProc ;
         wndclass.cbClsExtra = 0;
         wndclass.cbWndExtra = 0;
wndclass.cbWndExtra = 0;
wndclass.bTnstance = hInstance;
         wndclass.hbrBackground = GetStockObject (WHITE BRUSH) ;
          wndclass.lpszMenuName = szAppName
         wndclass.lpszClassName = szAppName ;
          if (!RegisterClass (&wndclass))
              return FALSE ;
     hWnd = CreateWindow (szAppName, "ROP2 Demonstration Program",
                        WS OVERLAPPEDWINDOW,
                        CW USEDEFAULT, 0,
                        CW USEDEFAULT, 0,
                        NULL, NULL, hInstance, NULL) ;
     ShowWindow (hWnd, nCmdShow) ;
     UpdateWindow (hWnd) ;
```

Figure 13-2. The ROP2LOOK program

(continued)

Figure 13-2. Continued

```
while (GetMessage (&msg, NULL, 0, 0))
           TranslateMessage (&msg) ;
           DispatchMessage (&msg) ;
     return msg.wParam ;
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
                   hWnd ;
     unsigned
                    iMessage ;
     WORD
                    wParam ;
     LONG
                    lParam ;
     static LOGPEN lpBlack = { PS_SOLID, 1, 1, RGB ( 0, 0, 0) }, lpWhite = { PS_SOLID, 1, 1, RGB (255, 255, 255) };
     static short nDrawingMode = R2 COPYPEN ;
                    hDC ;
     HDC
     HMENU
                    hMenu ;
                    hPenBlack, hPenWhite;
     HPEN
     PAINTSTRUCT ps ;
                    rect :
     RECT
     short
                    i;
     switch (iMessage)
           case WM COMMAND:
                hMenu = GetMenu (hWnd) ;
                CheckMenuItem (hMenu, nDrawingMode, MF_UNCHECKED) ;
                nDrawingMode = wParam ;
                CheckMenuItem (hMenu, nDrawingMode, MF_CHECKED) ;
                InvalidateRect (hWnd, NULL, FALSE) ;
                break ;
           case WM PAINT:
                hDC = BeginPaint (hWnd, &ps) ;
                hPenBlack = CreatePenIndirect (&lpBlack) ;
                hPenWhite = CreatePenIndirect (&lpWhite) ;
                SetMapMode (hDC, MM ANISOTROPIC) ;
                GetClientRect (hWnd, &rect);
SetViewportExt (hDC, rect.right, rect.bottom);
                SetWindowExt (hDC, 10, 4) ;
                for (i = 0 ; i < 10 ; i += 2)
                      SetRect (&rect, i, 0, i + 2, 4) ;
                      FillRect (hDC, &rect, GetStockObject (i / 2)) ;
                SetROP2 (hDC, nDrawingMode) ;
                SelectObject (hDC, hPenWhite) ;
                MoveTo (hDC, 1, 1);
LineTo (hDC, 9, 1);
                SelectObject (hDC, hPenBlack) ;
                MoveTo (hDC, 1, 3) ;
LineTo (hDC, 9, 3) ;
                EndPaint (hWnd, &ps) ;
```

Figure 13-2. Continued

```
DeleteObject (hPenBlack);
DeleteObject (hPenWhite);
break;

case WM_DESTROY:
PostQuitMessage (0);
break;

default:
return DefWindowProc (hWnd, iMessage, wParam, lParam);

return OL;
}

return OL;
}
```

```
Rop2Look MENU
      BEGIN
             POPUP "&Drawing Mode"
                   BEGIN
                          MENUITEM "O R2 BLACK",
                          MENUITEM "1 R2 NOTMERGEPEN",
                          MENUITEM "2 R2 MASKNOTPEN",
MENUITEM "3 R2 NOTCOPYPEN",
MENUITEM "4 R2 MASKPENNOT",
                                                                    3
                                                                    5
                          MENUITEM "5 R2 NOT",
                          MENUITEM "6 R2 XORPEN",
                                                                  7
                          MENUITEM "7 R2_NOTMASKPEN", 8
MENUITEM "8 R2_MASKPEN", 9
                          MENUITEM "9 R2 NOTXORPEN",
                                                                  10
                          MENUITEM "A R2 NOP",
                                                                  11
                          MENUITEM "B R2 MERGENOTPEN", 12
MENUITEM "C R2 COPYPEN", 13
MENUITEM "D R2 MERGEPENNOT", 14
                                                                   13, CHECKED
                          MENUITEM "E R2 MERGEPEN",
                                                                  15
                          MENUITEM "F R2 WHITE",
                                                                  16
                    END
      END
```

```
ROP ~ LOOK · DEF
```

```
ROP2LOOK
NAME
DESCRIPTION
              'ROP2 Demonstration Program (C) Charles Petzold, 1987'
STUB
              'WINSTUB.EXE'
CODE
              MOVEABLE
DATA
              MOVEABLE MULTIPLE
HEAPSIZE
              1024
STACKSIZE
              4096
EXPORTS
              WndProc
```

The program draws a background divided into five sections colored with the white, light gray, gray, dark gray, and black stock brushes (a subject that we'll get to soon). It then draws two very thick pens: a white pen on the top and a black pen on the bottom. You can select one of the 16 ROP2 codes from the menu. Figure 13-3 shows the white pen on the top and the black pen on the bottom with the drawing mode set to R2_NOTMERGEPEN: The white pen always displays as black, and the black pen inverts the destination.




Figure 13-3. The ROP2LOOK display with the drawing mode set to R2_NOTMERGEPEN

ROP2LOOK uses initialized logical pen structures for the white and black pens. You'll note that both these pens have a logical width of 1. Why do they appear so thick? The program uses the MM_ANISOTROPIC mapping mode and sets the width of the client area to 10 logical units and the height to 4 logical units. The pens are therefore one-tenth the width of the client area.

ROP2 and Color

The drawing mode gets more interesting—and much more complex—when color is introduced. Let's look at a display capable of eight pure colors (such as the EGA). The pen can be any of these eight pure colors, and for simplicity's sake, let's restrict the background to these colors also. The eight colors are combinations of the bits in the red, green, and blue color planes, as shown in the following table—a 1 means the color is illuminated, and a 0 means the color is off.

Red	Green	Blue	Pure Color
0	0	0	Black
0	0	1	Blue
0	1	0	Green
0	1	1	Cyan
1	0	0	Red
1	0	1	Magenta
1	1	0	Yellow
1	1	1	White

Each of the three color planes is affected separately by the raster operation. For example, say you have a cyan background color and a magenta pen color, and your drawing mode is R2_NOTMERGEPEN. What color will the pen actually draw? For red, the pen is 1 (has red), and the destination is 0 (no red). Looking at the ROP2 table on page 551, you see that the result is 0 (no red). For green, the pen is 0 (no green), and the destination is 1 (has green), so the result is 0 (no green). For blue, the pen is 1 (has blue), and the destination is 1 (has blue), so the result is 0 (no blue). Thus the line has no red, no green, and no blue. The color will be black.

Let's take the R2_XORPEN drawing mode, which performs a logical exclusive OR operation on each of the possible combinations in the three color planes. The following table shows the resultant color for all combinations of the eight destination colors and the eight pen colors.

	Pen Color							
Destination	Black	Blue	Green	Cyan	Red	Magenta	Yellow	White
Black	Black	Blue	Green	Cyan	Red	Magenta	Yellow	White
Blue	Blue	Black	Cyan	Green	Magenta	Red	White	Yellow
Green	Green	Cyan	Black	Blue	Yellow	White	Red	Magenta
Cyan	Cyan	Green	Blue	Black	White	Yellow	Magenta	Red
Red	Red	Magenta	Yellow	White	Black	Blue	Green	Cyan
Magenta	Magenta	Red	White	Yellow	Blue	Black	Cyan	Green
Yellow	Yellow	White	Red	Magenta	Green	Cyan	Black	Blue
White	White	Yellow	Magenta	Red	Cyan	Green	Blue	Black

At the beginning of Chapter 12 I mentioned that Windows GDI is strong in the area of raster operations. The drawing mode is one example of that. And if you think that you'll probably never ever use some of these ROP2 codes, just wait until you see the regular raster operation codes in Chapter 14—there are more than two hundred raster operations that you'll probably never use. But it's nice to know that they're available.

DRAWING FILLED AREAS

Now let's take the next step up, from drawing lines to drawing figures. Windows' six functions for drawing filled figures with borders are listed in the chart below:

Function	Figure
Rectangle	Rectangle with square corners
Ellipse	Ellipse
RoundRect	Rectangle with rounded corners
Chord	Arc on the circumference of an ellipse with endpoints connected by a chord
Pie	Pie wedge on the circumference of an ellipse
Polygon	Multisided figure

Windows draws the outline of the figure with the current pen selected in the device context. The current background mode, background color, and drawing mode are all used for this outline, just as if Windows were drawing a line. Everything we learned about lines also applies to the border around these figures.

The figure is filled with the current brush selected in the device context. By default, this is the stock object called WHITE_BRUSH, which means that the interior will be drawn as white. Windows defines six stock brushes: WHITE_BRUSH, LTGRAY_BRUSH, GRAY_BRUSH, DKGRAY_BRUSH, BLACK_BRUSH, and NULL_BRUSH (or HOLLOW_BRUSH). The first five of these brushes were used to color the client area of ROP2LOOK. LTGRAY_BRUSH is 25 percent black, GRAY_BRUSH is 50 percent black and 50 percent white, and DKGRAY_BRUSH is 75 percent black. When inverted, LTGRAY_BRUSH becomes DKGRAY_BRUSH and GRAY_BRUSH remains the same (as you can determine by experimenting with ROP2LOOK).

You can select one of the stock brushes into your device context the same way you select a stock pen. Windows defines HBRUSH to be a handle to a brush, so you can first define a variable for the brush handle:

```
HBRUSH hBrush ;
```

You can get the handle to GRAY_BRUSH by calling GetStockObject:

```
hBrush = GetStockObject (GRAY_BRUSH) ;
```

You can select it into the device context by calling SelectObject:

```
SelectObject (hDC, hBrush) ;
```

Now when you draw one of these figures, the interior will be gray.

If you want to draw a figure without a border, select the NULL_PEN into the device context:

```
SelectObject (hDC, GetStockObject (NULL_PEN));
```

Or you can use the R2_NOP drawing mode:

```
SetROP2 (hDC, R2_NOP) ;
```

If you want to draw the outline of the figure but not fill in the interior, select the NULL_BRUSH into the device context:

```
SelectObject (hDC, GetStockObject (NULL_BRUSH));
```

You can also create customized brushes just as you can create customized pens. We'll cover that topic shortly.

The Bounding Box

The Rectangle, Ellipse, RoundRect, Chord, and Pie functions (as well as the Arc line-drawing function) are all similar in that they are built up from a rectangular "bounding box." You define the coordinates of a box that encloses the object—a bounding box—and Windows draws the object within this box.

The simplest filled object is the rectangle:

```
Rectangle (hDC, xLeft, yTop, xRight, yBottom) ;
```

The point (xLeft, yTop) is the upper left corner of the rectangle, and (xRight, yBottom) is the lower right corner; both points are expressed in logical units. A figure drawn using the Rectangle function is shown in Figure 13-4.




Figure 13-4. A figure drawn using the Rectangle function


In the MM_TEXT mapping mode, xRight must be greater than xLeft, and yBottom must be greater than yTop. However, in all the other mapping modes (except possibly MM_ISOTROPIC and MM_ANISOTROPIC), the value of yBottom is less than that of yTop because the coordinates on the y axis increase as you move up.

Programmers who have worked with graphics before are accustomed to the problem of being off by 1 pixel. Some graphics systems draw a figure to encompass the right and bottom coordinates, and some draw figures up to (but not including) the right and bottom coordinates. Windows uses the latter approach, but there's an easier way to think about it.

Consider the function call-

```
Rectangle (hDC, 1, 1, 5, 4) ;
```

I mentioned above that Windows draws the figure within a "bounding box." You can think of the display as a grid where each pixel is within a grid cell. The imaginary bounding box is drawn on the grid, and the rectangle is then drawn within this bounding box. Here's how the figure would be drawn in the MM_TEXT mapping mode:



The area separating the rectangle from the top and left of the client area is 1 pixel wide. Windows uses the current brush to color the 2 pixels on the inside of the rectangle. If the pen used to draw the outline is greater than 1 pixel in width, then the pen is centered on the border.

Once you know how to draw a rectangle, then you also know how to draw an ellipse, because it uses the same parameters:

```
Ellipse (hDC, xLeft, yTop, xRight, yBottom) ;
```

A figure drawn using the *Ellipse* function is shown (with the imaginary bounding box) in Figure 13-5.




Figure 13-5. A figure drawn using the Ellipse function

Windows does not include "square" or "circle" functions. In all mapping modes except MM_TEXT and MM_ANISOTROPIC, you can easily draw squares and circles using the Rectangle and Ellipse functions by making the difference between xLeft and xRight the same as the difference between yTop and yBottom. In MM_TEXT, squares and circles are a little more difficult. You have to call GetDeviceCaps with the ASPECTX and ASPECTY indexes and scale the dimensions based on the aspect ratio of the pixels. In MM_ANISOTROPIC, you also have to take into account the ratio of the window and viewport extents.

The function to draw rectangles with rounded corners uses the same bounding box as the Rectangle and Ellipse functions but includes two more parameters:

```
RoundRect (hDC, xLeft, yTop, xRight, yBottom, xCornerEllipse, yCornerEllipse);
```

A figure drawn using this function is shown in Figure 13-6.




Figure 13-6. A figure drawn using the RoundRect function

Windows uses a small ellipse to draw the rounded corners. The width of this ellipse is xCornerEllipse, and the height is yCornerEllipse, with both points expressed in logical units. Imagine Windows splitting this small ellipse into four quadrants and using one quadrant for each of the four corners. The rounding of the corners is more pronounced for larger values of xCornerEllipse and yCornerEllipse. If xCornerEllipse is equal to the difference between xLeft and xRight and yCornerEllipse is equal to the difference between yTop and yBottom, then the RoundRect function will draw an ellipse.

The rounded rectangle shown in Figure 13-6 was drawn using the MM_TEXT mapping mode with the corner ellipse dimensions calculated with these formulas:

```
xCornerEllipse = (xRight - xLeft) / 4;
yCornerEllipse = (yBottom - yTop) / 4;
```

This is an easy approach, but the results admittedly don't look quite right, because the rounding of the corners is more pronounced along the larger rectangle dimension. To correct this

problem, you'll probably want to make xCornerEllipse equal to yCornerEllipse in real dimensions.

The Arc, Chord, and Pie functions all take identical parameters:

```
Arc (hDC, xLeft, yTop, xRight, yBottom, xStart, yStart, xEnd, yEnd);

Chord (hDC, xLeft, yTop, xRight, yBottom, xStart, yStart, xEnd, yEnd);

Pie (hDC, xLeft, yTop, xRight, yBottom, xStart, yStart, xEnd, yEnd);
```

A line drawn using the Arc function is shown in Figure 13-7; figures drawn using the Chord and Pie functions are shown in Figures 13-8 and 13-9 (on the following page).




Figure 13-7. A line drawn using the Arc function




Figure 13-8. A figure drawn using the Chord function






Figure 13-9. A figure drawn using the Pie function

Windows uses an imaginary line to connect (xStart, yStart) with the center of the ellipse. At the point at which that line intersects the ellipse, Windows begins drawing an arc in a counterclockwise direction around the circumference of the ellipse. Windows also uses an imaginary line to connect (xEnd, yEnd) with the center of the ellipse. At the point at which that line intersects the ellipse, Windows stops drawing the arc.

For the Arc function, Windows is now finished, because the arc is an elliptical line rather than a filled area. For the Chord function, Windows connects the endpoints of the arc. For the Pie function, Windows connects each endpoint of the arc with the center of the ellipse. The interiors of the chord and pie-wedge figures are filled with the current brush.

The ARCS Program

You may wonder about this use of starting and ending positions in the Arc, Chord, and Pie functions. Why not simply specify starting and ending points on the circumference of the ellipse? Well, you can, but you would have to figure out what those points are. Windows' method gets the job done without requiring such specificity.

You can experiment with arcs, chords, and pie wedges using the ARCS program, shown in Figure 13-10. The program draws the bounding box and the ellipse using a dotted pen. Your menu choice determines whether the program draws an arc, a chord, or a pie wedge. The line or figure is drawn with a pen that is 3 pixels wide. The starting and ending points are connected to the center of the ellipse with a normal black pen.

```
arcs.obj : arcs.c arcs.h
cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp arcs.c
arcs.res : arcs.rc arcs.h
rc -r arcs.rc
```

Figure 13-10. The ARCS program

(continued)

Figure 13-10. Continued

```
arcs.exe : arcs.obj arcs.def arcs.res
link4 arcs, /align:16, /map, slibw, arcs
rc arcs.res
```

```
/* ARCS.C -- Demonstrates Drawing Arcs, Chords, and Pies with GDI */
#include <windows.h>
#include "arcs.h"
long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG) ;
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
    HANDLE
             hInstance, hPrevInstance;
    LPSTR
                lpszCmdLine ;
    int
                nCmdShow ;
    static char szAppName [] = "Arcs" ;
                hWnd ;
    HWND
    MSG
                msq ;
    WNDCLASS
                wndclass ;
    if (!hPrevInstance)
         wndclass.style
                               = CS_HREDRAW | CS_VREDRAW ;
         wndclass.lpfnWndProc = WndProc ;
         wndclass.cbClsExtra
                              = 0;
         wndclass.cbWndExtra
         wndclass.hCursor = LoadCursor (NULL, IDC_ARROW) ;
         wndclass.hbrBackground = GetStockObject (WHITE BRUSH) ;
         wndclass.lpszMenuName = szAppName ;
         wndclass.lpszClassName = szAppName ;
         if (!RegisterClass (&wndclass))
              return FALSE :
    hWnd = CreateWindow (szAppName, "Arcs, Chords, and Pies",
                        WS OVERLAPPEDWINDOW,
                        CW USEDEFAULT, 0,
                        CW_USEDEFAULT, 0,
NULL, NULL, hInstance, NULL) ;
    ShowWindow (hWnd, nCmdShow) ;
    UpdateWindow (hWnd) ;
    while (GetMessage (&msg, NULL, 0, 0))
         TranslateMessage (&msq) :
         DispatchMessage (&msg) ;
    return msg.wParam ;
```

(continued)

Figure 13-10. Continued

```
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
     HWND
                hWnd ;
    unsigned
                 iMessage ;
                  wParam ;
    WORD
     LONG
                 lParam ;
    static short xClient, yClient, x1, x2, x3, x4, y1, y2, y3, y4,
                  nFigure = IDM_ARC ;
                  hDC ;
    HDC
    HMENU
                 hMenu ;
    HPEN
                 hPen ;
    PAINTSTRUCT ps ;
    short
                 x, y ;
    switch (iMessage)
          case WM SIZE:
               x3 = y3 = 0;
               x4 = xClient = LOWORD (1Param) ;
               y4 = yClient = HIWORD (1Param) ;
               x2 = 3 * (x1 = xClient / 4) ;
               y2 = 3 * (y1 = yClient / 4) ;
               break ;
          case WM COMMAND:
               switch (wParam)
                    case IDM ARC:
                    case IDM CHORD:
                    case IDM PIE:
                         hMenu = GetMenu (hWnd) ;
                         CheckMenuItem (hMenu, nFigure, MF UNCHECKED) ;
                         CheckMenuItem (hMenu, nFigure = wParam, MF_CHECKED)
                         InvalidateRect (hWnd, NULL, FALSE) ;
                         break :
               break ;
          case WM_LBUTTONDOWN:
               if (!(wParam & MK SHIFT))
                    x3 = LOWORD (1Param) ;
                    y3 = HIWORD (1Param) ;
                    InvalidateRect (hWnd, NULL, TRUE) ;
                    break :
                                        /* fall through for MK_SHIFT */
          case WM RBUTTONDOWN:
               x4 = LOWORD (1Param) ;
               y4 = HIWORD (1Param) ;
               InvalidateRect (hWnd, NULL, TRUE) ;
               break ;
          case WM PAINT:
               hDC = BeginPaint (hWnd, &ps) ;
               hPen = SelectObject (hDC, CreatePen (PS_DOT, 1, OL)) ;
               Rectangle (hDC, x1, y1, x2, y2) ;
               Ellipse
                         (hDC, x1, y1, x2, y2);
               DeleteObject (SelectObject (hDC, CreatePen (PS_SOLID, 3, OL)))
```

Figure 13-10. Continued

```
switch (nFigure)
               case IDM ARC:
                     Arc (hDC, x1, y1, x2, y2, x3, y3, x4, y4) ;
                     break ;
               case IDM CHORD:
                     Chord (hDC, x1, y1, x2, y2, x3, y3, x4, y4);
               case IDM PIE:
                     Pie (hDC, x1, y1, x2, y2, x3, y3, x4, y4);
          DeleteObject (SelectObject (hDC, hPen)) ;
          MoveTo (hDC, x3, y3);
LineTo (hDC, xClient / 2, yClient / 2);
          LineTo (hDC, x4, y4) ;
          EndPaint (hWnd, &ps) ;
          break ;
     case WM DESTROY:
          PostQuitMessage (0) ;
          break ;
     default:
          return DefWindowProc (hWnd, iMessage, wParam, 1Param) ;
return OL ;
```

```
#define IDM_ARC 1
#define IDM_CHORD 2
#define IDM_PIE 3
```

```
#include "arcs.h"

Arcs MENU
BEGIN
POPUP "&Options"
BEGIN
MENUITEM "&Arc", IDM ARC, CHECKED
MENUITEM "&Chord", IDM_CHORD
MENUITEM "&Pie", IDM_PIE

END

END
```

(continued)

Figure 13-10. Continued

NAME ARCS 'Arc, Chord, and Pie Drawing Program (C) Charles Petzold, 1987' DESCRIPTION 'WINSTUB. EXE' STUB MOVEABLE CODE MOVEABLE MULTIPLE DATA HEAPSIZE 1024 STACKSIZE 4096 WndProc EXPORTS

When you click on the client area using the left mouse button, ARCS uses that point as the starting point, which is the point (x3, y3) in the program. Clicking on the client area with the right mouse button sets the ending point, the point (x4, y4). Users with a one-button mouse can hold down the Shift key and click the mouse to set the ending point.

ARCS also shows some typical pen-handle manipulation. After the program gets the device context by calling *BeginPaint*, it creates a dotted pen and selects it into the device context:

```
hPen = SelectObject (hDC, CreatePen (PS_DOT, 1, OL));
```

The hPen handle returned from SelectObject is a handle to the stock BLACK_PEN.

When ARCS needs to draw the arc, chord, or pie wedge, it creates a 3-pixel-wide pen and selects that into the device context:

```
DeleteObject (SelectObject (hDC, CreatePen (PS_SOLID, 3, OL))) ;
```

The pen handle returned from SelectObject, which is the handle to the dotted pen, is then deleted using DeleteObject.

When ARCS needs to draw the lines connecting the starting and ending points with the center of the ellipse, it selects hPen—the handle to the stock BLACK_PEN—into the device context and deletes the 3-pixel-wide pen returned from SelectObject:


```
DeleteObject (SelectObject (hDC, hPen)) ;
```

Now the two pens that were created have been deleted. The pen currently selected in the device context is a stock pen, and the device context can be released.

The Trigonometry of Pie Charts

If you use the *Pie* function to create pie charts, the size of each pie wedge will be based on the relative sizes of data items. This involves calculating starting and ending points of the pie figures that are derived from the internal angle of the pie wedge.

It's time for a trigonometry refresher. In a Cartesian coordinate system (with x increasing to the right and y increasing moving up), we can draw a triangle like this:



The relationship between each of the three sides of the triangle and the angle α is given by the formulas:

$$sin(\alpha) = y / r$$

 $cos(\alpha) = x / r$
 $tan(\alpha) = y / x$

If you know the angle α (which in a pie chart will be a fraction of a circle) and r (which will be the radius of the circle), you can determine that the point (x, y) is equal to:

$$(r \cdot \cos(\alpha), r \cdot \sin(\alpha))$$

In the sin and cos functions included with Microsoft C 4.0, the angles are in terms of radians. There are 2 \bullet PI radians in 360 degrees.

Let's try drawing a pie chart that uses five numbers. For convenience, we'll set this condition with a #define statement:

```
#define NUM 5
```

In a real program, that would be a variable.

You'll also find it convenient to define an identifier called TWO_PI that is the number of radians in a circle:

```
#define TWO_PI (2.0 * 3.14159) ;
```

Next you define some variables:

The initialized values in *nValues* are the data we'll be graphing. In a real program, these values would be variables. The *nSum* array is set to the accumulated sum of the data values where the first element of the array is set to 0:

```
nSum [0] = 0 ;
```

The array element nSum [NUM] is the sum of the five values.

Now we are ready to start drawing the pie chart. Set the mapping mode to MM_ISOTROPIC, which is the mode in which you can most easily draw a circle:

```
SetMapMode (hDC, MM_ISOTROPIC) ;
SetWindowExt (hDC, 400, 400) ;
SetViewportExt (hDC, xClient, -yClient) ;
SetViewportOrg (hDC, xClient / 2, yClient / 2) ;
```

The logical point (0,0) is the center of the client area, and the x and y coordinates define a normal Cartesian coordinate system.

Our pie has a radius of 100 logical units. Here's the code to paint the five pie segments:

The pie chart produced from this code is shown in Figure 13-11. The first pie wedge is at the right of the pie chart, just above the x axis. The other pie wedges are drawn in a counterclockwise direction.




Figure 13-11. A pie chart drawn using the Pie function

The values:

```
TWO_PI * nSum [i] / nSum [NUM] and:
```

```
TWO_PI * nSum [i + 1] / nSum [NUM]
```

are ratios of the accumulated sum of the items to the total sum of the items converted to angles that are measured counterclockwise from the horizontal. The second formula includes the item that the particular pie wedge represents; the first does not. By taking the cosine and sine of these angles and multiplying by 100, we're calculating the starting and ending points on the circle.

Note these important points: Whenever you use C floating-point library functions, be sure to include the MATH.H header file in the source code:

#include <math.h>

This informs the C compiler that the math functions take floating-point parameters and return floating-point values. You must also specify the "alternate" math library when you compile the program using this compiler switch:

-FPa

Do not use the Microsoft 8087 libraries or 8087-emulation libraries with Windows programs.

The Polygon Function and the Polygon Filling Mode

Polygon is the sixth and last function for drawing a bordered and filled figure. The function call is similar to the PolyLine function:

Polygon (hDC, 1pPoints, nCount);

The *IpPoints* parameter is a far pointer to an array of POINT structures (in logical coordinates), and *nCount* is the number of points. If the last point in this array is different from the first point, Windows adds another line that connects the last point with the first point. (This does not happen with the *PolyLine* function.)

Windows fills this bounded area with the current brush in one of two ways, depending on the current polygon filling mode defined in the device context. By default, the polygon filling mode is ALTERNATE, which means that Windows fills in only those interiors accessible from the outside of the polygon by crossing an odd number of lines (1, 3, 5, and so forth). The other interiors are not filled. You can also set the polygon filling mode to WINDING, in which case Windows fills in all the interior areas. The two polygon filling modes are most simply demonstrated with a five-pointed star. In Figure 13-12, the star on the left was drawn with the ALTERNATE mode, and the star on the right was drawn with the WINDING mode.




Figure 13-12. Figures drawn with the two polygon filling modes: ALTERNATE (left) and WINDING (right)

Both figures were drawn with an array of points defined like this:

```
static POINT pt [] = { -59, -81, 0, 100, 59, -81, -95, 31, 95, 31 };
```

The five points of the star were manually calculated from trigonometric tables. The WM_PAINT logic looks like this:

```
case WM_PAINT:
    hDC = BeginPaint (hWnd, %ps) ;
    hPen = CreatePen (PS_SOLID, 3, 0L) ;
     SelectObject (hDC, hPen) ;
     SelectObject (hDC, GetStockObject (LTGRAY_BRUSH));
    SetMapMode (hDC, MM_ISOTROPIC) ;
    SetWindowExt (hDC, 440, -220);
    SetViewportExt (hDC, xClient, yClient) ;
     SetWindowOrg (hDC, -110, 110);
     SetPolyFillMode (hDC, ALTERNATE) ;
    Polygon (hDC, pt, sizeof (pt) / sizeof (POINT));
    SetWindowOrg (hDC, -330, 110);
     SetPolyFillMode (hDC, WINDING) ;
     Polygon (hDC, pt, sizeof (pt) / sizeof (POINT));
     EndPaint (hWnd, &ps) ;
     DeleteObject (hPen) ;
    break :
```

Brushing the Interior

The interiors of the *Rectangle*, *RoundRect*, *Ellipse*, *Chord*, *Pie*, and *Polygon* figures are filled in with the current brush (also sometimes called a "pattern") selected in the device context. A brush is an 8 by 8 bitmap that is repeated horizontally and vertically to fill the area.

When Windows uses dithering to display more colors than are normally available on a display, it actually uses a brush for the color. In the discussion of color in Chapter 7, I mentioned that Windows can use dithering of black and white pixels to create 64 different shades of gray. More precisely, Windows can create 64 different monochrome brushes. For pure black, all bits in the 8 by 8 bitmap are 0. One bit out of the 64 is made 1 (that is, white) for the first gray shade, two bits are white for the second gray shade, and so on, until all bits in the 8 by 8 bitmap are 1 for pure white.

On a color video system (such as the EGA), dithered colors are also bitmaps. Because Windows uses three color planes in the EGA, the brush is actually like three separate 8 by 8 monochrome bitmaps. Each plane can have a density of color ranging from all bits set to 0 to all bits set to 1. Windows can thus create brushes for a total of 64 times 64 times 64—or 262,144—dithered colors.

We've already used stock brushes. Windows also has four functions that let you create logical brushes. You select the brush into the device context with *SelectObject*. Like logical pens, logical brushes are GDI objects. Any brush that you create must be deleted, but it must not be deleted while it is selected in the device context.

Here's the first function to create a logical brush:

```
hBrush = CreateSolidBrush (rgbColor) ;
```

The word *Solid* in this function doesn't really mean that the brush is a pure color. When you select the brush into the device context, Windows creates an 8 by 8 bitmap for a dithered color and uses that bitmap for the brush. We used *CreateSolidBrush* in the COLORSCR program in Chapter 7. The brush was used as the background color defined in the window class structure.

You can also create a brush with "hatch marks," which are made up of horizontal, vertical, or diagonal lines. Brushes of this style are most commonly used for coloring the interiors of bar graphs. The function for creating a hatch brush is:

```
hBrush = CreateHatchBrush (nHatchStyle, rgbColor) ;
```

The nHatchStyle parameter describes the appearance of the hatch marks. The parameter can be one of the following styles: HS_HORIZONTAL, HS_VERTICAL, HS_FDIAGONAL, HS_BDIAGONAL, HS_CROSS, and HS_DIAGCROSS. Figure 13-13 shows the kind of hatch marks that each of these styles produces.

HS_HORIZONTAL		HS_BDIAGONAL	11//
HS_VERTICAL	-	HS_CROSS	##
HS_FDIAGONAL	1111	HS_DIAGCROSS	***

Figure 13-13. The six hatch brush styles

The rgbColor parameter of CreateHatchBrush is the color of the hatch lines. When you select the brush into a device context, Windows converts this color to the nearest pure color. The area between the hatch lines is colored based on the background mode and background color defined in the device context. If the background mode is OPAQUE, the background color (which is also converted to a pure color) is used to fill in the spaces between the lines. In this case, neither the hatch lines nor the fill color can be a dithered color. If the background mode is TRANSPARENT, Windows draws the hatch lines without filling in the area between them.

Earlier I discussed the problems that you can encounter with pen colors when you develop a program on a color display and later run the program on a monochrome display. You should beware of the same problems when you choose colors for hatch marks and the brush background. Colored hatch marks that look fine on a color display may disappear into the background when displayed in monochrome.

Because brushes are always 8 by 8 bitmaps, the appearance of hatch brushes will also vary according to the resolution of the device on which they are displayed. Each of the hatch marks shown in Figure 13-13 was drawn in a 32-pixel by 16-pixel rectangle, which means that the 8 by 8 bitmap was repeated 4 times horizontally and 2 times vertically. On a 300-dots-perinch laser printer, the same 32-pixel by 16-pixel rectangle would occupy an area about one-ninth of an inch wide and one-nineteenth of an inch high.

You can also create your own brushes based on bitmaps using CreatePatternBrush:

```
hBrush = CreatePatternBrush (hBitmap) ;
```

This function was discussed in Chapter 9. The *hBitmap* parameter is a handle to an 8 by 8 bitmap. How you get this bitmap handle is covered in the next section of this chapter.

Windows also includes a function that encompasses the three other functions for creating brushes (CreateSolidBrush, CreateHatchBrush, and CreatePatternBrush):

```
hBrush = CreateBrushIndirect (&logbrush) ;
```

The variable *logbrush* is a structure of type LOGBRUSH ("logical brush"). The three fields of this structure are shown below. The value of the *lbStyle* field determines how Windows interprets the other two fields:

lbStyle (WORD)	lbColor (DWORD)	lbHatch (short)
BS_SOLID	Color of brush	Ignored
BS_HOLLOW	Ignored	Ignored
BS_HATCHED	Color of hatches	Hatch brush style
BS_PATTERN	Ignored	Handle to bitmap

Earlier we used SelectObject to select a logical pen into a device context, DeleteObject to delete a logical pen, and GetObject to get information about a logical pen. You can use these same three functions with brushes. Once you have a handle to a brush, you can select the brush into a device context using SelectObject:

```
SelectObject (hDC, hBrush);
```

You can later delete a created brush with the DeleteObject function:

```
DeleteObject (hBrush) ;
```

Do not delete a brush that is currently selected in a device context, however. If you need to obtain information about a brush, you can call *GetObject*:

```
GetObject (hBrush, sizeof (LOGBRUSH), (LPSTR) &logbrush); where logbrush is a structure of type LOGBRUSH.
```

Brushes and Bitmaps

When you use the CreatePatternBrush or CreateBrushIndirect function with the lbStyle field set to BS_PATTERN, you first need a handle to a bitmap. The bitmap must be least 8 pixels wide and 8 pixels high. If it's larger, Windows uses only the upper left corner of the bitmap for the brush.

Because brushes and bitmaps are GDI objects, you must delete any that you create in your program before the program terminates. When you create a brush based on a bitmap, Windows makes a copy of the bitmap bits for use when drawing with the brush. You can delete the bitmap immediately after calling *CreatePatternBrush* (or *CreateBrushIndirect*) without affecting the brush. Similarly, you can delete the brush without affecting the bitmap.

One method of getting a handle to a bitmap was discussed in Chapter 9. You can use ICONEDIT to create a bitmap file (with the extension .BMP), include that filename in a BITMAP statement in the resource script, and then load the bitmap into your program. The LoadBitmap function returns a handle of type HBITMAP:

```
hBitmap = LoadBitmap (hInstance, lpszBitmap) ;
```

The variable *lpszBitmap* is the name of the bitmap in the resource script file.

The second method of getting a handle to a bitmap is to use this function:

```
hBitmap = CreateBitmap (nWidth, nHeight, nPlanes, nBitsPixel, lpBits);
```

To create a bitmap to use for a brush, *nWidth* and *nHeight* should both be set to 8. If you want a monochrome bitmap, *nPlanes* and *nBitsPixel* should both be set to 1. The variable *lpBits* is a long pointer to an array of bytes containing the pixel pattern of the bitmap. You can set this parameter to NULL if you want to create an uninitialized bitmap, in which case the bitmap will contain random data.

The third method of getting a handle to a bitmap is this:

```
hBitmap = CreateCompatibleBitmap (hDC, nWidth, nHeight);
```

This creates a bitmap with the same number of color planes and the same number of color bits per pixel as the device context indicated by hDC. (The only reason this function requires hDC is to get this color information.) The bitmap initially contains random data.

The final method for getting a handle to a bitmap requires a pointer to a structure (here named *bitmap*) of type BITMAP:

```
hBitmap = CreateBitmapIndirect (&bitmap) ;
```

Watch out for the difference between the types HBITMAP and BITMAP. HBITMAP is a handle to a bitmap. BITMAP is a structure that describes the bitmap. The BITMAP structure has seven fields, as described in the following list. Five of them are similar to the parameters of the *CreateBitmap* function.

THE GRAPHICS DEVICE INTERFACE

bmType.

Set to 0

bmWidth bmHeight Width of bitmap in pixels Height of bitmap in pixels

bmWidthBytes

Two times number of words in each raster line

bmPlanes |

Number of color planes

bmBitsPixel

Number of adjacent color bits per pixel

bmBits

Far pointer to an array of bytes containing the bitmap pattern

When you have a handle to a bitmap, you can use GetObject to obtain information about the bitmap:

```
GetObject (hBitmap, sizeof (BITMAP), (LPSTR) &bitmap) ;
```

where bitmap is a structure of type BITMAP. However, GetObject does not copy a valid far pointer into the bmBits field. To get the actual bits that make up the bitmap, you can call:

```
GetBitmapBits (hBitmap, dwCount, lpBits) ;
```

GetBitmapBits copies dwCount number of bytes into an array whose address is lpBits. You can also set the bits of a bitmap using the SetBitmapBits function:

```
SetBitmapBits (hBitmap, dwCount, lpBits) ;
```

The bmBits field of the BITMAP structure and the lpBits parameter of the CreateBitmap, SetBitmapBits, and GetBitmapBits functions are far pointers to an array of bytes that define the bitmap pattern. This array of bytes is arranged in scan lines starting from the top. If the bitmap has more than one color plane, then the planes are arranged sequentially:

Plane 1

Top scan line

Second scan line [and so forth]

Bottom scan line

Plane 2

Top scan line

Second scan line

[and so forth]

For the three-plane EGA, the first plane is red, the second is green, and the third is blue.

The total size of this array of bytes is equal to (using the fields of the logical bitmap structure):

```
bmPlanes * bmHeight * bmWidthBytes
```

The bmWidthBytes field is the width of each scan line in bytes. This value must be the even number equal to or the next equal number greater than:

```
bmWidth * bmBitsPixel / 8
```

In other words, each scan line is padded with bytes if necessary to get an integral number of words. The scan line is padded at the right because the bytes are arranged from left to right. The most significant bit of the first byte is the leftmost pixel.

Creating and Using Bitmap Brushes

We've covered the background information you need to create and use brushes based on bitmaps. Now let's put that information to work. Let's say that you want to draw a rectangle filled in with a brush that looks like little bricks, as shown in Figure 13-14.





Figure 13-14. A figure filled in with a customized brush

The bitmap you need has a pixel pattern that looks like this:



This is a monochrome bitmap with a height and width of 8. Here are three methods you can use to create a brush based on this bitmap.

Method one

Create an 8 by 8 bitmap in ICONEDIT that resembles the diagram shown above and save it under the name BRICK.BMP. In your resource script file, include a statement identifying this file as a bitmap and naming it "Brick":

Brick BITMAP brick.bmp

Within your program, define variables of type HBITMAP (handle to a bitmap) and HBRUSH (handle to a brush):

```
HBITMAP hBitmap ;
HBRUSH hBrush ;
```

These two handles are set by the following statements:

```
hBitmap = LoadBitmap (hInstance, "Brick");
hBrush = CreatePatternBrush (hBitmap);
```

When you have a valid device context, select the brush into the device context and display the rectangle:

```
SelectObject (hDC, hBrush) ;
Rectangle (hDC, xLeft, yTop, xRight, yBottom) ;
```

When you release the device context, delete the brush and bitmap:

```
DeleteObject (hBrush) ;
DeleteObject (hBitmap) ;
```

You don't have to wait until you release the device context to delete the bitmap—you can do so anytime after you create the brush based on the bitmap.

Method two

This method defines the bitmap pixels within the program as an array of eight unsigned integers. Each integer corresponds to a scan line in the bitmap pattern. A 1 bit is used for white and a 0 bit for black:

The bitmap is created using CreateBitmap by referencing this array of integers:

```
hBitmap = CreateBitmap (8, 8, 1, 1, (LPSTR) wBrickBits);
hBrush = CreatePatternBrush (hBitmap);
SelectObject (hDC, hBrush);
Rectangle (hDC, xLeft, yTop, xRight, yBottom);
```

After you're finished with the brush and the bitmap (and the brush is no longer selected in a valid device context), you delete the bitmap and the brush:

```
DeleteObject (hBrush) ;
DeleteObject (hBitmap) ;
```

Rather than using an array of integers for the bitmap's bits, you can use instead an array of unsigned characters. Because each scan line must contain an even number of bytes, however, you have to insert a 0 after each byte:

Method three

This method is similar to the second method except that you use the logical bitmap and logical brush structures to create the bitmap and the brush. Begin by defining these variables:

The last field of the logical bitmap structure remains uninitialized. This field must contain a far pointer to the array of bytes that define the bitmap pattern. Do not initialize the structure with this pointer, however. Instead use an assignment statement:

```
bitmap.bmBits = (LPSTR) wBrickBits;
```

Watch out when you assign a far address of a local data item to the field of a structure. If the program's data segment is moved in memory (as it can be following a *GetMessage*, *LocalAlloc*, or *LocalReAlloc* call), that far address can become invalid. A good rule is to make this assignment immediately before using the structure. After the assignment, you use this structure to create the bitmap:

```
hBitmap = CreateBitmapIndirect (&bitmap) ;
```

Now that you have the handle to a bitmap, you can use the CreateBrushIndirect function to create the brush:

```
logbrush.lbHatch = hBitmap ;
hBrush = CreateBrushIndirect (&logbrush) ;
SelectObject (hDC, hBrush) ;
Rectangle (hDC, xLeft, yTop, xRight, yBottom) ;
```


Later on, delete both the brush and the bitmap:

```
DeleteObject (hBrush);
DeleteObject (hBitmap);
```

Brush Alignment

When Windows fills in an area with a brush, it repeats the 8 by 8 bitmap both horizontally and vertically. This brush's appearance can vary slightly, depending on how Windows aligns the upper left corner of the bitmap with the display surface. The attribute in the device context that determines this alignment is called the "brush origin." This attribute is always expressed in terms of screen coordinates. If you obtain a device context using <code>BeginPaint</code> or <code>GetDC</code>, the brush origin is initially set to the upper left corner of your window's client area. If the client area begins 30 pixels from the left of the screen and 20 pixels from the top of the screen, the brush origin is set to the point (30, 20).

Whenever Windows uses a brush within the client area, the upper left corner of the brush's bitmap coincides with those client-area device points where both x and y are multiples of 8. Let's take an example involving a hatch brush with style HS_FDIAGONAL, which looks like this:



In MM_TEXT mode, when you draw a rectangle that is filled in with the HS_FDIAGONAL brush, the downward hatch line will intersect the upper left corner of the rectangle if this corner is at the logical point (8, 8). However, the hatch line will be aligned 4 pixels from the top of the corner if the rectangle begins at the logical point (8, 4).

In most cases, adjusting the brush origin is an unnecessary refinement to your drawing, but sometimes you'll want to do it. The process involves three steps:

- 1. Call UnrealizeObject for the brush. (Do not call UnrealizeObject for stock brushes.)
- 2. Set the brush origin with SetBrushOrg, remembering to use screen coordinates.
- 3. Select the brush into the device context using SelectObject.

One situation in which you'll need to change the brush origin is when you want the background of a child window to blend in with the background of its parent window. When you obtain a handle to the device context for the child window, the brush origin will be the upper left corner of the child window. You need to change the brush origin to be the upper left corner of the parent window. (We did this when coloring child window controls in Chapter 7.) In this case, you're changing the brush origin in one device context so that it coincides with the brush origin in another device context.

You'll also need to change brush origins when you draw several figures sharing the same device context but you don't want the brushes to coincide. For instance, suppose you want to use brushes to color the bars of a bar chart. If you didn't care about brush alignment, you might draw each of the bars using a function that looks like this:

```
void DrawBar1 (hDC, xLeft, yTop, xRight, yBottom, hBrush)
    HDC     hDC;
    short    xLeft, yTop, xRight, yBottom;
    HBRUSH    hBrush;
    (
    HBRUSH    hBrushOriginal;

    hBrushOriginal = SelectObject (hDC, hBrush);
    Rectangle (hDC, xLeft, yTop, xRight, yBottom);
    SelectObject (hDC, hBrushOriginal);
}
```

This function simply selects the brush handle passed as a function parameter (saving the handle to the brush originally selected), draws a rectangle, and then selects the original brush back into the device context. If a program used this routine to draw several adjacent bars that it filled in with the HS_FDIAGONAL brush, the result would look like Figure 13-15. Notice that the hatch lines for all three bars align, which has the unfortunate effect of drawing the eye downward from left to right.




Figure 13-15. Three bars that have the same device context and brush origin

To avoid this effect, you need to align the brush with each bar individually, which you can accomplish with the following function:

```
void DrawBar2 (hWnd, hDC, xLeft, yTop, xRight, yBottom, hBrush)
    HWND
             hWnd ;
    HDC
         hDC ;
              xLeft, yTop, xRight, yBottom;
    short
    HBRUSH
             hBrush ;
    HBRUSH
            hBrushOriginal;
    POINT
              pt ;
    UnrealizeObject (hBrush) ;
    pt.x = xLeft ;
    pt.y = yTop ;
    LPtoDP (hDC, &pt, 1);
    ClientToScreen (hWnd, &pt) ;
    SetBrushOrg (hDC, pt.x, pt.y) ;
    hBrushOriginal = SelectObject (hDC, hBrush);
    Rectangle (hDC, xLeft, yTop, xRight, yBottom) ;
    SelectObject (hDC, hBrushOriginal);
```

You "unrealize" the brush by calling *UnrealizeObject* and then set the brush origin to the upper left corner of the bar that's being drawn. This requires translating the upper left corner of the bar to client-area coordinates using *LPtoDP* and then to screen coordinates using *Client-ToScreen*. The result is shown in Figure 13-16. Now the hatch lines begin in the upper left corner of each bar and do not align from one bar to the next.




Figure 13-16. Three bars that have the same device context but a different brush origin

RECTANGLES, REGIONS, AND CLIPPING

Windows includes several additional drawing functions that work with RECT (rectangle) structures and "regions." A region is an area of the screen that is a combination of rectangles, other polygons, and ellipses.

Working with Rectangles

These three drawing functions require a pointer to a rectangle structure:

```
FillRect (hDC, &rect, hBrush);
FrameRect (hDC, &rect, hBrush);
InvertRect (hDC, &rect);
```

In these functions, the *rect* parameter is a structure of type RECT with four fields: *left*, *top*, *right*, and *bottom*. The coordinates in this structure are treated as logical coordinates.

FillRect fills the rectangle (up to but not including the right and bottom coordinate) with the specified brush. This function doesn't require that you first select the brush into the device context. We used the FillRect function in the ROP2LOOK program earlier in this chapter to color the background with five stock brushes.

FrameRect uses the brush to draw a rectangular frame but does not fill in the rectangle. Using a brush to draw a frame may seem a little strange, because with the functions that you've seen so far (such as Rectangle), the border is drawn with the current pen. FrameRect allows you to draw a rectangular frame that isn't necessarily a pure color. This frame is one logical unit wide. If logical units are larger than device units, than the frame will be 2 pixels or more wide.

InvertRect inverts all the pixels in the rectangle, turning ones to zeros and zeros to ones. This function turns a white area to black, a black area to white, and a green area to magenta.

Windows also includes nine functions that allow you to manipulate RECT structures easily and cleanly. For instance, to set the four fields of a RECT structure to particular values, you would conventionally use code that looks like this:

```
rect.left = xLeft;
rect.top = xTop;
rect.right = xRight;
rect.bottom = xBottom;
```

By calling the SetRect function, however, you can achieve the same result with a single line:

```
SetRect (&rect, xLeft, yTop, xRight, yBottom) ;
```

The other eight functions can also come in handy when you want to do one of the following:

Move a rectangle a number of units along the x and y axes:

```
OffsetRect (&rect, x, y) ;
```

Increase or decrease the size of a rectangle:

```
InflateRect (&rect, x, y) ;
```

Set the fields of a rectangle equal to 0:

```
SetRectEmpty (&rect) ;
```

Copy one rectangle to another:

```
CopyRect (&DestRect, &SrcRect) ;
```

Obtain the intersection of two rectangles:

```
IntersectRect (&DestRect, &SrcRect1, &SrcRect2);
```

Obtain the union of two rectangles:

```
UnionRect (&DestRect, &SrcRect1, &SrcRect2);
```

· Determine if a rectangle is empty:

```
bEmpty = IsRectEmpty (&rect) ;
```

Determine if a point is in a rectangle:

```
bInRect = PtInRect (&rect, point) ;
```

In most cases, the equivalent code for these functions is simple. Sometimes, you'll find that using one of these functions actually increases the size of your .EXE file. In some instances, in fact, equivalent code even takes up less space in your source code file. For example, you can duplicate the *CopyRect* function call with:

```
DestRect = SrcRect ;
```

Creating and Painting Regions

A region is a description of an area of the display that is a combination of rectangles, other polygons, and ellipses. You can use regions for drawing or for clipping. You use a region for clipping by selecting the region into the device context.

Like pens, brushes, and bitmaps, regions are GDI objects. (The fifth and final type of GDI object is the logical font, which we'll look at in Chapter 15.) You must treat regions the same way you treat the other GDI objects: Delete any regions that you create, but don't delete a region while it is selected in the device context.

When you create a region, Windows returns a handle to the region of type HRGN. The simplest type of region describes a rectangle. You can create a rectangular region in one of two ways:

```
hRgn = CreateRectRgn (xLeft, yTop, xRight, yBottom) ;
```

or:

```
hRgn = CreateRectRgnIndirect (&rect) ;
```

Regions are always expressed in terms of device coordinates.

You can also create elliptical regions using:

```
hRgn = CreateEllipticRgn (xLeft, yTop, xRight, yBottom) ;
Or:
```

```
hRgn = CreateEllipticRgnIndirect (&rect) ;
```

Be forewarned that the elliptical region functions are remarkably slow. When you first experiment with them, you might think that your program has crashed. Be patient.

Creating a polygonal region is similar to using the Polygon function:

```
hRgn = CreatePolygonRgn (&point, nCount, nPolyFillMode);
```

The *point* parameter is an array of structures of type POINT, *nCount* is the number of points, and *nPolyFillMode* is either ALTERNATE or WINDING.

So what, you say? What makes these regions so special? Here's the function that unleashes the power of regions:

```
nRgnType = CombineRgn (hDestRgn, hSrcRgn1, hSrcRgn2, nCombine);
```

This combines two source regions (hSrcRgn1 and hSrcRgn2) and causes the destination region handle (hDestRgn) to refer to that combined region. All three region handles must be valid, but the region previously described by hDestRgn is destroyed. (When you use this function, you might want to make hDestRgn refer initially to a small rectangular region.)

The nCombine parameter describes how the hSrcRgn1 and hSrcRgn2 regions are to be combined:

nCombine Value	New Region	
RGN_AND	Overlapping area of the two source regions	
RGN_OR	All the two source regions	
RGN_XOR	All the two source regions excluding the overlapping area	
RGN_DIFF	All of hSrcRgn1 not in hSrcRgn2	
RGN_COPY	The hSrcRgn1 made the same as hSrcRgn2	

The *nRgnType* value returned from *CombineRgn* is one of the following: NULLREGION, indicating an empty region; SIMPLEREGION, indicating a simple rectangle, ellipse, or polygon; COMPLEXREGION, indicating a combination of rectangles, ellipses, or polygons; and ERROR, meaning that an error has occurred.

Once you have a handle to a region, you can use it with four drawing functions:

```
FillRgn (hDC, hRgn, hBrush);
FrameRgn (hDC, hRgn, hBrush, xFrame, yFrame);
InvertRgn (hDC, hRgn);
PaintRgn (hDC, hRgn);
```

The FillRgn, FrameRgn, and InvertRgn functions are similar to the FillRect, FrameRect, and InvertRect functions. The xFrame and yFrame parameters to FrameRgn are the width and height of the frame to be painted around the region. Although regions always use device coordinates, these two parameters are in terms of logical coordinates. The PaintRgn function fills in the region with the brush currently selected in the device context.

When you are finished with a region, you can delete it using the same function that deletes other GDI objects:

```
DeleteObject (hRgn) ;
```

Clipping with Rectangles and Regions

Regions can also play a role in clipping. (I previously discussed clipping in Chapter 3, when we first started writing on the client area.) The *InvalidateRect* function invalidates a rectangular area of the display and generates a WM_PAINT message. Often we use the *InvalidateRect* function to erase the client area and generate a WM_PAINT message:

```
InvalidateRect (hWnd, NULL, TRUE) ;
```

You can obtain the coordinates of the invalid rectangle by calling <code>GetUpdateRect</code>, and you can validate a rectangle of the client area using the <code>ValidateRect</code> function. When you receive a <code>WM_PAINT</code> message, the coordinates of the invalid rectangle are available from the <code>PAINTSTRUCT</code> structure that is filled in by the <code>BeginPaint</code> function. This invalid rectangle also defines a "clipping region." You cannot paint outside the clipping region.

Windows has two functions similar to *InvalidateRect* and *ValidateRect* that work with regions rather than rectangles:

```
InvalidateRgn (hWnd, hRgn, bErase);
and:
ValidateRgn (hWnd, hRgn);
```

However, when you receive a WM_PAINT message as a result of an invalid region, the clipping region will still be a rectangle that encompasses the invalid region.

If you want a nonrectangular clipping region, you can select a region into the device context using either:

```
SelectObject (hDC, hRgn);

or:

SelectClipRgn (hDC, hRgn);
```

SelectObject returns a handle to the previous clipping region selected in the device context, whereas SelectClipRgn returns an nRgnType value like CombineRgn. Windows also includes several functions to manipulate this clipping region, such as ExcludeClipRect to exclude a

rectangle from the clipping region, *IntersectClipRect* to create a new clipping region that is the intersection of the previous clipping region and a rectangle, and *OffsetClipRgn* to move a clipping region to another part of the client area.

The CLOVER Program

The CLOVER program forms a region out of four ellipses, selects this region into the device context, and then draws a series of lines emanating from the center of the window's client area. The lines appear only in the area defined by the region. The resulting display is shown in Figure 13-17.




Figure 13-17. The CLOVER display, drawn using a complex clipping region

To draw this graphic by conventional methods, you would have to calculate the end point of each line based on formulas involving the circumference of an ellipse. By using a complex clipping region, you can simply draw the lines and let Windows determine the end points. The CLOVER program is shown in Figure 13-18.

```
clover.obj : clover.c
    cl -c -D LINT_ARGS -FPa -Gsw -Os -W2 -Zp clover.c

clover.exe : clover.obj clover.def
    link4 clover, /align:16, /map, slibw, clover
```

Figure 13-18. The CLOVER program

(continued)

Figure 13-18. Continued

```
/* CLOVER.C -- Clover Drawing Program using Regions */
#include <windows.h>
#include <math.h>
#define TWO PI (2.0 * 3.14159)
long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG) ;
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
               hInstance, hPrevInstance;
    HANDLE
    LPSTR
                lpszCmdLine ;
                nCmdShow ;
    int
     static char szAppName [] = "Clover" ;
            hWnd ;
    MSG
                msq ;
    WNDCLASS
               wndclass ;
    if (!hPrevInstance)
         = CS HREDRAW | CS VREDRAW ;
                              = 0;
         wndclass.cbWndExtra
         wndclass.hInstance
                               = hInstance ;
         wndclass.hIcon
                                = NULL ;
         wndclass.hCursor
                               = LoadCursor (NULL, IDC ARROW) ;
         wndclass.hbrBackground = GetStockObject (WHITE BRUSH) ;
         wndclass.lpszMenuName = NULL ;
         wndclass.lpszClassName = szAppName ;
         if (!RegisterClass (&wndclass))
              return FALSE ;
    hWnd = CreateWindow (szAppName, "Draw a Clover",
                        WS OVERLAPPEDWINDOW,
                        CW USEDEFAULT, 0,
CW USEDEFAULT, 0,
                        NULL, NULL, hinstance, NULL) ;
    ShowWindow (hWnd, nCmdShow) ;
    UpdateWindow (hWnd) ;
    while (GetMessage (&msg, NULL, 0, 0))
         TranslateMessage (&msg) ;
         DispatchMessage (&msg) ;
    return msg.wParam :
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
    HWND
                hWnd ;
    unsigned
                iMessage ;
    WORD
                 wParam ;
    LONG
                 lParam ;
    static HRGN hRgnClip ;
    static short xClient, yClient ;
```

Figure 13-18. Continued

```
double
               fAngle, fRadius ;
HCURSOR
               hCursor ;
HDC
               hDC ;
HRGN
               hRgnTemp [6];
PAINTSTRUCT
               ps ;
short
switch (iMessage)
     case WM SIZE:
           xClient = LOWORD (lParam) ;
           yClient = HIWORD (1Param) ;
           hCursor = SetCursor (LoadCursor (NULL, IDC WAIT)) ;
           ShowCursor (TRUE) ;
           if (hRgnClip)
                 DeleteObject (hRgnClip) ;
           hRgnTemp [0] = CreateEllipticRgn (0, yClient / 3, xClient / 2, 2 * yClient / 3); hRgnTemp [1] = CreateEllipticRgn (xClient / 2, yClient / 3,
                                         xClient, 2 * yClient / 3) ;
           hRgnTemp [2] = CreateEllipticRgn (xClient / 3, 0,
           2 * xClient / 3, yClient / 2);
hRgnTemp [3] = CreateEllipticRgn (xClient / 3, yClient / 2,
2 * xClient / 3, yClient);
           hRgnTemp [4] = CreateRectRgn (0, 0, 1, 1)
           hRgnTemp [5] = CreateRectRgn (0, 0, 1, 1);
hRgnClip = CreateRectRgn (0, 0, 1, 1);
           CombineRgn (hRgnTemp [4], hRgnTemp [0], hRgnTemp [1], RGN_OR);
            CombineRgn (hRgnTemp [5], hRgnTemp [2], hRgnTemp [3], RGN_OR);
                                          hRgnTemp [4], hRgnTemp [5], RGN XOR);
            CombineRgn (hRgnClip,
            for (i = 0 ; i < 6 ; i++)
                 DeleteObject (hRqnTemp [i]) ;
           SetCursor (hCursor) ;
            ShowCursor (FALSE) ;
           break ;
      case WM PAINT:
           hDC = BeginPaint (hWnd, &ps) ;
           SetViewportOrg (hDC, xClient / 2, yClient / 2) ;
           SelectClipRgn (hDC, hRgnClip) ;
           fRadius = hypot (xClient / 2.0, yClient / 2.0) ;
           for (fAngle = 0.0; fAngle < TWO PI; fAngle += TWO PI / 360)
                 MoveTo (hDC, 0, 0);
                 LineTo (hDC, (short) ( fRadius * cos (fAngle) + 0.5),
(short) (-fRadius * sin (fAngle) + 0.5));
           EndPaint (hWnd, &ps) ;
           break ;
```

(continued)

Figure 13-18. Continued

```
case WM DESTROY:
    DeleteObject (hRgnClip);
    PostQuitMessage (0);
    break;

default:
    return DefWindowProc (hWnd, iMessage, wParam, lParam);

return OL;
}
```

```
NAME
             CLOVER
DESCRIPTION
              'Clover Drawing Using Regions (C) Charles Petzold, 1987'
             'WINSTUB.EXE'
STUB
             MOVEABLE
CODE
DATA
              MOVEABLE MULTIPLE
HEAPSIZE
             1024
STACKSIZE
              4096
EXPORTS
              WndProc
```

Because regions always use device coordinates, the CLOVER program has to recreate the region every time it receives a WM_SIZE message. This takes several seconds. CLOVER begins by creating four elliptical regions that are stored as the first four elements of the hRgnTemp array. Then the program creates three "dummy" regions:

```
hRgnTemp [4] = CreateRectRgn (0, 0, 1, 1);
hRgnTemp [5] = CreateRectRgn (0, 0, 1, 1);
hRgnClip = CreateRectRgn (0, 0, 1, 1);
```

The two elliptical regions at the left and right of the client area are combined:

```
CombineRqn (hRqnTemp [4], hRqnTemp [0], hRqnTemp [1], RGN_OR);
```

Similarly, the two elliptical regions at the top and bottom of the client area are combined:

```
CombineRqn (hRqnTemp [5], hRqnTemp [2], hRqnTemp [3], RGN_OR);
```

Finally, these two combined regions are in turn combined into hRgnClip:

```
CombineRgn (hRgnClip, hRgnTemp [4], hRgnTemp [5], RGN_XOR) ;
```

The RGN_XOR identifier is used to exclude overlapping areas from the resultant region. Finally, the six temporary regions are deleted:

```
for (i = 0 ; i < 6 ; i++)
    DeleteObject (hRgnTemp [i]);</pre>
```

The WM_PAINT processing is simple, considering the results. The viewport origin is set to the center of the client area (to make the line drawing easier), and the region created during the WM_SIZE message is selected as the device context's clipping region:

```
SetViewportOrg (hDC, xClient / 2, yClient / 2);
SelectClipRqn (hDC, hRqnClip);
```

Now all that's left is drawing the lines—360 of them, spaced 1 degree apart. The length of each line is the variable *fRadius*, which is the distance from the center to the corner of the client area:

During processing of WM_DESTROY, the region is deleted:

```
DeleteObject (hRgnClip) ;
```

SOME MISCELLANEOUS GDI FUNCTIONS

A few additional drawing functions don't fit into any convenient categories. These include FloodFill, Drawlcon, ScrollWindow, ScrollDC, LineDDA, and LineProc.

FloodFill fills in an area with the current brush. The syntax is:

```
FloodFill (hDC, xStart, yStart, rqbColor) ;
```

This is the function that the Windows PAINT program calls when you use the "bucket of paint" icon. Starting at the logical point (xStart, yStart), the function fills in an area until it encounters a boundary of rgbColor.

FloodFill doesn't work if the point (xStart, yStart) is rgbColor itself or if the point is outside the clipping region. If you use FloodFill during normal repainting of your client area, you might want to invalidate the entire client area before calling BeginPaint to be sure that (xStart, yStart) is in the clipping region.

Drawlcon draws an icon on the display:

```
Drawlcon (hDC, xStart, yStart, hIcon);
```

This function works only in the MM_TEXT mapping mode. We used *Drawlcon* in Chapter 9. Both *ScrollWindow* and *ScrollDC* scroll part of the window's client area. We used *ScrollWindow* in the final version of the SYSMETS program in Chapter 3. It's not a GDI function, so it always uses device units. The general syntax is:

```
ScrollWindow (hWnd, xScroll, yScroll, &rectScroll, &rectClip);
```

Note that the first parameter is a handle to a window rather than to a device context. The section of the client area indicated by the *rectScroll* rectangle structure is shifted right *xScroll* pixels and down *yScroll* pixels. These two parameters can be negative if you use the function to scroll to the left or up.

Only the area within the rectClip rectangle is affected by this scrolling, so it makes sense to set rectClip only to be the same rectangle as rectScroll, a larger rectangle, or NULL. If you want the area within rectScroll to be scrolled without affecting anything outside the rectangle, set rectClip to equal rectScroll. If it is acceptable for the area within rectScroll to be shifted outside the rectangle, set rectClip to NULL. The area uncovered by the scrolling is invalidated and generates a WM_PAINT message. Because ScrollWindow is not a GDI function, it can't perform clipping and will also scroll dialog boxes or child windows that may be covering the surface of the client area.

ScrollDC is a GDI function and works differently. The syntax is:

When not set to NULL, the last two parameters return information to the program. If you pass a region handle to Windows in the sixth parameter, Windows sets the region to the invalid region uncovered by the scroll. If you pass a pointer to a RECT structure in the last parameter, Windows sets the structure to indicate the invalid rectangle uncovered by the scroll.

The LineDDA function calculates all the points on a straight line that connects two given points. (DDA stands for "digital differential analyzer.") The syntax is:

```
LineDDA (xStart, yStart, xEnd, yEnd, lpfnLineProc, lpData);

LineDDA requires a call-back function of the form:
```

LineProc must be included in the EXPORTS section of your module definition (.DEF) file. The lpfnLineProc parameter you pass to LineDDA must be the result of a MakeProcInstance call:

```
lpfnLineProc = MakeProcInstance (LineProc, hInstance) ;
```

When you call *LineDDA*, Windows calls *LineProc* once for each point on the line connecting (xStart, yStart) and (xEnd, yEnd). The point is indicated by the x and y parameters to *LineProc* also receives the far pointer to programmer-defined data that you supply in the *LineDDA* call.

Note that LineDDA does not require a handle to a device context. The function is simply a line calculation algorithm that gives your program each point it calculates. What you do with these points is up to you. In the LINEDDA program, shown in Figure 13-19, I chose to draw a rectangle and connect the corners of the rectangle with the corners of the client area. Not satisfied with the mundane dotted and dashed line styles that Windows allows one to use with more ease, I chose to draw the lines as a series of tiny ellipses. The result is shown in Figure 13-20 (on page 593).

```
linedda.obj : linedda.c
    cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp linedda.c
linedda.exe : linedda.obj linedda.def
    link4 linedda, /align:16, /map, slibw, linedda
```

```
/* LINEDDA.C -- LineDDA Demonstration */
#include <windows.h>
long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG) ;
void FAR PASCAL LineProc (short, short, LPSTR) ;
HANDLE hInst ;
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
     HANDLE hInstance, hPrevInstance;
     LPSTR
                 lpszCmdLine ;
                 nCmdShow ;
     int
     static char szAppName [] = "LineDDA" ;
     HWND hWnd;
     MSG
                 msq ;
     WNDCLASS wndclass :
     if (!hPrevInstance)
          wndclass.style = CS_HREDRAW | CS_VREDRAW ;
wndclass.spcleFyter
wndclass.cbcleFyter
          wndclass.cbClsExtra = 0;
wndclass.cbWndExtra = 0;
          wndclass.hInstance = hInstance;
          wndclass.hIcon = NULL;
wndclass.hCursor = LoadCursor (NULL, IDC_ARROW);
          wndclass.hbrBackground = GetStockObject (WHITE BRUSH) ;
          wndclass.lpszMenuName = NULL ;
          wndclass.lpszClassName = szAppName ;
          if (!RegisterClass (&wndclass))
               return FALSE ;
     hInst = hInstance ;
     hWnd = CreateWindow (szAppName, "LineDDA Demonstration",
                           WS OVERLAPPEDWINDOW,
                           CW USEDEFAULT, 0,
CW USEDEFAULT, 0,
                           NULL, NULL, hInstance, NULL) ;
```

Figure 13-19. The LINEDDA program

Figure 13-19. Continued

```
ShowWindow (hWnd, nCmdShow) ;
      UpdateWindow (hWnd) ;
      while (GetMessage (&msg, NULL, 0, 0))
            TranslateMessage (&msg) ;
            DispatchMessage (&msg) ;
      return msg.wParam ;
long FAR PASCAL WndProc (hWnd, iMessage, wParam, lParam)
                        hWnd ;
                         iMessage ;
      unsigned
      WORD
                         wParam ;
      LONG
                         lParam ;
      static FARPROC lpfnLineProc ;
      static short xClient, yClient, xL, xR, yT, yB;
      HDC
                         hDC ;
      PAINTSTRUCT
                         ps :
      switch (iMessage)
             case WM CREATE:
                   lpfnLineProc = MakeProcInstance (LineProc, hInst) ;
                   break ;
                   xR = 3 * (xL = (xClient = LOWORD (1Param)) / 4) ;
                   yB = 3 * (yT = (yClient = HIWORD (1Param)) / 4) ;
                   break :
             case WM PAINT:
                   hDC = BeginPaint (hWnd, &ps) ;
                   LineDDA (xL, yT, xR, yT, lpfnLineProc, (LPSTR) &hDC) ;
                   LineDDA (xR, yT, xR, yB, lpfnLineProc, (LPSTR) &hDC);
LineDDA (xR, yB, xL, yB, lpfnLineProc, (LPSTR) &hDC);
LineDDA (xL, yB, xL, yT, lpfnLineProc, (LPSTR) &hDC);
                   LineDDA (0, 0, xL, yT, lpfnLineProc, (LPSTR) &hDC);
LineDDA (xClient, 0, xR, yT, lpfnLineProc, (LPSTR) &hDC);
LineDDA (xClient, yClient, xR, yB, lpfnLineProc, (LPSTR) &hDC);
LineDDA (0, yClient, xL, yB, lpfnLineProc, (LPSTR) &hDC);
                   EndPaint (hWnd, &ps) ;
                   break ;
             case WM DESTROY:
                   PostQuitMessage (0) ;
                   break ;
                   return DefWindowProc (hWnd, iMessage, wParam, 1Param) ;
       return OL ;
```

(continued)

Figure 13-19. Continued

```
NAME
               LINEDDA
DESCRIPTION
               'LineDDA Demonstration (C) Charles Petzold, 1987'
               'WINSTUB.EXE'
STUB
CODE
               MOVEABLE
DATA
               MOVEABLE MULTIPLE
HEAPSIZE
               1024
STACKSIZE
               4096
EXPORTS
               WndProc
               LineProc
```




Figure 13-20. The LINEDDA display

The *LineDDA* function is called eight times during processing of the WM_PAINT message, once for each of the eight lines. The *lpData* parameter is the address of the handle to the device context.

The LineProc function is short:

Note that the *nCounter* variable is defined as static so that its value is preserved between *LineProc* calls. It cycles through the values 0, 1, 2, and 3. When the value is 2, *LineProc* draws an ellipse centered on the point.

PROGRAMS THAT DRAW FOREVER

A fun program in any graphics system is one that runs "forever," simply drawing a hypnotic series of rectangles with random sizes and colors. You can create such a program in Windows, but it's not quite as easy as it first seems. By now you should know that this is definitely not the way to do it:

```
case WM_PAINT:
                        /* Very, very bad code !!! */
    hDC = BeginPaint (hWnd, &ps) ;
    while (TRUE)
         xLeft = rand () % xClient ;
         xRight = rand () % xClient ;
               = rand () % yClient ;
         yBottom = rand () % yClient ;
         nRed = rand() & 255;
         nGreen = rand() & 255;
         nBlue = rand () & 255;
         hDC = GetDC (hWnd) ;
         hBrush = CreateSolidBrush (RGB (nRed, nGreen, nBlue));
         SelectObject (hDC, hBrush) ;
         Rectangle (hDC, min (xLeft, xRight), min (yTop, yBottom),
                         max (xLeft, xRight), max (yTop, yBottom));
     EndPaint (hWnd, &ps) ;
     break ;
```

Sure, this will work, but nothing else will. Because Windows is a nonpreemptive multitasking environment, a program can't enter into an infinite loop like this. This loop will stop all other processing in the system.

One acceptable alternative is setting a Windows timer to send WM_TIMER messages to your window function. For each WM_TIMER message, you obtain a device context with GetDC, draw a random rectangle, and then release the device context with ReleaseDC. But that takes some of the fun out of the program, because the program can't draw the random rectangles as quickly as possible. It must wait for each WM_TIMER message.

There must be plenty of "dead time" in Windows, time during which all the message queues are empty and Windows is just sitting in a little loop waiting for keyboard or mouse input. Couldn't we somehow get control during that dead time and draw the rectangles, relinquishing control only when a message is added to a program's message queue? That's one of the purposes of the *PeekMessage* function. Here's one example of a *PeekMessage* call:

PeekMessage (&msg, NULL, 0, 0, PM_REMOVE)

The first four parameters (a pointer to a MSG structure, a window handle, and two values indicating a message range) are identical to those of *GetMessage*. Setting the second, third, and fourth parameters to NULL or 0 indicates that we want *PeekMessage* to return all messages for all windows in the program. Like *GetMessage*, *PeekMessage* effectively yields control to other programs if messages are waiting in the other programs' message queues. Like *GetMessage*, *PeekMessage* returns messages only for window functions in the program that makes the function call.

The last parameter to *PeekMessage* is set to PM_REMOVE if the message is to be removed from the message queue. You can set it to PM_NOREMOVE if the message isn't to be removed. This is why *PeekMessage* is a "peek" rather than a "get"—it allows a program to check the next message in the program's queue without actually removing it. *GetMessage* doesn't return control to a program unless it retrieves a message from the program's message queue. But *PeekMessage* will return under two conditions:

- When there's a message in the program's message queue, in which case the return value of PeekMessage is TRUE (nonzero).
- When there are no messages in the message queue of any program running under Windows, in which case the return value of PeekMessage is FALSE (0).

A message loop that uses *PeekMessage* rather than *GetMessage* essentially says to Windows, "Let other programs run for a little while, but once they've emptied their message queues, return control to me—I'm not finished with my work." If two or more programs are running that use a *PeekMessage* loop to retrieve messages, Windows uses a round-robin approach, returning control sequentially to each program waiting with a *PeekMessage* call.

This allows us to replace the normal message loop, which looks like this:

with an alternative message loop like this:

Notice that the WM_QUIT message is explicitly checked. You don't have to do this in a normal message loop, because the return value of *GetMessage* is 0 when it retrieves a WM_QUIT message. But *PeekMessage* uses its return value to indicate whether a message was retrieved, so the check of WM_QUIT is required.

If the return value of *PeekMessage* is TRUE, the message is processed normally. If the value is FALSE, the program can do some work (such as displaying yet another random rectangle) before returning control to Windows.

(Although the Windows documentation notes that you can't use *PeekMessage* to remove WM_PAINT messages from the message queue, this isn't really a problem. After all, *GetMessage* doesn't remove WM_PAINT messages from the queue either. The only way to remove a WM_PAINT message from the queue is to validate the invalid regions of the window's client area, which you can do with *ValidateRect*, *ValidateRgn*, or a *BeginPaint* and *EndPaint* pair. If you process a WM_PAINT message normally after retrieving it from the queue with *PeekMessage*, you'll have no problems. What you can't do is use code like this to empty your message queue of all messages:

```
while (PeekMessage (&msg, NULL, 0, 0, PM_REMOVE));
```

This statement removes and discards all messages from your message queue except WM_PAINT. If a WM_PAINT message is in the queue, you'll be stuck inside the while loop forever.)

The Windows TERMINAL program uses a *PeekMessage* loop when it receives input from a communications line. This allows TERMINAL to check "continuously" for incoming data. The SPOOLER program uses this technique to print on a printer or plotter and—as you'll see in Chapter 16—a Windows program that prints also includes a function with a *PeekMessage* loop. Armed with the *PeekMessage* function, we can now write a program that relentlessly displays random rectangles. The program, called RANDRECT, is shown in Figure 13-21. A typical RANDRECT display appears on the back cover of this book.

```
randrect.obj : randrect.c
    cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp randrect.c

randrect.exe : randrect.obj randrect.def
    link4 randrect, /align:16, /map, slibw, randrect
```

```
/* RANDRECT.C -- Displays Random Rectangles */
#include <windows.h>
#include <stdlib.h>
long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG) ;
void DrawRectangle (HWND) ;
short xClient, yClient ;
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
    HANDLE hInstance, hPrevInstance;
    LPSTR
               lpszCmdLine :
                nCmdShow ;
     int
     static char szAppName [] = "RandRect" ;
    HWND hWnd;
                msg ;
    MSG
    WNDCLASS wndclass :
    if (!hPrevInstance)
         wndclass.style
                                 = CS HREDRAW | CS VREDRAW ;
         wndclass.lpfnWndProc = WndProc;
wndclass.cbClsExtra = 0;
         wndclass.cbWndExtra = 0;
         wndclass.hInstance = hInstance;
         wndclass.hIcon = NULL;
wndclass.hCursor = LoadCursor (NULL, IDC_ARROW);
         wndclass.hbrBackground = GetStockObject (WHITE_BRUSH) ;
         wndclass.lpszMenuName = NULL ;
         wndclass.lpszClassName = szAppName ;
         if (!RegisterClass (&wndclass))
              return FALSE ;
```

Figure 13-21. The RANDRECT program

(continued)

Figure 13-21. Continued

```
hWnd = CreateWindow (szAppName, "Random Rectangles",
                            WS OVERLAPPEDWINDOW,
                            CW_USEDEFAULT, 0,
                            CW USEDEFAULT, 0,
NULL, NULL, hInstance, NULL);
     ShowWindow (hWnd, nCmdShow) ;
     UpdateWindow (hWnd) ;
     while (TRUE)
           if (PeekMessage (&msg, NULL, 0, 0, PM REMOVE))
                 if (msg.message == WM QUIT)
                      break ;
                 TranslateMessage (&msg) ;
                 DispatchMessage (&msg) ;
           else
                 DrawRectangle (hWnd) ;
     return msg.wParam ;
void DrawRectangle (hWnd)
     HWND
           hWnd ;
     HBRUSH hBrush ;
            hDC :
     HDC
     short xLeft, xRight, yTop, yBottom, nRed, nGreen, nBlue;
     xLeft = rand () % xClient ;
xRight = rand () % xClient ;
     yTop = rand () % yClient
     yBottom = rand () % yClient ;
     nRed = rand () & 255;
nGreen = rand () & 255;
nBlue = rand () & 255;
     hDC = GetDC (hWnd) ;
     hBrush = CreateSolidBrush (RGB (nRed, nGreen, nBlue)) ;
     SelectObject (hDC, hBrush) ;
     Rectangle (hDC, min (xLeft, xRight), min (yTop, yBottom), max (xLeft, xRight), max (yTop, yBottom));
     ReleaseDC (hWnd, hDC) ;
     DeleteObject (hBrush) ;
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
             hWnd ;
      HWND
      unsigned iMessage ;
      WORD
               wParam ;
     LONG
               lParam :
     switch (iMessage)
           case WM SIZE:
                 xClient = LOWORD (1Param) ;
                 yClient = HIWORD (1Param) ;
                 break ;
```

Figure 13-21. Continued

NAME RANDRECT

DESCRIPTION 'Random Rectangle Drawing Program (C) Charles Petzold, 1987'

STUB 'WINSTUB.EXE'

CODE MOVEABLE
DATA MOVEABLE MULTIPLE
HEAPSIZE 1024
STACKSIZE 4096
EXPORTS WndProc

Chapter 14

Bits, Blts, and Metafiles

Bitmaps and metafiles represent two very different ways of storing pictorial information. The bitmap is a complete digital representation of the picture. Each pixel in the image corresponds to one or more bits in the bitmap. Monochrome bitmaps require only one bit per pixel; color bitmaps require additional bits to indicate the color of each pixel.

Bitmaps can be constructed "manually," which is one of the purposes of the ICONEDIT program included with the Windows Software Development Kit. You can also use the Windows PAINT program for making bitmapped images. If you create a picture in PAINT and copy part of it to the clipboard, then the clipboard contains a bitmap. Bitmaps can also be obtained from digital scanners or imaging devices. Through this process, photographs or other images can become manipulable data in Windows programs.

Bitmaps have two major drawbacks. First, they are highly susceptible to problems involving device dependence, of which the most obvious is color. Displaying a color bitmap on a monochrome device is often unsatisfactory. Another problem involving device dependence is the resolution and aspect ratio. A bitmap is created based on a particular resolution and aspect ratio, but this information is not included in the bitmap file. Although bitmaps can be stretched or compressed, this generally involves duplicating or dropping rows or columns of pixels and can lead to distortion in the scaled image.

The second major drawback of bitmaps is that they require a large amount of storage space. For instance, a bitmap representation of an entire 640-by-350, eight-color EGA screen requires 84 KB.

A metafile, on the other hand, stores pictorial information as a series of records that correspond directly to GDI calls, such as *MoveTo*, *Rectangle*, *TextOut*, and others that you encountered in Chapter 13. A metafile is thus a description of a picture rather than a digital representation of it. Metafiles are more closely associated with Windows drawing programs (such as Micrografx's Windows DRAWI) and other CAD (computer-aided design) programs. The user of these programs draws an image with lines, rectangles, ellipses, text, and other graphics primitives. Although these programs generally use a private format for storing the picture in a file, they can usually transfer the picture to the clipboard in the form of a metafile. Metafiles usually require much less storage space than bitmaps. The storage space for a bitmap is governed by the size of the image and number of colors it contains, whereas the storage space for a metafile is governed by the complexity of the image and the number of individual GDI instructions it contains.

In the introduction to GDI in Chapter 12, I talked about two types of device contexts that don't refer to real devices: the memory device context and the metafile device context. We'll see how these work as we examine bitmaps and metafiles and explore the ways we can create, use, and manipulate them. The subject of bitmaps and metafiles will come up again in Chapter 17, "The Clipboard." Text, bitmaps, and metafiles are the three primary forms of data that can be shared by applications through the clipboard.

BITMAPS AS OBJECTS AND FILES

The subject of bitmaps has come up often in previous chapters. In Chapter 9 we created bitmaps in ICONEDIT and used them as a program resource. In Chapter 10 we saw how bitmaps can substitute for text in a menu. In Chapter 13 we constructed small 8-by-8-pixel bitmaps to use for brushes. Let's now look at bitmaps more comprehensively.

Creating Bitmaps in a Program

Windows includes four functions that let you create a bitmap in your program. They are:

```
hBitmap = CreateBitmap (xWidth, yHeight, nPlanes, nBitsPixel, lpBits);
hBitmap = CreateBitmapIndirect (&bitmap);
hBitmap = CreateCompatibleBitmap (hDC, xWidth, yHeight);
hBitmap = CreateDiscardableBitmap (hDC, xWidth, yHeight);
```

In the *CreateBitmap* function, *IpBits* can be set to NULL if you are creating an uninitialized bitmap. The resultant bitmap contains random data. In the *CreateCompatibleBitmap* and *CreateDiscardableBitmap* functions, Windows uses the device context referenced by *hDC* to obtain the number of color planes and number of color bits per pixel. The bitmap created by these functions is uninitialized.

CreateBitmapIndirect is similar to CreateBitmap except that CreateBitmapIndirect uses the logical bitmap structure of type BITMAP to define the bitmap. The following table provides information on the fields of this structure:

Field	Type	Description	
bmType	short	Type of bitmap (set to 0 for logical bitmaps)	
bmWidth	short	Width of bitmap in pixels (greater than 0)	
bmHeight	short	Height of bitmap in scan lines (greater than 0)	
bmWidthBytes	short	Width of bitmap in bytes (must be even)	
bmPlanes	BYTE	Number of color planes	
bmBitsPixel	BYTE	Number of color bits per pixel	
bmBits	LPSTR	Far pointer to array of bits	

The bmWidthBytes field must be an even number—the lowest even number of bytes required to store one scan line. The array of the bits referenced by bmBits must be organized based on the bmWidthBytes field. If bm is a structure variable of type BITMAP, you can calculate the bmWidthBytes field by the following statement:

```
bm.bmWidthBytes = (bm.bmWidth * bm.bmBitsPixel + 15) / 16 * 2;
```

If Windows cannot create the bitmap (generally because not enough memory is available), it will return a NULL. You should check the return value from the bitmap creation functions, particularly if you're creating large bitmaps.

The handle to the bitmap is not a handle to a global memory block, so don't try to use the GlobalLock function on it. The handle is instead a local handle to the GDI module's data segment. This handle references a small local memory block in GDI that contains a second handle to a global memory block containing the information in the BITMAP structure and the actual bits.

Once you create a bitmap, you cannot change the size, the number of color planes, or the number of bits per pixel. You would have to create a new bitmap and transfer the bits from the original bitmap to this new bitmap. If you have a handle to a bitmap, you can get the size and color organization using:

```
GetObject (hBitmap, sizeof (BITMAP), (LPSTR) &bitmap);
```

This copies the information about the bitmap into a structure (called *bitmap* here) of type BITMAP. This function doesn't fill in the *bmBits* field. To get access to the actual bits of the bitmap, you must call:

```
GetBitmapBits (hBitmap, dwCount, lpBits);
```


This copies dwCount bits into a character array referenced by the far pointer lpBits. To ensure that all the bits of the bitmap are copied into this array, you can calculate the dwCount parameter based on the fields of the bitmap structure:

You can also direct Windows to copy a character array containing the bitmap bits back into an existing bitmap using the function:

```
SetBitmapBits (hBitmap, dwCount, lpBits);
Because bitmaps are GDI objects, you should delete any bitmap you create:
DeleteObject (hBitmap);
```

The Monochrome Bitmap Format

For a monochrome bitmap, the format of the bits is relatively simple and can almost be derived directly from the image you want to create. For instance, suppose you want to create a bitmap that looks like this:



You can write down a series of bits (0 for black and 1 for white) that directly corresponds to this grid. Reading these bits from left to right, you can then assign each group of 8 bits a hexadecimal byte. If the width of the bitmap is not a multiple of 16, pad the bytes to the right with zeros to get an even number of bytes:

The width in pixels is 20, the height in scan lines is 5, and the width in bytes is 4. You can set up a logical bitmap structure for this bitmap with the following statement:

= { 0, 20, 5, 4, 1, 1 };

```
and you can store the bits in a BYTE array:

static BYTE byBits [] = { 0x51, 0x77, 0x10, 0x00, 0x57, 0x77, 0x50, 0x00, 0x13, 0x77, 0x50, 0x00, 0x57, 0x77, 0x50, 0x00, 0x51, 0x11, 0x10, 0x00 };
```

static BITMAP bitmap

Creating the bitmap with CreateBitmapIndirect requires two statements:

```
bitmap.bmBits = (LPSTR) byBits ;
hBitmap = CreateBitmapIndirect (&bitmap) ;
```

Be careful when working with the pointer to byBits. It's OK to call CreateBitmapIndirect right after you assign the far address to the bmBits field, but this field can become invalid if Windows moves your local data segment.

You may prefer the following statements, which avoid this problem:

```
hBitmap = CreateBitmapIndirect (&bitmap);
SetBitmapBits (hBitmap, (DWORD) sizeof byBits, &byBits);
```

You can also avoid using the bitmap structure entirely and create the bitmap in one statement:

```
hBitmap = CreateBitmap (20, 5, 1, 1, &byBits);
```

The Color Bitmap Format

Bitmaps in color are a little more complex and are extremely device dependent. A color bitmap is organized to facilitate the transfer of the bits to a particular device. Whether the bitmap is organized as a series of color planes or as multiple color bits per pixel depends on the device for which the bitmap is suitable.

Let's look first at a bitmap that has a *bmBitsPixel* field of 1 (which means that it has 1 color bit per pixel) but a *bmPlanes* value greater than 1. A color bitmap for the EGA is a good example. Windows uses three color planes of the EGA, so *bmPlanes* is 3. The array of bits begins with the array of bits for the first plane, followed by the array of bits for the second plane, followed by the array of bits for the third plane. In effect, the monochrome format for the array is simply repeated for the number of planes in the bitmap. For the EGA, the first plane is defined as red, the second as blue, and the third as green.

A bitmap can also represent color as a multiple number of bits per pixel. Suppose a device can represent 16 colors using 4 color bits per pixel. For each scan line, the first 4 bits represent the color for the leftmost pixel, the second 4 bits represent the color for the next pixel, and so forth. The *bmWidthBytes* value in the BITMAP structure reflects the increased byte width of each scan line, but the *bmWidth* value is still the number of pixels per scan line.

Here's the catch: Nothing in the bitmap specifies how these multiple planes or multiple color bits correspond to actual display colors. A particular color bitmap is suitable only for a particular color output device with actual display memory organized like the bitmap. For instance, suppose you have a device that stores color information in three color planes, but the first plane represents cyan, the second plane magenta, and the third plane yellow. This arrangement is perfectly legitimate—it's simply a different way of representing color than that used by the EGA. A bitmap created on this device would have the same bit organization as the EGA bitmap, but the planes mean different things. If you displayed such a bitmap on the EGA, the image might be recognizable, but the colors would be wrong.

Bitmaps as Files

You can also store bitmaps as disk files. By convention, the extension for such a bitmap is BMP. ICONEDIT lets you create monochrome bitmap files, and in Chapter 17 you'll see how to create a bitmap file for any bitmap you can copy into the clipboard. The following table shows the format of the bitmap file:

Offset	Size	Corresponding BITMAP Field	Value
0	Byte		2
1	Byte		80H for discardable bitmap
2	Word	bmType	0
4	Word	bmWidth	Width in pixels
6	Word	bmHeight	Height in scan lines
6 8	Word	bmWidthBytes	Width in even number of bytes
10	Byte	bmPlanes	Number of color planes
11	Byte	bmBitsPixel	Number of color bits per pixel
12	Word		0
14	Word		0
16			Bits

You'll note that six of these fields correspond to the BITMAP structure. Within your program, you can load a bitmap file into memory using normal file I/O calls. You can then use the information in the file to create a bitmap with the four functions described earlier. We'll do this in Chapter 17.

You can also make a bitmap file into a resource, as we did in Chapter 9. The resource script includes a statement that looks something like this:

```
MyBitmap BITMAP filename.bmp
```

Your program gets a handle to the bitmap with the LoadBitmap function:

```
hBitmap = LoadBitmap (hInstance, "MyBitmap") ;
```

Unlike other resources, bitmaps must be explicitly deleted before your program terminates:

```
DeleteObject (hBitmap) ;
```

The Dimensions of a Bitmap

Two other functions connected with bitmaps are the source of some confusion. These are:

```
SetBitmapDimension (hBitmap, xDimension, yDimension);
and:

dwDimension = GetBitmapDimension (hBitmap);
```

The xDimension and yDimension values (encoded as the low and high words in the dwDimension value returned from GetBitmapDimension) are the width and height of the bitmap in units of 0.1 mm, which correspond to logical units in the MM_LOMETRIC mapping mode. GDI itself doesn't use these dimensions. They are part of neither the BITMAP structure nor the bitmap file format. However, two cooperating applications could use these dimensions to aid in the scaling of bitmaps that are exchanged through the clipboard or other means.

TIFF: Tag Image File Format

To aid in the interchange of bitmapped digital images between digital scanners, printers, and application programs such as page makeup software, Microsoft and Aldus Corporation (in conjunction with some hardware manufacturers) have devised a more extensive format for the storage of bitmaps in files. This is called TIFF, the Tag Image File Format. The information in this format includes aspect ratio information (in terms of pixels per inch horizontally and vertically), color representation, orientation, and a bitmap compression method, if one is used. Information on TIFF is included with the Windows Software Development Kit.

THE MEMORY DEVICE CONTEXT

When you first start working with bitmaps, it may come as a bit of a shock to find that Windows doesn't have a function that transfers a bitmap to the display surface of a device context. You'll search in vain for a function that looks like this:

```
DrawBitmap (hDC, xStart, yStart, hBitmap) ; /* No such function !!! */
```

This function would copy a bitmap to the device context represented by hDC beginning at the logical point (xStart, yStart). We'll write our own DrawBitmap function later in this chapter. First, however, you need to become familiar with several concepts, starting with the memory device context.

A memory device context is a device context that has a "display surface" that exists only in memory. You can create a memory device context using the function:

```
hMemDC = CreateCompatibleDC (hDC) ;
```

The hDC handle is a handle to an existing valid device context. The function returns a handle to the memory device context. Upon creation of the memory device context, all the attributes are set to the normal default values. You can do almost anything you want with this memory device context. You can set the attributes to nondefault values, obtain the current settings of the attributes, and select pens, brushes, regions into it. And yes, you can even draw on it. But it doesn't make much sense to do so just yet. Here's why.

When you first create a memory device context, it has a "display surface" that contains exactly 1 monochrome pixel. That is a very small display surface. (Don't rely on Get-DeviceCaps to tell you this. The HORZSIZE, VERTSIZE, HORZRES, VERTRES, BITSPIXEL, and PLANES values for hMemDC will all be set to the values associated with the original hDC. If GetDeviceCaps really returned the correct values associated with the memory device context when it is first created, then the HORZRES, VERTRES, BITSPIXEL, and PLANES indexes would all return 1.) What you need to do is make the display surface of the memory device context larger. You do this by selecting a bitmap into the device context:

```
SelectObject (hMemDC, hBitmap);
```

Now the display surface of hMemDC has the same width, height, and color organization as the bitmap referenced by hBitmap. With the default window and viewport origins, the logical point (0, 0) of the memory device context corresponds to the upper left corner of the bitmap.

If the bitmap had some kind of picture on it, then that picture is now part of the memory device context's display surface. Any changes you make to that bitmap (for instance, by using SetBitmapBits to set a different array of bits to the bitmap) are reflected in this display surface. Anything you draw on the memory device context is actually drawn on the bitmap. In short, the bitmap is the display surface of the memory device context.

Earlier I discussed the various functions to create bitmaps. One of them is:

```
hBitmap = CreateCompatibleBitmap (hDC, xWidth, yHeight);
```

If hDC is the handle to the normal device context for a screen or a printer, then the number of color planes and number of bits per pixel of this bitmap are the same as for the device. However, if hDC is the handle to a memory device context (and no bitmap has yet been selected into the memory device context), then CreateCompatibleBitmap returns a monochrome bitmap that is xWidth pixels wide and yHeight pixels high.

A bitmap is one of five GDI objects. You saw in Chapter 13 how to use SelectObject to select a pen, brush, or region into a device context, and in Chapter 15 you'll learn how to use the function to select a font into a device context. You can use SelectObject to select these four GDI objects into a memory device context also. However, you cannot select a bitmap into a normal device context, only into a memory device context.

When you're finished with the memory device context, you must delete it:

```
DeleteDC (hMemDC) ;
```

Well, you may say, this is all very nice, but we haven't yet solved the problem of getting the bitmap on the display. All we've done is select it into a memory device context. Now what? Now we have to learn how to "blt" (pronounced "blit") the bits from one device context to another.

THE MIGHTY BLT

Graphics involves writing pixels on a display device. In Chapter 13 we looked at the more refined ways of doing this, but for power-pixel manipulation, nothing in Windows comes close to BitBlt and its two cousins, PatBlt and StretchBlt. BitBlt (pronounced "bit blit") stands for "bit block transfer." BitBlt is a pixel-mover, or (more vividly) a raster-blaster. The simple word transfer doesn't really do justice to BitBlt. It does more than a transfer—it really does a logical combination of three sets of pixels using 1 of 256 different types of raster operations.

The PatBit Function

PatBlt ("pattern block transfer") is the simplest of the three "blt" functions. It's really quite different from BitBlt and StretchBlt in that it uses only one device context. But PatBlt is nonetheless a reasonable place to begin.

In Chapter 13 you encountered the device context attribute called the drawing mode. This attribute can be set to 1 of 16 binary raster operation (ROP2) codes. When you draw a line, the drawing mode determines the type of logical operation that Windows performs on the pixels of the pen and the pixels of the device context destination. PatBlt is similar to the drawing mode except that it alters a rectangular area of the device context destination rather than merely a line. It performs a logical operation involving the pixels in this rectangle and a "pattern." This "pattern" is nothing new—pattern is simply another name for a brush. For this pattern, PatBlt uses the brush currently selected in the device context.

The syntax of PatBlt is:

PatBlt (hDC, xDest, yDest, xWidth, yHeight, dwROP);

The xDest, yDest, xWidth, and yHeight parameters are in logical units. The logical point (xDest, yDest) specifies the upper left corner of a rectangle. The rectangle is xWidth units wide and yHeight units high. (See the section below entitled "Blt Coordinates" for a more precise definition of these values.) This is the rectangular area that PatBlt alters. The logical operation that PatBlt performs on the brush and the destination device context is determined by the dwROP parameter, which is a doubleword (32-bit integer) ROP code—not one of the ROP2 codes used for the drawing mode.

Windows has 256 ROP codes. These define all possible logical combinations of a source display area, a destination display area, and a pattern (or brush). The device driver for the video display supports all 256 raster operations through the use of a "compiler" of sorts. This compiler uses the 32-bit ROP code to create a set of machine-language instructions on the stack that can carry out this logical operation on the pixels of the display; it then executes these instructions. The high word of the 32-bit ROP code is a number between 0 and 255. The low word is a number that assists the device driver "compiler" in constructing the machine

code for the logical operation. Fifteen of the 256 ROP codes have names. If you want to use any of the others, you'll have to look up the number in the table in the Programmer's Reference included with the Windows Software Development Kit.

Because the *PatBlt* function uses only a destination device context and a pattern (and not a source device context), it can accept only a subset of these 256 ROP codes—that is, the 16 ROP codes that use only the destination device context and a pattern. The 16 raster operations supported by *PatBlt* are shown in the table below. You'll note that this is similar to the table showing ROP2 codes on page 551 of Chapter 13.

Pattern (P): Destination (D):	1	0	0	0	Boolean Operation	ROP Code	Name
Result:	0	0	0	0	0	000042	BLACKNESS
	0	0	0	1	~(P D)	0500A9	
	0	0	1	0	-P & D	0A0329	
	0	0	1	1	~p	OFO001	
	0	1	0	0	P & ~D	500325	
	0	1	0	1	~D	550009	DSTINVERT
	0	1	1	0	$P \wedge D$	5A0049	PATINVERT
	0	1	1	1	~(P & D)	5F00E9	
	1	0	0	0	P & D	A000C9	
	1	0	0	1	-(P ∧ D)	A50065	
	1	0	1	0	D	AA0029	
	1	0	1	1	~P D	AF0229	
	1	1	0	0	P	F00021	PATCOPY
	1	1	0	1	P ~D	F50225	
	1	1	1	0	PD	FA0089	
	1	1	1	1	1	FF0062	WHITENESS

For a monochrome device context, a 1 bit corresponds to a white pixel and a 0 bit to a black pixel. Destinations and patterns that are either pure black or pure white are the easiest to consider when you start thinking about *PatBlt*. For instance, if you call:

```
PatBlt (hDC, xDest, yDest, xWidth, yHeight, 0x5F00E9L);
```

then the rectangular area that begins at the logical point (xDest, yDest) and that is xWidth pixels wide and yHeight pixels high will be colored black only if the destination was originally white and you had WHITE_BRUSH selected in the device context. Otherwise, the destination will be colored white. Of course, even in a monochrome device context, destinations and brushes can be dithered combinations of black and white pixels. In this case, Windows performs the logical combination on a pixel-by-pixel basis, which can lead to some odd results. For instance, if your destination has already been colored with GRAY_BRUSH, and GRAY_BRUSH is also the current brush selected in the device context, then:

```
PatBlt (hDC, xDest, yDest, xWidth, yHeight, PATINVERT);
```

will set the destination to either pure white or pure black, depending on how the dithered pixels of the destination coincide with the dithered pixels of the brush.

Color introduces more complexities. Windows performs the logical operation for each color plane separately or each set of color bits separately, depending on how the memory of the device is organized.

Some of the more common uses of *PatBlt* are shown below. If you want to draw a black rectangle, you call:

```
PatBlt (hDC, xDest, yDest, xWidth, yHeight, BLACKNESS);
```

To draw a white rectangle, use:

```
PatBlt (hDC, xDest, yDest, xWidth, yHeight, WHITENESS);
```

The function:

```
PatBlt (hDC, xDest, yDest, xWidth, yHeight, DSTINVERT) ;
```

always inverts the colors of the rectangle. If WHITE_BRUSH is currently selected in the device context, then the function:

```
PatBlt (hDC, xDest, yDest, xWidth, yHeight, PATINVERT) ;
```

also inverts the rectangle.

You'll recall that the FillRect function fills in a rectangular area with a brush:

```
FillRect (hDC, &rect, hBrush);
```

The FillRect function is equivalent to this code:

In fact, this code (in more optimized assembly language) is what Windows uses to execute the FillRect function. When you call:

```
InvertRect (hDC, &rect) ;
```

Windows translates it into the function:

```
PatBlt (hDC, rect.left, rect.top,
rect.right - rect.left,
rect.bottom - rect.top, DSTINVERT);
```

Blt Coordinates

When I introduced the syntax of the *PatBlt* function, I said that the point (*xDest*, *yDest*) specifies the upper left corner of a rectangle and that this rectangle is *xWidth* units wide and *yHeight* units high. Actually, although that's also what the Windows documentation says, the statement is not entirely accurate. Before we proceed any further, I need to clear up some confusion concerning the blt functions and coordinates.

BitBlt, PatBlt, and StretchBlt are the only GDI drawing functions that specify logical rectangular coordinates in terms of a logical width and height measured from a single corner. All the other GDI drawing functions that use rectangular bounding boxes require that coordinates be specified in terms of an upper left corner and a lower right corner. For the MM_TEXT mapping mode, the above description of the PatBlt parameters is accurate. For the metric mapping modes, however, it's not. If you use positive values of xWidth and yHeight, then the point (xDest, yDest) will be the lower left corner of the rectangle. If you want (xDest, yDest) to be the upper left corner of the rectangle, the yHeight parameter must be set to the negative height of the rectangle.

To be more precise, the rectangle that *PatBlt* colors has a logical width given by the absolute value of *xWidth* and a logical height given by the absolute value of *yHeight*. These two parameters can be negative. The rectangle is defined by two corners given by the logical points (*xDest*, *yDest*) and (*xDest* + *xWidth*, *yDest* + *yHeight*). The upper left corner of the rectangle is always included in the area that *PatBlt* modifies. The lower right corner is outside the rectangle. Depending on the mapping mode and the signs of the *xWidth* and *yHeight* parameters, the upper left corner of this rectangle could be the point:

```
(xDest, yDest)

Or:
    (xDest, yDest + yHeight)

Or:
    (xDest + xWidth, yDest)

Or;
    (xDest + xWidth, yDest + yHeight);
```

If you've set the mapping mode to MM_LOENGLISH and you want to use PatBlt on the square inch at the upper left corner of the client area, you can use:

```
PatBlt (hDC, 0, 0, 100, -100, dwROP);

Or:

PatBlt (hDC, 0, -100, 100, 100, dwROP);

Or:

PatBlt (hDC, 100, 0, -100, -100, dwROP);

Or:

PatBlt (hDC, 100, -100, -100, 100, dwROP);
```

The easiest way to set the correct parameters to PatBlt is to set xDest and yDest to the upper left corner of the rectangle. If your mapping mode defines y coordinates as increasing

as you move up the display, use a negative value for the *yHeight* parameter. If your mapping mode defines *x* coordinates as increasing to the left (which is almost unheard of), use a negative value for the *xWidth* parameter.

Transferring Bits with BitBlt

In one sense, BitBlt is a superset of PatBlt. It does everything PatBlt does but also introduces a second device context into the logical operation. Here's the general syntax:

```
BitBlt (hDestDC, xDest, yDest, xWidth, yHeight, hSrcDC, xSrc, ySrc, dwROP);
```

The *BitBlt* call modifies the destination device context (whose handle is *hDestDC*) within the rectangle defined by the logical point (*xDest*, *yDest*) and the *xWidth* and *yHeight* parameters, both of which are in logical units. These parameters define a rectangle as described in the previous section. *BitBlt* also uses a rectangle in a source device context (whose handle is *SrcDC*). This rectangle begins at the logical point (*xSrc*, *ySrc*) and is also *xWidth* logical units wide and *yHeight* logical units high.

BitBlt performs a logical combination of three elements: the brush selected in the destination device context, the pixels in the source device context rectangle, and the pixels in the destination device context rectangle. The result is written to the destination device context rectangle. You can use any of the 256 ROP codes for the dwROP parameter to BitBlt. The 15 ROP codes that have names are shown in the table below. If you need to use any of the others, you can look them up in the Programmer's Reference.

Pattern (P): Source (S): Destination (D):	1 1 1	1 1 0	1 0 1	000	0 1 1	0 1 0	0 0 1	0 0	Boolean Operation	ROP Code	Name
Result:	0	0	0	0	0	0	0	0	0	000042	BLACKNESS
2000	0	0	0	1	0	0	0	1	- (S D)	1100A6	NOTSRCERASE
	0	0	1	1	0	0	1	1	~S	330008	NOTSRCCOPY
	0	1	0	0	0	1	0	0	S & -D	440328	SRCERASE
	0	1	0	1	0	1	0	1	-D	550009	DSTINVERT
	0	1	0	1	1	0	1	0	$P \wedge D$	5A0049	PATINVERT
	0	1	1	0	0	1	1	0	SAD	660046	SRCINVERT
	1	0	0	0	1	0	0	0	S & D	8800C6	SRCAND
	1	0	1	1	1	0	1	1	-s D	BB0226	MERGEPAINT
	1	1	0	0	0	0	0	0	P&S	C000CA	MERGECOPY
	1	1	0	0	1	1	0	0	S	CC0020	SRCCOPY
	1	1	1	0	1	1	1	0	SID	EE0086	SRCPAINT
	1	1	1	1	0	0	0	0	P	F00021	PATCOPY
	1	1	1	1	1	0	1	1	P -S D	FB0A09	PATPAINT
	1	1	1	1	1	1	1	1	1	FF0062	WHITENESS

Look at the eight 0's and 1's that show the result of the logical combination. The twodigit hexadecimal number that corresponds to these bits is the high word of the ROP code. If we can create a table of the result we want from the pattern, source, and destination, we can easily determine the ROP code from the table of ROP codes in the Programmer's Reference. We'll be doing this a little later. If you use 1 of the 16 ROP codes shown in the table on page 610, then you can use *PatBlt* instead of *BitBlt*, because you're not referencing a source device context.

You can set hSrcDC and hDestDC to the same device context handle, in which case BitBlt will perform a logical combination of the destination rectangle, the source rectangle, and the current brush selected in the device context. However, it's a little risky to do this in your client-area device context. If part of the source rectangle is covered by another window, then Windows will use the pixels of this other window as the source. Windows doesn't know what's underneath that dialog box in your client area.

However, examples of the BitBlt function using the same device context for the source and destination are the easiest to grasp. The function:

```
BitBlt (hDC, 100, 0, 50, 100, hDC, 0, 0, SRCCOPY);
```

copies the rectangle beginning at logical point (0, 0) that is 50 logical units wide and 100 logical units high to the rectangular area beginning at the logical point (100, 0).

The DrawBitmap Function

BitBlt becomes most valuable in working with bitmaps that have been selected into a memory device context. When you perform a "bit block transfer" from the memory device context to a device context for your client area, the bitmap selected in the memory device context is transferred to your client area.

Earlier I mentioned a hypothetical *DrawBitmap* function that would draw a bitmap on a display surface. Such a function would have the syntax:

```
DrawBitmap (hDC, xStart, yStart, hBitmap) ;
```

I promised we'd write a DrawBitmap function; here it is:

void DrawBitmap (hDC, xStart, yStart, hBitmap)

```
HDC hDC;
short xStart, yStart;
HBITMAP hBitmap;
(
BITMAP bm;
HDC hMemDC;
DWORD dwSize;
POINT pt;
```

```
hMemDC = CreateCompatibleDC (hDC);
SelectObject (hMemDC, hBitmap);
SetMapMode (hMemDC, GetMapMode (hDC));

GetObject (hBitmap, sizeof (BITMAP), (LPSTR) &bm);
pt.x = bm.bmWidth;
pt.y = bm.bmHeight;
DPtoLP (hDC, &pt, 1);

BitBlt (hDC, xStart, yStart, pt.x, pt.y, hMemDC, 0, 0, SRCCOPY);
DeleteDC (hMemDC);
```

I'm assuming here that you don't want the height or width of the bitmap stretched or compressed in any way. That is, if your bitmap is 100 pixels wide, you want it to cover a 100-pixelwide rectangle of your client area regardless of the mapping mode.

DrawBitmap first creates a memory device context using CreateCompatibleDC and then selects the bitmap into it with SelectObject. The mapping mode of the memory device context is set to the same mapping mode as the video device context. Because BitBlt works with logical coordinates and logical sizes and you don't want the bitmap stretched or compressed, the xWidth and yHeight parameters to BitBlt must be logical units that correspond to the physical pixel size of the bitmap. For this reason, DrawBitmap gets the dimensions of the bitmap using GetObject and makes a POINT structure out of the width and height. It then converts this point to logical coordinates.

Copying the bitmap to the screen requires the BitBlt function:

```
BitBlt (hDC, xStart, yStart, pt.x, pt.y, hMemDC, 0, 0, SRCCOPY);
```

Notice the use of zero xSrc and ySrc coordinates—when you select a bitmap into a memory device context, the point (0, 0) represents the upper left corner of the bitmap. Also notice that it doesn't matter what brush is currently selected in the destination device context (hDC), because SRCCOPY doesn't use the brush.

Using Different ROP Codes

SRCCOPY is definitely the most popular dwROP parameter to BitBlt, and you may be hardpressed to find uses for the other 255 ROP codes. So I'll give you a couple of examples in which other ROP codes show their stuff.

In the first example, you have a monochrome bitmap that you want to transfer to the screen. However, you want to display the bitmap so that the black (0) bits don't affect anything currently on the client area. Moreover, you want all the white (1) bits to color the client area with a brush, perhaps a colored brush created from *CreateSolidBrush*. How do you do it? I'll assume that you're working in the MM_TEXT mapping mode and that you want

to write the bitmap starting at the point (xStart, yStart) in your client area. You already have a handle to the monochrome bitmap (hBitmap) and a handle to the colored brush (hBrush). You know the width and height of the bitmap and have them stored in a BITMAP structure named bm. Here's the code:

```
hMemDC = CreateCompatibleDC (hDC);
SelectObject (hMemDC, hBitmap);
hBrush = SelectObject (hDC, hBrush);
BitBlt (hDC, xStart, yStart, bm.bmWidth, bm.bmHeight, hMemDC, 0, 0, 0xE20746L);
SelectObject (hDC, hBrush);
DeleteDC (hMemDC);
```

BitBlt performs a logical combination of a destination device context (hDC), a source device context (hMemDG), and the brush currently selected in the destination device context. So you create a memory device context, select the bitmap into it, select the colored brush into your client-area display context, and call BitBlt. Then you select the original brush into your display device context and delete the memory device context.

The only puzzling part of this code is the ROP code 0xE20746. This ROP code causes Windows to perform the logical operation:

((Destination \ Pattern) & Source) \ Destination

Still not obvious? Try this approach: Copy this part of the table on page 613:

									- 11
Pattern:	1	1	1	1	0	0	0	0	
Source:	1	1	0	0	1	1	0	0	
Destination:	1	0	1	0	1	0	1	0	
Result:	?	?	?	?	?	3	?	?	

For every black bit in the bitmap (which will be selected into the source memory device context), you want the destination device context to be unchanged. This means that everywhere the Source is a 0, you want the Result to be the same bit as the Destination:

Pattern:	1	1	1	1	0	0	0	0	
Source:	1	1	0	0	1	1	0	0	
Destination:	1	0	1	0	1	0	1	0	
Result:	?	?	1	ō	?	?	1	0	

We're halfway there. For every white bit in the bitmap, you want the destination device context to be colored with the pattern. The brush you select in the destination device context is this pattern. So everywhere the Source is 1 you want the Result to be the Pattern:

Pattern:	1	1	1	1	0	0	0	0
Source:	1	1	0	0	1	1	0	0
Destination:	1	0	1	0	1	0	1	0
Result:	1	1	1	0	0	0	1	0

This means that the high word of the ROP code is 0xE2. You can look that up in the ROP table in the Programmer's Reference and find that the full ROP code is 0xE20746.

Perhaps at this point you discover that you mixed up the white and black bits when you created the bitmap in ICONEDIT. That's easy to fix. It's merely a different logical operation:

Pattern:	1	1	1	1	0	0	0	0
Source:	1	1	0	0	1	1	0	0
Destination:	1	0	1	0	1	0	1	0
Result:	1	0	1	$\overline{1}$	1	0	0	ō

Now the high word of the ROP code is 0xB8, and the entire ROP code is 0xB8074A, which performs the logical operation:

((Destination \(^{\text{Pattern}}\)) & Source) \(^{\text{Pattern}}\)

Here's the second example: Back in Chapter 9 I discussed the two bitmaps that make up icons and cursors. The use of two bitmaps allows these figures to be "transparent" in spots or to invert the display surface underneath. The two bitmaps for icons and cursors are coded as follows:

Bitmap 1:	0	0	1	1
Bitmap 2:	0	1	0	1
Result:	Black	White	Screen	Inverse Screen

Windows selects Bitmap 1 into a memory device context and uses *BitBlt* with a ROP code called SRCAND to transfer the bitmap to the display. This ROP code performs the logical operation:

Destination & Source

In Bitmap 1, the destination is left unchanged for 1 bits and set to 0 for 0 bits. Windows then selects Bitmap 2 into the device context and uses *BitBlt* with SRCINVERT. The logical operation is:

Destination \ Source

In Bitmap 2, this leaves the destination unchanged for all 0 bits and inverts the destination for all 1 bits.

Look at the first and second columns of the table: Bitmap 1 with SRCAND blacks out the bits, and Bitmap 2 with SRCINVERT turns selected bits to white by inverting the black bits. These operations set the black and white bits that make up the icon or cursor. Now look at the third and fourth columns of the table: Bitmap 1 with SRCAND leaves the display unchanged, and Bitmap 2 with SRCINVERT inverts the colors of selected bits. These operations let the icon or cursor be transparent or invert the underlying colors.

Another example of the creative use of ROP codes accompanies the description of the GrayString function in Chapter 15.

More Fun with Memory Device Contexts

We've been using memory device contexts to transfer an existing bitmap to the display. You can also use memory device contexts to draw on the surface of a bitmap. We did this in the GRAFMENU program in Chapter 10, when we used the *GetBitmapFont* function to make menu items using bitmaps. First, you create a memory device context:

```
hMemDC = CreateCompatibleDC (hDC) ;
```

Next, you create a bitmap of the desired size. If you want to create a monochrome bitmap, you can make it compatible with hMemDG:

```
hBitmap = CreateCompatibleBitmap (hMemDC, xWidth, yHeight);
```

Or to make the bitmap have the same color organization as the video display, you can make the bitmap compatible with hDG:

```
hBitmap = CreateCompatibleBitmap (hDC, xWidth, yHeight) ;
```

You can now select the bitmap into the memory device context:

```
SelectObject (hMemDC, hBitmap) ;
```

Now you can draw on this memory device context (and by extension, the bitmap) using all the GDI functions we discussed in Chapters 12 and 13 and more that you'll encounter in Chapter 15. When you first create the bitmap, it contains random bits, so you may want to begin by using the *PatBlt* function with a ROP code of WHITENESS or BLACKNESS to erase the background of the memory device context.

When you're done drawing on the memory device context, simply delete it:

```
DeleteDC (hMemDC) ;
```

Now you're left with a bitmap containing everything you drew on it while it was selected in the memory device context. (We'll go through this process again in the BOUNCE program shown later in this chapter.)

The SCRAMBLE program, shown in Figure 14-1, uses a memory device context as a temporary holding space for *BitBlt* operations that swap the contents of two rectangles of the display.

```
scramble.obj : scramble.c
cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp scramble.c
scramble.exe : scramble.obj scramble.def
link4 scramble, /align:16, /map, slibw, scramble
```

```
/* SCRAMBLE.C -- Scramble (and Unscramble) Screen */
#include <windows.h>
#include <stdlib.h>
#define NUM 200
long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG) ;
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
                       hInstance, hPrevInstance;
      HANDLE
                        lpszCmdLine :
       int
                        nCmdShow ;
      static short nKeep [NUM][4] ;
      HDC
                       hDC
                                 = CreateDC ("DISPLAY", NULL, NULL, NULL) ;
      HDC
                        hMemDC = CreateCompatibleDC (hDC) ;
                       xSize = GetSystemMetrics (SM_CXSCREEN) / 10;
ySize = GetSystemMetrics (SM_CYSCREEN) / 10;
      short
      HBITMAP
                       hBitmap = CreateCompatibleBitmap (hDC, xSize, ySize) ;
                       i, j, x1, y1, x2, y2;
      SelectObject (hMemDC, hBitmap) ;
      srand (LOWORD (GetCurrentTime ())) ;
      for (i = 0 ; i < 2 ; i++)
             for (j = 0 ; j < NUM ; j++)
                    if (i == 0)
                          nKeep [i] [0] = x1 = xSize * (rand () % 10) ;
                          NKeep [j] [1] = y1 = ySize * (rand () % 10);

nKeep [j] [2] = x2 = xSize * (rand () % 10);

nKeep [j] [3] = y2 = ySize * (rand () % 10);
                    else
                         x1 = nKeep [NUM - 1 - j] [0];
y1 = nKeep [NUM - 1 - j] [1];
x2 = nKeep [NUM - 1 - j] [2];
                          y2 = nKeep [NUM - 1 - j] [3] ;
                   BitBlt (hMemDC, 0, 0, xSize, ySize, hDC, x1, y1, SRCCOPY);
BitBlt (hDC, x1, y1, xSize, ySize, hDC, x2, y2, SRCCOPY);
BitBlt (hDC, x2, y2, xSize, ySize, hMemDC, 0, 0, SRCCOPY);
      return FALSE ;
```

Figure 14-1. The SCRAMBLE program

(continued)

Figure 14-1. Continued

```
NAME SCRAMBLE
DESCRIPTION 'Screen Scrambler (C) Charles Petzold, 1987'
STUB 'WINSTUB.EXE'
CODE MOVEABLE
DATA MOVEABLE MULTIPLE
HEAPSIZE 1024
STACKSIZE 4096
```

SCRAMBLE doesn't have a window function. In WinMain, it obtains a device context for the entire screen:

```
hDC = CreateDC ("DISPLAY", NULL, NULL, NULL);
and also a memory device context:
hMemDC = CreateCompatibleDC (hDC);
```

Then it determines the dimensions of the full screen and divides them by 10:

```
xSize = GetSystemMetrics (SM_CXSCREEN) / 10 ;
ySize = GetSystemMetrics (SM_CYSCREEN) / 10 ;
```

The program uses these dimensions to create a bitmap:

```
hBitmap = CreateCompatibleBitmap (hDC, xSize, ySize) ;
```

and selects it into the memory device context:

```
SelectObject (hMemDC, hBitmap) ;
```

Using the normal C rand ("random number generator") function, SCRAMBLE finds four random values that are multiples of the xSize and ySize values:

```
x1 = xSize * (rand () % 10);
y1 = ySize * (rand () % 10);
x2 = xSize * (rand () % 10);
y2 = ySize * (rand () % 10);
```

The program swaps two rectangular blocks of the display through the use of three BitBlt functions. The first copies the rectangle beginning at point (xI, yI) into the memory device context:

```
BitBlt (hMemDC, 0, 0, xSize, ySize, hDC, x1, y1, SRCCOPY);
```

The second copies the rectangle beginning at point (x2, y2) into the location beginning at (x1, y1):

```
BitBlt (hDC, x1, y1, xSize, ySize, hDC, x2, y2, SRCCOPY);
```

The third copies the rectangle in the memory device context to the area beginning at point (x2, y2):

```
BitBlt (hDC, x2, y2, xSize, ySize, hMemDC, 0, 0, SRCCOPY);
```

This process effectively swaps the contents of the two rectangles on the display. SCRAMBLE does this 200 times, after which the screen should be thoroughly scrambled. But do not fear, because SCRAMBLE keeps track of this mess and then unscrambles the screen, returning it to normal before exiting.

You can also use memory device contexts to copy the contents of one bitmap to another. For instance, suppose you want to create a bitmap that contains only the upper left quadrant of another bitmap. If the original bitmap has the handle hBitmap, you can copy the dimensions into a structure of type BITMAP:

```
GetObject (hBitmap, sizeof (BITMAP), (LPSTR) &bm);
```

and create a new uninitialized bitmap of one-quarter the size:

```
hBitmap2 = CreateBitmap (bm.bmWidth / 2, bm.bmHeight / 2, bm.bmPlanes, bm.bmBitsPixel, NULL);
```

Now create two memory device contexts and select the original bitmap and the new bitmap into them:

```
hMemDC1 = CreateCompatibleDC (hDC);
hMemDC2 = CreateCompatibleDC (hDC);
SelectObject (hMemDC1, hBitmap);
SelectObject (hMemDC2, hBitmap2);
```

Finally, copy the upper left quadrant of the first bitmap to the second:

```
BitBlt (hMemDC2, 0, 0, bm.bmWidth / 2, bm.bmHeight / 2,
    hMemDC1, 0, 0, SRCCOPY);
```

You're done except for cleaning up:

```
DeleteDC (hMemDC1);
DeleteDC (hMemDC2);
```

Color Conversions

If the destination and source device contexts in the *BitBlt* call have different color characteristics, Windows must convert the bitmap from one color format to another. The best color conversion occurs when the source bitmap is monochrome. Windows uses the text color and background color attributes in the destination device context for this conversion:

Monochrome DC (Source)	Color DC (Destination)	
0 (Black)	Text color (default is black)	
1 (White)	Background color (default is white)	

The background color attribute, which you encountered in Chapter 13, is the color Windows uses to fill in the gaps in dotted and dashed lines and between the hatches in hatched brushes. You can change the background color with SetBkColor. The text color, which you'll encounter in Chapter 15, determines the color of text. You can change this with SetTextColor. With default settings, the monochrome bitmap simply turns into a black and white bitmap on the color device context.

Translating a bitmap in a color source device context to a monochrome destination device context is less satisfactory:

Color DC (Source)	Monochrome DC (Destination)	
Pixel != Background color	0 (Black)	
Pixel == Background color	1 (White)	

In this case Windows uses the background color of the source device context to determine what color is translated to white. Every other color is translated to black.

Here's another color-related problem: Windows needs to equate a particular combination of color bits in the bitmap (either in different planes or the same planes) to the 32-bit color value of the background color. This means that the color device context must refer to a real device or be a memory device context based on a real device. For instance, suppose you have a monochrome device driver. You create a memory device context based on the screen device context and select a color bitmap into that memory device context. You now try to transfer that bitmap to a monochrome device context. It won't work, because Windows doesn't know how the multiple planes or multiple bits per pixel in the memory device context bitmap relate to real colors.

Mapping Mode Conversions

The *BitBlt* call requires different starting coordinates for the source and destination device contexts, but it needs only one width and one height:

```
BitBlt (hDestDC, xDest, yDest, xWidth, yHeight, hSrcDC, xSrc, ySrc, dwROP);
```

The xWidth and yHeight values are in logical units, and they apply to both the rectangle in the source device context and the rectangle in the destination device context. BitBlt must convert all coordinates and sizes to device coordinates before calling on the driver file to perform the actual operation. Because the xWidth and yHeight values are used for both the source and destination device contexts, the values must be converted to device units (pixels) separately for each device context.

When the source and destination device contexts are the same, or when both device contexts use the MM_TEXT mapping mode, then the size of this rectangle in device units will be the same in both device contexts. Windows can then do a simple pixel-to-pixel transfer. However, when the size of the rectangle in device units is different in the two device contexts, Windows turns the job over to the more versatile *StretchBlt* function.

Stretching Bitmaps with StretchBlt

StretchBlt adds two parameters to the BitBlt call:

```
StretchBlt (hDestDC, xDest, yDest, xDestWidth, yDestHeight, hSrcDC, xSrc, ySrc, xSrcWidth, ySrcHeight, dwROP);
```

Because StretchBlt accepts different width and height parameters for the source and destination rectangles, it allows you to stretch or compress a bitmap in the source device context to fit a larger or smaller area in the destination device context.

Just as *BitBlt* provides a superset of *PatBlt*'s functionality, *StretchBlt* expands on *BitBlt* by allowing you to specify the sizes of the source and destination rectangles separately. As with *PatBlt* and *BitBlt*, all coordinates and values in *StretchBlt* are in logical units. (We've already used *StretchBlt* in two programs: The BLOWUP program in Chapter 5 used the function to copy an area of the display into BLOWUP's client area; the GRAFMENU program in Chapter 10 used *StretchBlt* to expand the size of a bitmap for use in a menu.)

StretchBlt also allows you to flip an image vertically or horizontally. If the signs of xSrc-Width and xDestWidth (when converted to device units) are different, then StretchBlt creates a mirror image: Left becomes right, and right becomes left. If ySrcHeight and yDestHeight are different, then StretchBlt turns the image upside down. You can verify this with the BLOWUP program by capturing the image starting at the upper right corner (a negative width), the lower left corner (a negative height), or the lower right corner (a negative height and width).

If you've experimented with BLOWUP, you've probably discovered that *StretchBlt* can be slow, particularly when it works with a large bitmap. *StretchBlt* also has some problems related to the inherent difficulties of scaling bitmaps. When expanding a bitmap, *StretchBlt* must duplicate rows or columns of pixels. If the expansion is not an integral multiple, then the process can result in some distortion of the image.

When shrinking a bitmap, StretchBlt must combine two or more rows or columns of pixels into a single row or column. It does this in one of three ways, depending on the stretching mode attribute in the device context. You can use the SetStretchBltMode function to change this attribute:

```
SetStretchBltMode (hDC, nMode) ;
```

The value of nMode can be one of the following:

- BLACKONWHITE (default)—If two or more pixels have to be combined into one
 pixel, StretchBlt performs a logical AND operation on the pixels. The resulting
 pixel is white only if all the original pixels are white, which in practice means that
 black pixels predominate over white pixels.
- WHITEONBLACK—If two or more pixels have to be combined into one pixel, StretchBlt performs a logical OR operation. The resulting pixel is black only if all the original pixels are black, which means that white pixels predominate.

 COLORONCOLOR—StretchBlt simply eliminates rows or columns of pixels without doing any logical combination. This is often the best approach for color bitmaps, because the other two modes can cause color distortions.

Animation

I mentioned at the beginning of Chapter 12 that GDI supports only static pictures. Although it's true that Windows has no traditional animation support (such as the ability to flip video pages, check for vertical retrace of the video signal, or construct rotatable sprites), that doesn't mean that we can't move images around on the display. Yes, it's time for the bouncing ball program. The BOUNCE program, shown in Figure 14-2, constructs a ball that bounces around in the window's client area. The program uses the timer to pace the ball; it draws the ball with a simple "bit block transfer" from a memory device context.

```
bounce.obj : bounce.c
cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp bounce.c
bounce.exe : bounce.obj bounce.def
link4 bounce, /align:16, /map, slibw, bounce
```

```
/* BOUNCE.C -- Bouncing Ball Program */
#include <windows.h>
long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG) ;
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
    HANDLE hInstance, hPrevInstance;
    LPSTR
               lpszCmdLine ;
                nCmdShow ;
     int
     static char szAppName [] = "Bounce" ;
    HWND hWnd;
    MSG
               msq :
     WNDCLASS wndclass ;
     if (!hPrevInstance)
                                = CS HREDRAW | CS VREDRAW ;
         wndclass.stvle
         wndclass.lpfnWndProc = WndProc ;
         wndclass.cbClsExtra = 0;
                                = 0 ;
         wndclass.cbWndExtra
         wndclass.hInstance = hInstance;
         wndclass.hCon = NULL;
wndclass.hCursor = LoadCursor (NULL, IDC_ARROW);
         wndclass.hbrBackground = GetStockObject (WHITE BRUSH)
         wndclass.lpszMenuName = NULL ;
         wndclass.lpszClassName = szAppName ;
```

Figure 14-2. The BOUNCE program

(continued)

Figure 14-2. Continued

```
if (!RegisterClass (&wndclass))
               return FALSE ;
     hWnd = CreateWindow (szAppName, "Bouncing Ball",
                           WS OVERLAPPEDWINDOW,
                           CW_USEDEFAULT, 0,
CW_USEDEFAULT, 0,
                           NULL, NULL, hInstance, NULL) ;
     if (!SetTimer (hWnd, 1, 50, NULL))
          MessageBox (hWnd, "Too many clocks or timers!",
szAppName, MB_ICONEXCLAMATION | MB_OK);
          return FALSE ;
     ShowWindow (hWnd, nCmdShow) ;
     UpdateWindow (hWnd) ;
     while (GetMessage (&msg, NULL, 0, 0))
          TranslateMessage (&msg) ;
          DispatchMessage (&msg) ;
     return msg.wParam ;
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
                  hWnd ;
     unsigned
                    iMessage ;
                    wParam ;
     WORD
     LONG
                    1Param ;
     static HANDLE hBitmap ;
     static short xClient, yClient, xCenter, yCenter, xTotal, yTotal,
                    xRadius, yRadius, xMove, yMove, xPixel, yPixel;
     HBRUSH
                    hBrush ;
     HDC
                    hDC, hMemDC;
     short
                    nScale ;
     switch (iMessage)
          case WM CREATE:
                hDC = GetDC (hWnd) ;
                xPixel = GetDeviceCaps (hDC, ASPECTX);
yPixel = GetDeviceCaps (hDC, ASPECTY);
                ReleaseDC (hWnd, hDC) ;
                break ;
          case WM SIZE:
                xCenter = (xClient = LOWORD (1Param)) / 2 ;
                yCenter = (yClient = HIWORD (lParam)) / 2 ;
                nScale = min (xClient * xPixel, yClient * yPixel) / 16 ;
                xRadius = nScale / xPixel ;
               yRadius = nScale / yPixel ;
               xMove = max (1, xRadius / 4);
               yMove = max (1, yRadius / 4);
```

(continued)

Figure 14-2 Continued

```
xTotal = 2 * (xRadius + xMove) ;
          yTotal = 2 * (yRadius + yMove) ;
          if (hBitmap)
                DeleteObject (hBitmap) ;
          hDC = GetDC (hWnd) ;
          hMemDC = CreateCompatibleDC (hDC) ;
          hBitmap = CreateCompatibleBitmap (hDC, xTotal, yTotal) ;
          ReleaseDC (hWnd, hDC) ;
          SelectObject (hMemDC, hBitmap) ;
          Rectangle (hMemDC, -1, -1, xTotal + 1, yTotal + 1) ;
          hBrush = CreateHatchBrush (HS DIAGCROSS, OL) ;
          SelectObject (hMemDC, hBrush);
SetBkColor (hMemDC, RGB (255, 0, 255));
          Ellipse (hMemDC, xMove, yMove, xTotal - xMove, yTotal - yMove) ;
          DeleteDC (hMemDC) ;
          DeleteObject (hBrush) ;
          break ;
    case WM TIMER:
          if (!hBitmap)
                break ;
          hDC = GetDC (hWnd) ;
          hMemDC = CreateCompatibleDC (hDC) ;
          SelectObject (hMemDC, hBitmap) ;
          BitBlt (hDC, xCenter - xTotal / 2,
                   yCenter - yTotal / 2, xTotal, yTotal, hMemDC, 0, 0, SRCCOPY);
          ReleaseDC (hWnd, hDC) ;
          DeleteDC (hMemDC) ;
          xCenter += xMove ;
          vCenter += yMove ;
          if ((xCenter + xRadius >= xClient) ||
               (xCenter - xRadius <= 0))
                     xMove = -xMove ;
          if ((yCenter + yRadius >= yClient) ||
    (yCenter - yRadius <= 0))
    yMove = -yMove ;</pre>
           break :
     case WM DESTROY:
           if (hBitmap)
                DeleteObject (hBitmap) ;
           KillTimer (hWnd, 1) ;
           PostQuitMessage (0) ;
           break :
     default:
           return DefWindowProc (hWnd, iMessage, wParam, 1Param) ;
return OL ;
```

Figure 14-2. Continued

```
NAME BOUNCE
DESCRIPTION 'Bouncing Ball Program (C) Charles Petzold, 1987'
STUB 'WINSTUB.EXE'
CODE MOVEABLE
DATA MOVEABLE MULTIPLE
HEAPSIZE 1024
STACKSIZE 4096
EXPORTS WndProc
```

BOUNCE reconstructs the ball whenever the program gets a WM_SIZE message, the diameter of the ball being one-sixteenth of either the height or the width of the client area, whichever is shorter. However, the program constructs a bitmap that is larger than the ball—on each of its four sides, the bitmap extends beyond the ball's dimensions by a factor of 25 percent of the ball's radius.

After the bitmap is selected into a memory device context, it is colored white:

```
Rectangle (hMemDC, -1, -1, xTotal + 1, yTotal + 1);
```

A diagonally hatched brush is selected into the memory device context, and the ball is drawn in the center of the bitmap:

```
Ellipse (hMemDC, xMove, yMove, xTotal - xMove, yTotal - yMove) ;
```

The margins around the edges of the ball effectively erase the previous image of the ball when the ball is moved. Redrawing the ball at another position requires only a simple *BitBlt* call using the ROP code of SRCCOPY:

BOUNCE demonstrates the simplest way to move an image around the display, but this approach isn't satisfactory for general purposes. If you're interested in animation, you'll want to explore some of the other ROP codes (such as SRCINVERT) that perform an exclusive OR operation on the source and destination.

METAFILES

A metafile is a collection of GDI functions that are encoded in a binary form. You create a metafile by first creating a metafile device context. You can then use most of the GDI drawing functions to draw on this metafile device context. These GDI calls don't really draw on anything, however. Instead, they are stored within the metafile. When you close the metafile device context, you get back a handle to the metafile. You can then "play" this metafile on a real device context and execute the GDI functions in the metafile.

Metafiles are used most often for sharing pictures between programs through the clipboard. Because metafiles describe a picture as a collection of GDI calls, they take up much less space and are more device independent than bitmaps. I'll begin the discussion of metafiles with some simple examples and then take up the more theoretical considerations.

Simple Use of Memory Metafiles

Suppose your company's logo consists of a rectangle with lines drawn between the opposing corners and a blue circle in the center. You need to draw this logo often on the client area of your programs' windows and on the printer. Let's make that logo a metafile.

We'll begin by defining a few necessary variables:

```
static HANDLE hMF;
HANDLE hBrush;
HDC hMetaDC;
```

During processing of the WM_CREATE message, you can create the metafile. You call CreateMetaFile to obtain a handle to a metafile device context:

```
hMetaDC = CreateMetaFile (NULL) ;
```

The NULL parameter indicates that this will be a "memory" metafile; that is, the metafile will be stored in memory rather than as a disk file.

You can now draw your logo on this metafile device context. You decide you want it to be 100 units high and 100 units wide:

```
Rectangle (hMetaDC, 0, 0, 100, 100);
MoveTo (hMetaDC, 0, 0);
LineTo (hMetaDC, 100, 100);
MoveTo (hMetaDC, 0, 100);
LineTo (hMetaDC, 100, 0);

hBrush = CreateSolidBrush (RGB (0, 0, 255));
SelectObject (hMetaDC, hBrush);
Ellipse (hMetaDC, 20, 20, 80, 80);
```

When you're finished drawing, you close the metafile device context by calling CloseMetaFile, which returns a handle to the metafile:

```
hMF = CloseMetaFile (hMetaDC) ;
```

Now you can delete the brush you created:

```
DeleteObject (hBrush) ;
```

You're done creating the metafile. The hMF variable is defined as static, so it will remain in existence during other messages.

We drew the logo with a height and width of 100. Are these logical units or device units? At this point, they are neither: They are simply units. They will take on meaning only when you play the metafile. Let's do so. During processing of your WM_PAINT message, you may

want to fill up the client area with 100 logos, and you don't care whether they get stretched out somewhat. We'll assume that you've obtained values of xClient and yClient representing the width and height of the client area and that you've defined some of the other variables used in this code.

You obtain a handle to the client-area device context and set a mapping mode of MM_ANISOTROPIC with 1000 logical units horizontally and vertically:

```
hDC = BeginPaint (hWnd, &ps);

SetMapMode (hDC, MM_ANISOTROPIC);
SetWindowExt (hDC, 1000, 1000);
SetViewportExt (hDC, xClient, yClient);
```

Now you can "play the metafile" 100 times by calling PlayMetaFile, each time changing the window origin to move the metafile to a new position:

In calling *PlayMetaFile*, you're in effect repeating all the calls that you made between *CreateMetaFile* and *CloseMetaFile* when you originally created the metafile during the WM_CREATE message. The results are shown in Figure 14-3.




Figure 14-3. Multiple figures drawn using the PlayMetaFile function

When you're finished processing the WM_PAINT message, you can end it normally:

```
EndPaint (hWnd, &ps) ;
```

One task remains. When you create a metafile, the handle is really the property of the GDI module, and you must explicitly delete it with *DeleteMetaFile* before you terminate the program. You can do this during processing of the WM_DESTROY message:

```
case WM_DESTROY:
   DeleteMetaFile (hMF);
   PostQuitMessage (0);
   break;
```

Storing Metafiles on Disk

In the above example, the NULL parameter to *CreateMetaFile* meant that we wanted to create a metafile stored in memory. We can also create a metafile stored on the disk as a normal file. This method is preferred for large metafiles because it uses less memory space. Windows has to maintain a relatively small area in memory to store the name of the file containing the metafile. On the other hand, a metafile stored on disk requires a disk access every time you play it.

Let's use the example of the company logo again. In addition to the variables shown above, you'll need a variable to store the filename of the metafile:

```
static char szFileName [80] ;
```

In this example, we'll use a temporary file. During processing of the WM_CREATE message, you can create a filename for a temporary file using the Windows GetTempFileName function:

```
GetTempFileName (0, MF, 0, szFileName) ;
```

Windows first checks the TEMP variable in the MS-DOS environment to select a disk and subdirectory for this file. If there is no TEMP variable in the MS-DOS environment, Windows uses the root directory of the first fixed disk. The filename begins with a tilde (~) followed by the characters we've specified in the *GetTempFileName* function (MF) and a unique number; the extension is .TMP. On return from the call, the filename is stored in the *szFileName* array.

We create the metafile device context using this filename:

```
hMetaDC = CreateMetaFile (szFileName) ;
```

We can write to this device context just as we did in the original example and then close the metafile device context to get the metafile handle:

```
hMF = CloseMetaFile (hMetaDC) ;
```

The processing of the WM_PAINT message is the same as in the original example. However, during processing of the WM_DESTROY message, you'll have to add something. The statement:

```
DeleteMetaFile (hMF) ;
```

deletes the area of memory that references the metafile handle to the disk file but the disk file still exists. You should also delete that file using the normal C function:

```
unlink (szFileName) ;
```

Here's another way to use disk-based metafiles. This method doesn't require that you maintain hMF as a static variable. First, you get a temporary filename and create the metafile device context as before:

```
GetTempFileName (0, MF, 0, szFileName) ;
hMetaDC = CreateMetaFile (szFileName) ;
```

Now you draw on the metafile device context. When you're finished, you can close the device context and get a handle to the metafile:

```
hMF = CloseMetaFile (hMetaDC) ;
```

But now you also delete the metafile:

```
DeleteMetaFile (hMF) ;
```

Do we really want to do this? We might. Deleting a disk-based metafile invalidates the metafile handle, freeing the memory required for the metafile but leaving the disk file intact. During processing of the WM_PAINT message, you can get a metafile handle to this disk file by calling <code>GetMetaFile</code>:

```
hMF = GetMetaFile (szFileName) ;
```

Now you can play this metafile just as before. When processing of the WM_PAINT message is over, you can delete the metafile handle:

```
DeleteMetaFile (hMF) ;
```

When it comes time to process the WM_DESTROY message, you don't have to delete the metafile, because it was deleted at the end of the WM_CREATE message and at the end of each WM_PAINT message. But you still should delete the disk file:

```
unlink (szFileName) ;
```

Using Preexisting Metafiles

What we've done in the last example above seems to imply that we can create a disk-based metafile in one program and then use it in another program by calling *GetMetaFile*. We can. The MFCREATE ("metafile create") program, shown in Figure 14-4 (on the following page),

is the shortest Windows program we've written since Chapter 2. All it does is create a diskbased metafile with the name MYLOGO.WMF. The .WMF extension stands for "Windows metafile" and is the customary extension for a metafile stored as a disk file.

```
mfcreate.obj : mfcreate.c
cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp mfcreate.c
mfcreate.exe : mfcreate.obj mfcreate.def
link4 mfcreate, /align:16, /map, slibw, mfcreate
```

```
/* MFCREATE.C -- Metafile Creation Program */
#include <windows.h>
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
     HANDLE hinstance, hPrevinstance;
     LPSTR lpszCmdLine ;
     int
             nCmdShow :
     HBRUSH hBrush = CreateSolidBrush (RGB (0, 0, 255));
             hMetaDC = CreateMetaFile ("MYLOGO.WMF") ;
     Rectangle (hMetaDC, 0, 0, 100, 100) ;
     MoveTo (hMetaDC, 0, 0) ;
     LineTo (hMetaDC, 100, 100) ;
    MoveTo (hMetaDC, 0, 100);
LineTo (hMetaDC, 100, 0);
SelectObject (hMetaDC, hBrush);
Ellipse (hMetaDC, 20, 20, 80, 80);
      DeleteMetaFile (CloseMetaFile (hMetaDC)) ;
     DeleteObject (hBrush) ;
     MessageBeep (0) ;
      return FALSE ;
```

```
MFCREATEDEF
```

```
NAME MFCREATE
DESCRIPTION 'Metafile Creation Program (C) Charles Petzold, 1987'
STUB 'WINSTUB.EXE'
CODE MOVEABLE
DATA MOVEABLE MULTIPLE
HEAPSIZE 1024
STACKSIZE 4096
```

Figure 14-4. The MFCREATE program

In the WinMain function, MFCREATE creates a metafile device context using the filename MYLOGO.WMF:

```
hMetaDC = CreateMetaFile ("MYLOGO.WMF") :
```

It then draws on this device context. When it's finished, it closes the metafile device context and deletes the metafile handle in one statement:

```
DeleteMetaFile (CloseMetaFile (hMetaDC));
```

The program beeps to indicate that it's finished and then exits WinMain.

Now you can use this metafile in another program. Here's the entire WM_PAINT logic. All you need to obtain the handle to the disk-based metafile is *GetMetaFile*. When you're done with the metafile, you call *DeleteMetaFile*:

Alternatively, you can define hMF as a static variable and call GetMetaFile once during processing of WM_CREATE and call DeleteMetaFile during processing of WM_DESTROY. Of course, this approach has some problems. The code assumes that MYLOGO.WMF is in the current directory or a directory listed in the PATH environment variable. If the file isn't in the current directory when you call GetMetaFile, Windows will display a message box asking the user to insert the MYLOGO.WMF disk in drive A. (The usual response of a user to a message box of this sort is "Huh?") You should search for the file before you call GetMetaFile.

Now let's try another approach.

Using Metafiles as Resources

In Chapter 9 you encountered a "user-defined resource," which in that case was a block of text. Now let's make a metafile into a user-defined resource. MYLOGO.WMF will then become part of the .EXE file for the program that needs it. The program MFRESORC ("metafile resource"), shown in Figure 14-5 (beginning on the following page), accomplishes this using the MYLOGO.WMF metafile created by MFCREATE.

```
mfresorc.obj : mfresorc.c
    cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp mfresorc.c

mfresorc.res : mfresorc.rc mylogo.wmf
    rc -r mfresorc.rc

mfresorc.exe : mfresorc.obj mfresorc.def mfresorc.res
    link4 mfresorc, /align:16, /map, slibw, mfresorc
    rc mfresorc.res
```

```
/* MFRESORC.C -- Metafile Resource Program */
#include <windows.h>
long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG) ;
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
             hInstance, hPrevInstance;
    HANDLE
                lpszCmdLine ;
    LPSTR
                nCmdShow :
    int
    static char szAppName [] = "MFResorc" ;
    HWND
               hWnd ;
    MSG
                msa :
    WNDCLASS wndclass;
     if (!hPrevInstance)
                              = CS HREDRAW | CS VREDRAW ;
         wndclass.style
         wndclass.lpfnWndProc = WndProc ;
          wndclass.cbClsExtra = 0 ;
          wndclass.cbWndExtra
                                = 0 :
         wndclass.hInstance
                                = hInstance ;
                                = NULL ;
         wndclass.hIcon
                                = LoadCursor (NULL, IDC ARROW) ;
         wndclass.hCursor
          wndclass.hbrBackground = GetStockObject (WHITE_BRUSH) ;
          wndclass.lpszMenuName = NULL ;
          wndclass.lpszClassName = szAppName ;
          if (!RegisterClass (&wndclass))
              return FALSE ;
    hWnd = CreateWindow (szAppName, "Metafile Resource Program",
                         WS OVERLAPPEDWINDOW,
                         CW USEDEFAULT, 0,
                         CW USEDEFAULT, 0,
                         NULL, NULL, hInstance, NULL) ;
     ShowWindow (hWnd, nCmdShow) ;
     UpdateWindow (hWnd) ;
     while (GetMessage (&msg, NULL, 0, 0))
          TranslateMessage (&msg) ;
          DispatchMessage (&msg) ;
     return msg.wParam ;
```

Figure 14-5. The MFRESORC program

Figure 14-5 Continued

```
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
              hWnd ;
    HWND
    unsigned
                  iMessage ;
    WORD
                  wParam ;
    LONG
                  1Param ;
    static HANDLE hMF ;
    static short xClient, yClient;
    HANDLE
                  hInstance, hResource ;
                  hDC ;
    PAINTSTRUCT ps ;
    short
                  x, y ;
    switch (iMessage)
         case WM CREATE:
              hInstance = ((LPCREATESTRUCT) 1Param) -> hInstance :
              LockResource (hResource) ;
              hMF = SetMetaFileBits (hResource) ;
              GlobalUnlock (hResource) ;
              break ;
         case WM SIZE:
              xClient = LOWORD (1Param) ;
              yClient = HIWORD (1Param) ;
              break ;
         case WM PAINT:
              hDC = BeginPaint (hWnd, &ps) ;
              SetMapMode (hDC, MM_ANISOTROPIC) ;
              SetWindowExt (hDC, 1000, 1000);
SetViewportExt (hDC, xClient, yClient);
              for (x = 0 ; x < 10 ; x++)
                   for (y = 0 ; y < 10 ; y++)
                        SetWindowOrg (hDC, -100 * x, -100 * y) ;
                        PlayMetaFile (hDC, hMF) ;
              EndPaint (hWnd, &ps) ;
              break ;
         case WM DESTROY:
              DeleteMetaFile (hMF) ;
              PostQuitMessage (0) ;
              break :
         default:
              return DefWindowProc (hWnd, iMessage, wParam, lParam) ;
    return OL ;
```

(continued)

Figure 14-5. Continued

MyLogo METAFILE "mylogo.wmf"

```
NAME MFRESORC
DESCRIPTION 'Metafile Resource Program (C) Charles Petzold, 1987'
STUB 'WINSTUB.EXE'
CODE MOVEABLE
DATA MOVEABLE MULTIPLE
HEAPSIZE 1024
STACKSIZE 4096
EXPORTS WndProc
```

The resource script is only one line:

```
MyLogo METAFILE "mylogo.wmf"
```

METAFILE may look like a normal resource script keyword like MENU or DIALOG, but it's not. We're defining this resource type. The name we give to this particular resource of the METAFILE type is "MyLogo."

During processing of the WM_CREATE message, MFRESORC must first call *FindResource* and *LoadResource* to obtain a handle to the resource:

```
hResource = LoadResource (hInstance,
FindResource (hInstance, "MyLogo", "METAFILE"));
```

Then the resource is locked:

```
LockResource (hResource) ;
```

Normally, you would lock a resource to obtain a pointer to the memory block. However, LockResource also performs the chore of actually loading the resource into memory. That's all we need to do. Now we can convert this global memory block to a metafile using Set-MetaFileBits, and the resource can be unlocked:

```
hMF = SetMetaFileBits (hResource) ;
GlobalUnlock (hResource) ;
```

SetMetaFileBits has a companion function, GetMetaFileBits, that converts a metafile handle to a global memory handle. GetMetaFileBits can be used only with a memory metafile.

The metafile that we loaded as a resource is a memory metafile. If you'd prefer to use a disk-based metafile, you can copy it. This is the code you would use following the GlobalUnlock statement:

```
GetTempFileName (0, MF, 0, szFileName) ;
hMF2 = CopyMetaFile (hMF, szFileName) ;
DeleteMetaFile (hMF) ;
hMF = hMF2 ;
```

The hMF2 handle need not be defined as a static variable. The MFRESORC program shows the deletion of the metafile handle during processing of WM_DESTROY:

```
DeleteMetaFile (hMF) :
```

You should also delete the temporary file:

```
unlink (szFileName) :
```

The CopyMetaFile function can also be used to copy an existing metafile to a memory metafile:

```
hMF2 = CopyMetaFile (hMF, NULL) ;
```

Looking at Metafiles

You can get a good idea of what a metafile is and is not by dumping out the contents of MYLOGO.WMF. The metafile begins with an 18-byte header record. This is followed by a series of metafile records, each of which contains three or more 2-byte words. The first word is the number of words in the record, including the first; the second word is 0; the third word is a code that indicates the GDI call that the record represents.

These codes are documented in WINDOWS.H with identifiers that begin with the word META. The low byte of this word identifies the particular GDI call; the high byte is generally the number of words that are parameters to the call. The words that follow this code are the actual parameters to the call in reverse order, excluding the hDC parameter. For instance, the GDI call:

```
Rectangle (hMetaDC, 0, 0, 100, 100) ;
```

shows up in the metafile as a seven-word record. In hexadecimal, these words are:

```
0007 0000 041B 0064 0064 0000 0000
```

The 041B word means that the call is *Rectangle* with four parameters excluding the initial *hDC*. The parameters follow.

The only real exception to this rule is the SelectObject call. Windows must save the object the function is selecting into the metafile device context. For instance, the call:

```
hBrush = CreateSolidBrush (RGB (0, 0, 255));
```

doesn't affect the metafile device context at all. You can even make this call before you create the metafile device context with *CreateMetaFile*. When you select that brush into the metafile device context, however, two records must be generated. The first is a record for *CreateBrushIndirect*:

```
0007 0000 FC02 0000 0000 00FF 0000
```

The four words following the identifying code FC02 are the elements of the LOGBRUSH structure in the same order as the structure (*lbStyle* first).

The call:

```
SelectObject (hMetaDC, hBrush);
```

is coded in this record:

```
0004 0000 012D 0000
```

The single parameter of 0000 indicates that it's a handle to the first object created in the metafile. Any following *SelectObject* calls with other GDI objects will have sequentially increasing parameters.

For a memory-based metafile, these records are stored in a global memory block. For a disk-based metafile, the records are stored in a disk file. The handle to a disk-based metafile references a small global memory block that contains the drive, the directory, and the name of the file.

Metafile Dos and Don'ts

When you play the metafile, Windows breaks down the metafile into records and executes the appropriate functions using the parameters in each record. From the format of the metafile records, some facts should be fairly obvious (and some not so obvious).

The metafile device context is not a true device context. It doesn't correspond to an actual device or even to a block of memory like the memory device context. It's simply a repository for GDI calls you make using the hMetaDC device context handle.

The metafile device context doesn't have any default device context attributes. It uses whatever device context attributes are in effect when you play the metafile.

All parameters enter the metafile device context as numbers. For instance, if the width and height of your client area are stored in xClient and yClient, and you call:

```
Rectangle (hMetaDC, 0, 0, xClient / 2, yClient / 2);
```

then the actual calculated values of xClient / 2 and yClient / 2 will enter the metafile. If you later play back that metafile, it will draw a rectangle based on these calculated values regardless of the current size of the client area.

If you change the mapping mode of your screen device context before you play the metafile, the coordinates in the metafile will be interpreted based on the newly chosen mapping mode (unless the metafile itself changes the mapping mode).

The only calls that go into the metafile are those that take a handle to a device context as the first parameter. Many GDI calls are not allowed in a metafile. It's easier to say what functions *cannot* be used with a metafile device context, because they fall into several categories:

- Any function that begins with the word Get, including GetDeviceCaps and GetTextMetrics. The metafile can do nothing with the information that these functions return.
- Any other function designed to return information to the program: RectVisible, PtVisible, EnumFonts, EnumObjects, DPtoLP, and LPtoDP. The Escape function (which you'll encounter in Chapter 16) is supported only for calls that don't return data.
- Any function that treats the metafile device context as if it were an actual device context: ReleaseDC, DeleteDC, CreateCompatibleDC, CreateCompatibleBitmap, CreateDiscardableBitmap, and PlayMetaFile.
- Some of the more complex GDI functions: DrawText, GrayString, DrawIcon, and SetBrushOrg.
- · Two functions that require handles to brushes: FillRect and FrameRect.

As I indicated above, *SelectObject* works a little differently for metafile device contexts. First, it doesn't return the handle of the object previously selected in the device context. When you use *SelectObject* with a metafile device context, the function returns a nonzero if it is successful and 0 otherwise. You can't use the construction:

```
DeleteObject (SelectObject (hMetaDC, ...)); /* WRONG !!! */
```

For SelectObject, the metafile also stores a description of the logical object that you are selecting into the device context. When you play the metafile, Windows starts with the pen, brush, font, and region currently selected in the device context. For SelectObject calls, it creates the indicated object and selects it into the device context but saves the original object. When it is done playing the metafile, Windows restores the original objects and deletes all the objects it created to play the metafile.

When you play a metafile, it uses the device context attributes currently in effect. The metafile can change any of these attributes, including the mapping mode, the text color, the drawing mode, and so forth. These changes remain in effect for the device context after the metafile has finished playing. If you want to retain your original device context attributes after the metafile has finished playing, call:

```
SaveDC (hDC) ;
```

before you play the metafile and:

```
RestoreDC (hDC, -1);
```

after the *PlayMetaFile* call. The metafile itself can also save and restore the device context while it is playing. Each *SaveDC* call must be balanced by a *RestoreDC* call with a -1 parameter.

One of the purposes of metafiles is to provide a format for device-independent pictures that can be shared by applications. There are some other considerations involved with using metafiles with the clipboard that will be discussed in Chapter 17.

Stay Tuned

Although the technique of using a metafile as a user-defined resource may seem extravagant for the simple example I gave earlier, it can actually be quite powerful. In Chapter 17 we'll explore how to pass metafiles between programs, and I'll show you a program called CLIPFILE that can save the contents of the clipboard to a file. If the clipboard contains a metafile, then CLIPFILE will save it as a .WMF file. You can then use this file as a user-defined resource in one of your own programs.

This means that you can create a picture in a program such as Micrografx's Windows DRAW!, copy it to the clipboard, save it as a .WMF file using CLIPFILE, make that file a user-defined resource, and recreate the picture in your own program. If you prefer bitmaps to metafiles, this same CLIPFILE program will let you save a bitmap stored in the clipboard to a .BMP file, again allowing you to use it as a resource in your own program.

Chapter 15

Text and Fonts

Writing text to the display was one of the first jobs we tackled in programming for Windows. Now it's time to explore the use of different font sizes and learn how to justify text. This chapter is largely restricted to writing text on the video display. The subject becomes more complex when you need to write text using the printer. The printer may be capable of using a greater variety of fonts than the video display, and the characteristics of these fonts can be quite different from the characteristics of the video fonts. Therefore, the subject of text and fonts is continued in the next chapter, "Using the Printer."

SIMPLE TEXT OUTPUT

Let's begin by looking at the different functions Windows provides for text output, the device context attributes that affect text, and the use of "stock" fonts.

The Text Drawing Functions

The most common text output function is the one we've used in virtually all our sample programs:

TextOut (hDC, xStart, yStart, lpString, nCount);

The xStart and yStart parameters are the starting position of the string in logical coordinates. Normally, this is the point at which Windows begins drawing the upper left corner of the first character. TextOut requires a far pointer to the character string and the length of the string. The function knows nothing about NULL-terminated character strings.

The meaning of the xStart and yStart parameters to TextOut can be altered by the SetTextAlign function. The TA_LEFT, TA_RIGHT, and TA_CENTER flags affect the horizontal positioning of the character string. For example, if you call SetTextAlign with the TA_CENTER flag, subsequent TextOut calls position the center of the string at xStart. Similarly, the TA_TOP,

TA_BOTTOM, and TA_BASELINE flags affect the vertical positioning. If you call *SetTextAlign* with the TA_UPDATECP flag, then Windows ignores the *xStart* and *yStart* parameters to *TextOut* and instead uses the current position previously set by *MoveTo* or *LineTo*. The *TextOut* function updates the current position to the end of the string (for TA_LEFT) or the beginning of the string (for TA_RIGHT). When the horizontal positioning is TA_CENTER, the current position remains the same after a *TextOut* call.

If you draw a lot of text and are dissatisfied with the speed of *TextOut*, the *ExtTextOut* function is a more efficient alternative. With *ExtTextOut* you specify the character spacing and a clipping rectangle.

A higher-level function for writing text is *DrawText*. Rather than specifying a coordinate starting position, you provide a structure of type RECT that defines a rectangle in which you want the text to appear:

```
DrawText (hDC, lpString, nCount, &rect, wFormat);
```

DrawText also requires a far pointer to the character string and the length of the string. If you use DrawText with NULL-terminated strings, however, you can set nCount to -1, and Windows will calculate the length of the string.

When wFormat is set to 0, Windows interprets the text as a series of lines that are separated by carriage return characters (ASCII number 13) or linefeed characters (ASCII number 10). The text begins at the upper left corner of the rectangle. A carriage return or linefeed is interpreted as a "newline" character; Windows breaks the current line and starts a new one. The new line begins at the left side of the rectangle, spaced one character height (without external leading) below the previous line. Any text (including parts of letters) that would be displayed to the right or below the bottom of the rectangle is clipped.

You can change the default operation of *DrawText* by including a *wFormat* parameter, which consists of one or more flags defined in WINDOWS.H and separated by the C bitwise OR operator. The DT_LEFT flag (the default) specifies a left-justified line, DT_RIGHT specifies a right-justified line, and DT_CENTER specifies a line centered between the left and right sides of the rectangle. Because the value of DT_LEFT is 0, you needn't include the identifier if you want text to be left-justified only.

If you don't want carriage returns or linefeeds to be interpreted as newline characters, you can include the identifier DT_SINGLELINE. Windows then interprets those ASCII numbers as displayable characters rather than control characters. When using DT_SINGLELINE, you can also specify whether the line is to be placed at the top of the rectangle (DT_TOP, the default), at the bottom of the rectangle (DT_BOTTOM), or halfway between the top and bottom (DT_VCENTER). DT_TOP, like DT_LEFT, has a value of 0, so you don't need to explicitly include the flag.

When displaying multiple lines of text, Windows normally breaks the lines only at carriage returns or linefeeds. If the lines are too long to fit in the rectangle, however, you can use the DT_WORDBREAK flag, which causes Windows to make breaks at the end of words within lines. For both single-line and multiple-line displays, Windows truncates any part of the text that falls outside the rectangle. You can override this by including the flag DT_NOCLIP,

which also speeds up the operation of the function. When Windows spaces multiple lines of text, it uses the character height without external leading. If you prefer that external leading be included in the line spacing, use the flag DT_EXTERNALLEADING.

If your text contains tab characters (ASCII number 9), you need to include the flag DT_EXPANDTABS. By default, the tab stops are set at every eighth character position. You can specify a different tab setting by using the flag DT_TABSTOP, in which case the upper byte of wFormat contains the character-position number of the new tab stops. I recommend that you avoid using DT_TABSTOP, however, because the upper byte of wFormat is also used for some other flags.

Device Context Attributes for Text

Several device context attributes affect text. In the default device context, the text color is black, but you can change that:

```
SetTextColor (hDC, rgbColor) ;
```

As with pen colors and hatch brush colors, Windows converts the value of rgbColor to a pure color. You can obtain the current text color by calling GetTextColor.

The spaces between the character strokes are colored in based on the setting of the background mode and the background color. You can change the background mode using:

```
SetBkMode (hDC, nMode) ;
```

where *nMode* is either OPAQUE or TRANSPARENT. The default background mode is OPAQUE, which means that Windows uses the background color to fill in the area between the character strokes. You can change the background color by using:

```
SetBkColor (hDC, rgbColor) ;
```

The value of rgbColor is converted to a pure color. The default background color is white. If the background mode is set to TRANSPARENT, Windows ignores the background color and doesn't color the area between the character strokes. Windows also uses the background mode and background color to color the spaces between dotted and dashed lines and the area between the hatches of hatched brushes, as you saw in Chapter 13.

Many Windows programs specify WHITE_BRUSH as the brush that Windows uses to erase the background of a window. The brush is specified in the window class structure. However, you may want to make the background of your program's window consistent with the "system colors" that a user can set in the CONTROL program. In that case, you would specify the background color this way:

```
wndclass.hbrBackground = COLOR_WINDOW + 1 ;
```

When you want to write text to the client area, you can set the text color and background color using the current system colors:

```
SetTextColor (hDC, GetSysColor (COLOR_WINDOWTEXT));
SetBkColor (hDC, GetSysColor (COLOR_WINDOW));
```

If you do this, then you'll want your program to be alerted if the system colors change:

```
case WM_SYSCOLORCHANGE:
    InvalidateRect (hWnd, NULL, TRUE) ;
    break ;
```

Another device context attribute that affects text is the intercharacter spacing. By default it's set to 0, which means that Windows doesn't add any space between characters. You can insert space by using the function:

```
SetTextCharacterExtra (hDC, nExtra);
```

The *nExtra* parameter is in logical units. Windows converts it to the nearest pixel, which can be 0. If you use a negative value for *nExtra* (perhaps in an attempt to squeeze characters closer together), Windows takes the absolute value of the number: You can't make the value less than 0. You can obtain the current intercharacter spacing by calling *GetTextCharacter-Extra*. Windows converts the pixel spacing to logical units before returning the value.

Using Stock Fonts

When you call *TextOut*, *ExtTextOut*, or *DrawText* to write text, Windows uses the font currently selected in the device context. The font defines a particular typeface and a size. The easiest way to write text in a choice of fonts is to use the five stock fonts that Windows provides. You can first obtain a handle to a stock font by calling:

```
hFont = GetStockObject (nFont) ;
```

where nFont is one of the five identifiers discussed below. You can then select that font into the device context:

```
SelectObject (hDC, hFont);
```

Or you can do it in one step:

```
SelectObject (hDC, GetStockObject (nFont));
```

GetStockObject is the same function that we used in Chapter 13 to obtain stock pens and brushes; SelectObject we used in Chapters 13 and 14 to select pens, brushes, bitmaps, and regions into the device context.

The font selected in the default device context is called the system font and is identified by the GetStockObject parameter SYSTEM_FONT. This is the ANSI character set font that Windows uses for text in menus, dialog boxes, message boxes, and window caption bars. On most devices, the terminal font is similar to the system font but uses the OEM rather than the ANSI character set. You can get a handle to this font by using OEM_FIXED_FONT as the parameter to GetStockObject. (The ANSI and OEM character sets are discussed in Chapter 4.)

The identifier ANSI_FIXED_FONT gives you a handle to a Courier font that is usually smaller than the system or terminal font. "FIXED" in the identifier means that all the characters have the same fixed width. You can obtain a handle to a font with variable character widths by using the identifier ANSI_VAR_FONT. This returns a handle to a Helvetica or a Times Roman font, either of which is usually smaller than the system font.

Finally, the identifier DEVICEDEFAULT_FONT returns a handle to the font that is most suitable for the device. For most graphics-based displays, no font meets this condition, so the identifier returns a handle to either a Courier font or the system font. For a dot-matrix printer, however, this identifier returns a handle to a font that is specific to the printer and that in some cases does not require Windows to operate the printer in a graphics mode.

When you select a new font into a device context, you must calculate the font's character height and average character width using <code>GetTextMetrics</code>. If you've selected ANSI_VAR_FONT, be aware that the average character width is really an average and that some characters have a smaller or larger width. Later in this chapter you'll learn how to use <code>GetTextExtent</code> to calculate the full width of a string made up of variable-width characters.

Although GetStockObject certainly offers the easiest access to different fonts, you don't have much control over what font Windows gives you. You'll see shortly how you can be very specific about the typeface and size that you want.

Graying Character Strings

Although TextOut and DrawText are the functions used most often to write character strings, Windows has another text output function called GrayString that exists for the express purpose of displaying grayed text. Windows uses grayed text most often to show disabled items in menus and dialog boxes. However, you might also want to use some grayed text within your client area. GrayString is complex and has some limitations. I'll begin by explaining how GrayString generally works and then show you an easier way to use it. Here's the general syntax:

The name of this function must be included in the EXPORTS section of your module definition (.DEF) file. You must obtain a far pointer to the function by calling MakeProcInstance:

lpfnOutputFunction = MakeProcInstance (hInstance, OutputFunction) ;

This far pointer is the parameter to *GrayString*. The *dwData* and *nCount* parameters to *GrayString* are passed as parameters to this call-back function. Most often, *dwData* is a far pointer (converted to a doubleword) to the text you want to gray, and *nCount* is set to the number of characters.

Here's what happens when you call *GrayString*. Windows creates a memory device context and a monochrome bitmap using the *xWidth* and *yHeight* parameters to *GrayString*. It selects the bitmap into the memory device context and passes to the call-back function the memory device context handle, the *dwData* parameter, and the *nCount* parameter.

Within the call-back function, you draw on this memory device context. The text color has been set to black and the background color to white. The drawing you do is relative to the upper left corner of this memory device context rather than the upper left corner of your original device context. You return a 1 from the output function if all goes well. Windows then uses the *PatBlt* function to perform a logical OR operation on this memory device context and the 50-percent gray brush. (The ROP code is 0xFA0089.) As a result, the white pixels in the memory device context are unchanged, and half the black pixels become white pixels.

Windows then performs a *BitBlt* operation on this memory device context and the device context you specified in the *GrayString* call (probably your client-area device context), starting at the point (*xStart*, *yStart*). The ROP code is 0xB8074A, which corresponds to a logical operation of:

((Destination \ Pattern) & Source) \ Pattern

You may recall this particular ROP code from Chapter 14. The pixels in your original device context (the destination) that correspond to white pixels in the memory device context (the source) are unchanged. The pixels in your original device context that correspond to black pixels in the memory device context are colored with the brush specified in the *GrayString* call. In other words, every other pixel that you color black in the memory device context is colored with the brush in your original device context.

The GrayString function has certain limitations. Here are the most important ones.

GrayString requires the MM_TEXT mapping mode. The xWidth and yHeight parameters to GrayString are treated as device units when Windows creates the bitmap, but they are treated as logical units when PatBlt and BitBlt are called.

The memory device context has default device context attributes when Windows calls the output function. Therefore, if you've selected a different font into your device context before calling *GrayString*, this font will not be selected in the memory device context. You can, however, select a different font into the memory device context within the output function.

Normally, the *dwData* parameter points to a character string, and *nCount* is the number of characters, but *dwData* and *nCount* can really be anything you want. Be aware of the following:

- If nCount is 0, then Windows assumes that dwData is a character string and
 calculates the number of characters. That calculated value is passed to the callback function.
- If you specify an xWidth or yHeight value of 0, then Windows computes the height
 and width of the string pointed to by dwData. It uses the memory device context
 for this calculation, so these heights and widths are based on the height and width
 of the system font, regardless of the font you eventually use in the call-back
 function.
- If the output function returns 0, then Windows assumes that an error has occurred
 and doesn't draw anything on your original device context. However, if you set the
 nCount parameter to -1 and the output function returns 0, then Windows simply
 transfers the memory device context intact to your original device context without
 first graying it. In this case, you have to determine the number of characters in the
 character string yourself, within the call-back function.

If you have a good feel for bitmaps, memory device contexts, and the raster operations, you might want to sidestep these limitations by writing your own text-graying function. Or you might prefer to use the easy *GrayString* syntax presented below.

The Easy Use of GrayString

In the general syntax to *GrayString*, the parameter called *lpfnOutputFunction* is a long pointer to a call-back function. If you set that parameter to NULL, Windows uses the *TextOut* function. You can also set the *nWidth* and *nHeight* parameters to 0. Here's the syntax you'll want to use for writing grayed text to the display:

```
GrayString (hDC, GetStockObject (BLACK_BRUSH), NULL, (DWORD) lpString, nCount, xStart, yStart, 0, 0);
```

If *IpString* is a pointer to a NULL-terminated text string, then *nCount* can also be set to 0, and Windows will calculate the length. *GrayString* uses the system font regardless of the font currently selected in the device context. The function ignores the device context settings for the text color, background mode, and background color, and it requires the MM_TEXT mapping mode.

Do you find it strange that we're specifying a black brush when we want to gray the text? With a little explanation, the reason becomes obvious. Windows uses *TextOut* to write to the memory device context. It grays this text by using *PatBlt* with GRAY_BRUSH and then

uses the brush specified in the *GrayString* call to color the pixels that are left. If you specified GRAY_BRUSH in the *GrayString* call, then the text would be grayed if either *xStart* or *yStart* (but not both) were an odd number. If both coordinates were odd or if both were even, then the text would not appear at all, because the two gray brushes would cancel each other out.

On color displays, you can also pass to *GrayString* a brush handle from *CreateSolidBrush*, if you've created a brush of a pure color. On monochrome displays, however, this brush would become a black-and-white dithered brush, and you would encounter the same problems as with a gray brush.

BACKGROUND ON FONTS

Much of the remainder of this chapter concerns working with different fonts. Before you get involved with specific code, however, you'll benefit from having a firm grasp of the subject's basics.

The Types of Fonts

Windows supports two broad categories of fonts, called "GDI-based fonts" and "device-based fonts."

The GDI-based fonts are stored in files with the extension .FON. These files are sometimes called "font resource files," and they are normally kept in the same subdirectory as the other Windows libraries. Each file contains one or more complete fonts. These files are in New Executable format, which you can verify by running EXEHDR on them. They are library modules, although somewhat unusual ones in that they contain no code or data. All they contain are two types of resources: a font directory and the fonts themselves.

Device-based fonts are internal to the graphics output device. For video display adapters, device-based fonts are currently rare. Windows uses the video adapter in graphics mode, so it must use the GDI-based fonts and write the pixels to the video display.

For printers, however, device-based fonts are common. For instance, Windows can write text to a dot-matrix printer using either the printer's normal text mode or the printer's graphics mode. With the text mode, Windows uses a device-based font and needs to send only the ASCII numbers of the characters out to the printer. With the graphics mode, Windows uses a GDI-based font and must send the pixel patterns to the printer. For laser printers, device-based fonts can be stored in ROM within the printer or in ROM cartridges. If the printer requires a downloadable font that originates from a disk file, this font is also classified as a device-based font, because it is specific to the particular device.

GDI-based fonts come in two flavors—"raster," or bitmap, fonts (the more common variety) and "vector," or stroke, fonts. In a raster font file, each character is stored as a bitmap pixel pattern. Figure 15-1 shows a character from a GDI-based raster font, blown up so that you can see the individual pixels.




Figure 15-1. A GDI-based raster font character

Each raster font is designed for a specific aspect ratio and character size. Windows can create larger character sizes from GDI-based raster fonts by simply duplicating rows or columns of pixels. However, this can be done only in integral multiples and within certain limits. At most, Windows can increase the height of a GDI-based raster font by 8 times the height of the pixel bitmap, and it can increase the width of a font by a factor of 5. But this maximum increase isn't guaranteed for every GDI-based raster font on every device. Right away, you can probably perceive one major difference between drawing graphics on the display and writing text to the display using the GDI-based raster fonts. Although you can draw a rectangle of virtually any size, GDI-based raster fonts are available only in discrete sizes. You can't write text using a font smaller than the smallest font. If you want a GDI-based raster font of a specific size, that size may not be available.

The GDI-based vector fonts partly solve this problem. The vector fonts are defined as a series of line segments in a "connect-the-dots" format. Vector fonts are continuously scalable, which means that the same font can be used for all aspect ratios and can be increased or decreased to any size. In general, GDI-based raster fonts look better than vector fonts at small sizes because the raster font was designed based on that particular size. At very large sizes, however, the raster fonts look grainy—as you can see in Figure 15-1—because Windows has to start doubling rows or columns of pixels. Thus the vector fonts are usually preferable for large sizes, although the characters look somewhat weak because their strokes are single lines. Figure 15-2 shows a character from a blown-up GDI-based vector font.




Figure 15-2. A GDI-based vector font character

Neither the raster approach nor the vector approach is the best way to define fonts. The optimum method involves filled outlines based on polynomial equations, in which the formulas are set such that the fonts can be scaled for any aspect ratio or size. However, this approach involves an amount of computation that is currently prohibitive on personal computers (although some laser printers use this approach internally to generate fonts).

For both GDI-based raster fonts and vector fonts, Windows can "synthesize" boldface, italics, underlining, and strikethrough without storing separate fonts for each attribute. For italics, for instance, Windows simply shifts the upper part of the character to the right. Because device-based fonts are stored and used in a device-specific manner, it is impossible to discuss them in the same detail as GDI-based fonts. Sometimes the device can italicize or boldface a device-based font, and sometimes it can't. You can obtain such information from the GetDeviceCaps function using the TEXTCAPS index. If you want to obtain this information for particular printers, you can use the DEVCAPS program in Chapter 12 or 16.

Type Talk I: Families and Faces

I've been using the word *font* rather loosely until now. The more rigorous definition of *font* that is preferred by typographers is this: A font is a complete collection of characters of a particular typeface and a particular size.

To a typographer, the term *typeface* denotes not only the style of type (such as Courier or Helvetica) but also whether the characters are oblique or italic or boldface, for example. When working with Windows, we'll use the word *typeface* to denote simply the style of the type. Common typefaces, in addition to Courier and Helvetica, are Times Roman, Gothic, and Palatino.

Windows groups typefaces into five "families," based on the general appearance of the type. These families are called Modern, Swiss, Roman, Script, and Decorative. The most common typefaces are categorized as Modern, Swiss, or Roman, depending on two characteristics. The first characteristic involves "stroke width"—the width of the lines that make up the characters—which can be constant or variable. Typefaces in the Modern family have constant stroke widths. Typefaces in the Swiss and Roman families have variable stroke widths. (Most typefaces with constant stroke widths are also of "fixed pitch," which means that all the characters in the font are the same width. Typefaces with variable stroke widths are generally of "variable pitch," which means that the characters have variable widths. However, it is the stroke width rather than the use of fixed or variable pitch that determines the family of a particular typeface.) The second characteristic involves "serifs," which are small lines that finish off the character strokes. The Swiss family comprises "sans-serif" typefaces (typefaces with no serifs); the Roman family comprises serif typefaces.

The Script family comprises typefaces that resemble script handwriting. The Decorative family includes typefaces that comprise "symbols" (sometimes also called "ornaments" or "dingbats") and can also contain typefaces of elaborate design such as Old English.

The table below summarizes the grouping of typefaces into families and shows the	
identifiers (defined in WINDOWS.H) that programs can use to specify the font family:	

Font Family	Stroke	Usual Pitch	Serifs	Typical Typefaces
FF_MODERN	Fixed	Fixed	_	Courier, Elite, Pica
FF_SWISS	Variable	Variable	No	Helvetica, Avant Garde
FF_ROMAN	Variable	Variable	Yes	Times Roman, Palatino, New Century Schoolbook
FF_SCRIPT	_			Cursive, Zapf Chancery
FF_DECORATIVE	-		-	Old English, Symbol, Zapf Dingbats

WINDOWS.H also includes a sixth font-family identifier, FF_DONTCARE, which a program can use when it wants to create a font but doesn't care what family it comes from.

The typeface names shown in this table are the common names by which these typefaces are known, but when a Windows program specifies a typeface, in most cases it uses an abbreviation (such as "Helv" for Helvetica and "Tms Rmn" for Times Roman) rather than the full name. As you'll see, Windows provides functions for programs to determine the names of the typefaces available on a particular device. These functions become particularly important when the device is a printer, because printers can include many device-based fonts with names that can be determined only when the program interrogates the device. Typefaces available for the video display are shown in Figure 15-3.

Courier Modern Helv Tms Rmn Roman boupt

Figure 15-3. Windows typefaces for the video display

The Font Resource Files

Your Windows subdirectory contains several files with the extension .FON. Some of the filenames begin with the letters COUR (Courier), HELV (Helvetica), or TMSR (Times Roman) followed by another letter: A, B, C, D, or E; these are the font resource files containing the GDIbased raster fonts. Each font resource file contains one or more sizes of a particular typeface. The terminating letter indicates the resolution and aspect ratio for which the font was designed. The GDI-based vector fonts are stored in the MODERN.FON, ROMAN.FON, and SCRIPT.FON files. Because the GDI-based vector fonts are continuously scalable, they aren't based on a particular aspect ratio or device resolution.

The table below lists the GDI-based font resource files, the font-family identifiers, the typefaces, and the character set:

Filename	Type	Family	Typeface	Character Set
FONTS.FON	Raster	FF_DONTCARE	System	ANSI
OEMFONTS.FON	Raster	FF_MODERN	Terminal	OEM
COURX.FON	Raster	FF_MODERN	Courier	ANSI
HELVx.FON	Raster	FF_SWISS	Helv	ANSI
TMSRx.FON	Raster	FF_ROMAN	Tms Rmn	ANSI
MODERN.FON	Vector	FF_MODERN	Modern	OEM
ROMAN.FON	Vector	FF_ROMAN	Roman	OEM
SCRIPT.FON	Vector	FF_SCRIPT	Script	OEM

The FONTS.FON and OEMFONTS.FON files are needed only in the "slow boot" version of Windows. In a normally installed version of Windows, the system and terminal fonts are merged into WIN200.BIN.

The GDI-based vector font files are sometimes referred to as "Set #1." There are five other sets corresponding to the terminating letter of the COURX.FON, HELVX.FON, and TMSRx FON filenames:

			Pixels per Logical Inch		er Logical Inch	
Set	Letter	Aspect Ratio	X (Horz)	Y (Vert)	Device	
#2	A	200	96	48	CGA	
#3	В	133	96	72	EGA	
#4	C	83	60	72	Okidata printers	
#5	D	167	120	72	IBM, Epson printers	
#6	E	100	96	96	VGA	

The aspect ratio is calculated as:

You might recall encountering this peculiar "logical inch" measurement in Chapter 12, when we explored the information available from *GetDeviceCaps* with the LOGPIXELSX and LOGPIXELSY parameters. We quickly established that a logical inch is different from a real inch.

For an EGA, GetDeviceCaps reports that the device has 96 pixels horizontally per logical inch and 72 pixels vertically per logical inch. This means that the raster fonts stored in the COURB.FON, HELVB.FON, and TMSRB.FON files are appropriate for display on an EGA. The fonts in the Set #2 files are too short for the EGA because they are based on a lower vertical resolution, and the fonts in Set #4 are too wide because they are based on a lower horizontal resolution.

Type Talk II: Getting the Point

Type size is expressed in units called "points." A point is very close to $\frac{1}{72}$ in., so close that it's often defined as exactly $\frac{1}{72}$ in. The point size indicates the height of the characters. For instance, when we speak of 12-point type, we're referring to characters that are $\frac{12}{72}$ ($\frac{1}{6}$) in. high from the top of the ascenders to the bottom of the descenders.

In Windows, another convenient measurement is the "twip"; this fabricated word stands for "twentienth of a point," which equals 1/1440 in. Note that the pixels-per-logical-inch measurements associated with each of the four sets of GDI-based raster fonts are such that the size of each pixel is an integral number of twips. Or rather, each pixel is an integral number of "logical twips":

Pixels per Logical Inch	Logical Twips per Pixel	
48	30	
60	24	
60 72	20	
96	15	
120	12	

If you run the EXEHDR utility on the COURX.FON, HELVX.FON, and TMSRX.FON font resource files, you'll see in the module description that the files contain fonts of particular point sizes. The COURX.FON files comprise 8-point, 10-point, and 12-point fonts. The HELVX.FON and TMSRX.FON files include those sizes and add 14-point, 18-point, and 24-point fonts. But here's the catch: These point sizes are dependent on the resolution given by the number of pixels per logical inch. For instance, the 24-point Times Roman font in the TMSRB.FON file has characters that are 24 pixels high. Only on a display that has 72 pixels per vertical inch will the 24 pixels correspond to a 24-point font.

Why Logical Inches?

The fact remains that the EGA actually displays 68 pixels per horizontal inch and 51 pixels per vertical inch. The logical inch is some 40 percent larger than the real inch. Why not simply base the fonts on the real dimensions of the EGA display and forget about this logical-inch business?

On paper, 8-point type with about 14 characters per horizontal inch is perfectly readable. If you were programming a word-processing or page-composition application for Windows, you would want to be able to show legible 8-point type on the display. But if you used the actual dimensions of the video display, each character would be about 6 pixels high and 5 pixels wide. Such characters would not be legible. Even if the display had sufficient resolution, you might still have problems reading actual 8-point type on a screen. When people read print on paper, the distance between the eyes and the paper is generally about a foot, but a video display is commonly viewed from a distance of 2 feet. The logical inch in effect provides a magnification of the screen, allowing the display of legible fonts in a size as small as 8-point. You can see this magnification effect in Windows WRITE when you display the ruler at the top of the client area.

Note also that having 96 pixels per logical inch horizontally makes the 640-pixel-wide display of the CGA and EGA equal to about 6.5 logical inches. This is precisely the width of text that you'll print on 8.5-in.-wide paper when you use the standard margins of an inch on each side. So the logical inch also takes advantage of the width of the screen to allow text to be displayed as large as possible.

This whole subject of logical inches is relevant only for the video display. For printers, a logical inch is the same as a real inch.

Type Talk III: Leading and Spacing

When we first started writing text to the display way back in Chapter 3, we obtained information from *GetTextMetrics* that allowed us to space the text properly. The six values from the TEXTMETRIC structure that describe the size of a character were shown in a diagram (Figure 3-3). Five of those values concern a character's height, as shown in Figure 15-4.




Figure 15-4. The five values defining character height

The word *leading* (pronounced "ledding") is derived from the lead that typesetters insert between blocks of metal type to add white space between lines of text. The *tmInternalLeading* value is the space for diacritics. (For some system and terminal fonts, *tmInternalLeading* is 0, and characters with diacritics are simply reduced in size to make room for the diacritics.) The *tmExternalLeading* "suggests" an additional space to leave between lines of characters. Programmers can use or ignore the external leading value. The

Courier, Helvetica, and Times Roman fonts have *tmExternalLeading* values of 0 and have positive *tmInternalLeading* values (except in the very smallest sizes) to more closely approximate how fonts are used in printed material.

When we refer to a font as being 8-point or 12-point, we're actually talking about the height of the font less the internal leading. The diacritics on certain capitals are considered to occupy the space that normally separates lines of type. The *tmHeight* value refers to the line spacing. In the case of the 24-point Times Roman font for the EGA (which conveniently has 72 pixels per logical inch vertically, or 1 pixel per logical point), the *tmHeight* value is 26 and the *tmInternalLeading* is 2. The line spacing is 28 points. The size of the font is 26 minus 2, or 24 points. We speak of this as a 24-point font on a 26-point line spacing, which is often abbreviated as 24/26. The 10-point Courier, Helvetica, and Times Roman fonts designed for the EGA all have a *tmHeight* value of 12 and a *tmInternalLeading* value of 2. The line spacing is 12 points, or ½ of a logical inch, which is the normal line spacing of a printer or typewriter.

The "Logical Twips" Mapping Mode

When we discussed mapping modes in Chapter 12, you might have thought the MM_TWIPS mapping mode would be used by programs that make heavy use of formatted text. In this mapping mode, logical units are in terms of a twentieth of a point. However, you probably won't want to use MM_TWIPS for the video display, because the mapping mode is based on real inches rather than logical inches. As a result, your program won't be able to equate the correct point sizes (8, 10, 12, 14, 18, and 24) of the available screen fonts to their heights in MM_TWIPS units.

You'll be better off if you define your mapping mode based on the logical-pixels-perinch dimensions available from *GetDeviceCaps*. I call this the "Logical Twips" mapping mode; here's all you need to set it:

```
SetMapMode (hDC, MM_ANISOTROPIC);
SetWindowExt (hDC, 1440, 1440);
SetViewportExt (hDC, GetDeviceCaps (hDC, LOGPIXELSX),
GetDeviceCaps (hDC, LOGPIXELSY));
```

Because the pixels-per-logical-inch values are always divisors of 1440, the scaling factor for this mapping mode is an integer. With this mapping mode set, if you want to request a font with 12-point line spacing (as we'll do shortly), you can specify the height of the font as 240 (12 times 20) logical units.

If you select a font into your device context and call GetTextMetrics to obtain the dimensions of the font, you can calculate the type size in points by using the formula:

```
(tm.tmHeight - tm.tmInternalLeading) / 20
```

The line spacing in points is equal to:

```
tm.tmHeight / 20
```

For some smaller fonts on low-resolution devices, the size and spacing of the type might actually involve a fraction of a point—for example, 8-point type with 8.5-point line spacing. To round to the nearest integral point size, you might instead want to use the formulas:

(tm.tmHeight - tm.tmInternalLeading + 10) / 20

and:

(tm.tm Height + 10) / 20

We'll use the "Logical Twips" mapping mode in the JUSTIFY program toward the end of this chapter.

Once again, remember that the discrepancy between logical inches and real inches occurs only for the display. If you use the "Logical Twips" mapping mode with a printer, you'll simply duplicate the MM_TWIPS mapping mode.

CREATING, SELECTING, AND DELETING LOGICAL FONTS

Now that we've nailed down the concept of logical inches, it's time to talk about logical fonts. The logical font is the fifth and final type of GDI object. The first four, covered in Chapters 13 and 14, are pens, brushes, bitmaps, and regions.

A logical font is the description of a font. Like the logical pen and logical brush, it is an abstract item that becomes real only when it is selected into a device context. For logical pens (for instance), you can specify any color you want for the pen, but Windows converts that to a pure color when you select the pen into the device context. Only then does Windows know about the color capabilities of the device.

With fonts, this distinction between the logical font that you request and the real font that you get is much more important, because the logical font and the real font can be very different. For example, suppose you request a 32-point Zapf Chancery font. Windows returns your program a handle to a logical font. Now you select that font into a device context. What happens? It depends. If the device context is a printer device context for an Apple LaserWriter Plus, you will indeed be able to write text to the printer using a 32-point Zapf Chancery font. But if you select this logical font into your screen device context, you'll get something that only approximates this font.

This is the process for creating, selecting, and deleting logical fonts:

- Create a logical font by calling CreateFont or CreateFontIndirect. These functions return a handle to a font of type HFONT.
- Select the logical font into the device context using SelectObject. Windows chooses a real font that matches most closely the logical font.

- Determine the size and the characteristics of the real font with GetTextMetrics.
 (You can also get the name of the font with GetTextFace.) The information lets you properly space the text that you write when this font is selected into the device context.
- Delete the logical font by calling DeleteObject. Don't delete the font while it is selected in a valid device context, however, and never delete stock fonts.

Windows has two functions for creating logical fonts. The first is:

```
hFont = CreateFont (nHeight ... lpszFaceName) ;
```

The *CreateFont* function has more parameters than any other Windows function—14 of them. The 14 parameters to *CreateFont* correspond directly to the 14 fields of the LOGFONT structure. You can also create a logical font using this structure:

```
LOGFONT logfont;

| lother program lines|
hFont = CreateFontIndirect (&logfont);
```

In most cases, using CreateFontIndirect and the logical font structure is neater and more efficient than specifying the 14 parameters to CreateFont.

After you create a logical font, you select it into your device context with SelectObject:

```
hFontOld = SelectObject (hDC, hFont) ;
```

Windows then matches the logical font with a real font. You can determine the name of the typeface by using the function:

```
GetTextFace (hDC, sizeof lpFaceName, lpFaceName) ;
```

where *lpFaceName* is a character array to receive the name. You can have Windows copy the various sizes of the font into a structure of type TEXTMETRIC using the familiar:

```
GetTextMetrics (hDC, &tm) ;
```

The GetObject function, which you can use to obtain information about a logical pen, brush, or bitmap, can also be used for logical fonts:

```
GetObject (hFont, sizeof (LOGFONT), &logfont);
```

But this function returns only the information that you put into *logfont* to create the font in the first place.

You can delete a logical font (but not while it is selected in a device context) with DeleteObject:

```
DeleteObject (hFont) ;
```

The PICKFONT Program

With the PICKFONT program, shown in Figure 15-5, you can create a logical font and see the characteristics of the real font after the logical font is selected into the screen device context.

```
/* PICKFONT.C -- Font Picker Program */
#include <windows.h>
#include "pickfont.h"
long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG) ; BOOL FAR PASCAL DlgProc (HWND, unsigned, WORD, LONG) ;
          szAppName [] = "PickFont" ;
DWORD
          dwAspectMatch = OL ;
          hDlg ;
HWND
LOGFONT 1f ;
short nMapMode = IDD TEXT ;
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
      HANDLE hInstance, hPrevInstance;
                  lpszCmdLine ;
       LPSTR
       int
                 nCmdShow ;
      HWND
                  hWnd :
               msg ;
       WNDCLASS wndclass ;
       if (!hPrevInstance)
                                    = CS HREDRAW | CS_VREDRAW;
             wndclass.style
             wndclass.tyfe - Co_nkbJAN | Co_vkBJAN |
wndclass.lpfnWndProc = WndProc ;
wndclass.cbClsExtra = 0 ;
wndclass.cbWndExtra = 0 ;
wndclass.hInstance = hInstance ;
wndclass.hIcon = LoadIcon (NULL, IDI APPLICATION) ;
wndclass.hCursor = LoadCursor (NULL, IDC ARROW) ;
             wndclass.hbrBackground = GetStockObject (WHITE_BRUSH) ;
wndclass.lpszMenuName = NULL ;
             wndclass.lpszClassName = szAppName ;
              if (!RegisterClass (&wndclass))
                    return FALSE ;
       hWnd = CreateWindow (szAppName, "Font Picker",
                                  WS OVERLAPPEDWINDOW | WS CLIPCHILDREN,
                                  CW USEDEFAULT, 0,
```

Figure 15-5. The PICKFONT program

(continued)

Figure 15-5. Continued

```
CW USEDEFAULT, 0,
                          NULL, NULL, hInstance, NULL) ;
     ShowWindow (hWnd, nCmdShow) ;
     UpdateWindow (hWnd) ;
     while (GetMessage (&msg, NULL, 0, 0))
          if (hDlg == 0 || !IsDialogMessage (hDlg, &msg))
                TranslateMessage (&msg) ;
                DispatchMessage (&msg) ;
     return msg.wParam ;
void MySetMapMode (hDC)
     HDC hDC ;
     if (nMapMode == IDD LTWPS)
          SetMapMode (hDC, MM_ANISOTROPIC) ;
          SetWindowExt (hDC, T440, 1440);
SetViewportExt (hDC, GetDeviceCaps (hDC, LOGPIXELSX),
                                 GetDeviceCaps (hDC, LOGPIXELSY)) ;
     else
          SetMapMode (hDC, MM_TEXT + nMapMode - IDD_TEXT) ;
void ShowMetrics (hDlg)
     HWND hDlg ;
     static TEXTMETRIC tm ;
     static struct
          short nDlqID ;
          short *pData ;
          shorts [] =
          TM HEIGHT,
                          &tm.tmHeight,
          TM_ASCENT,
TM_DESCENT,
                          &tm.tmAscent,
                          &tm.tmDescent,
          TM INTLEAD,
                          &tm.tmInternalLeading,
          TM EXTLEAD,
                          &tm.tmExternalLeading,
          TM_AVEWIDTH,
                          &tm.tmAveCharWidth,
          TM MAXWIDTH,
                          &tm.tmMaxCharWidth,
          TM WEIGHT,
                          &tm.tmWeight,
          TM OVER,
                          &tm.tmoverhang,
          TM DIGX,
                          &tm.tmDigitizedAspectX,
          TM DIGY,
                          &tm.tmDigitizedAspectY
                                                                 "Swiss",
     static char
                     *szFamily [] = { "Don't Care", "Roman",
                                       "Modern",
                                                      "Script", "Decorative" ) ;
     BOOL
                     bTrans ;
     char
                     szFaceName [LF FACESIZE] ;
     HDC
                     hDC ;
```

(continued)

Figure 15-5. Continued

```
HFONT
                      hFont ;
     short
                      1 ;
                      = GetDlgItemInt (hDlg, IDD_HEIGHT, &bTrans, TRUE) ;
     lf.lfHeight
                    = GetDlgItemInt (hDlg, IDD WIDTH, &bTrans, FALSE) ;
= GetDlgItemInt (hDlg, IDD WEIGHT, &bTrans, FALSE) ;
     lf.lfWidth
     lf.lfWeight
                    = (BYTE) (IsDlgButtonChecked (hDlg, IDD_ITALIC) ? 1 : 0) ;
     lf.lfItalic
     lf.lfUnderline = (BYTE) (IsDlgButtonChecked (hDlg, IDD_UNDER) ? 1 : 0) ;
     lf.lfStrikeOut = (BYTE) (IsDlqButtonChecked (hDlq, IDD STRIKE) ? 1:0);
     GetDlgItemText (hDlg, IDD FACE, lf.lfFaceName, LF FACESIZE) ;
     dwAspectMatch = IsDlqButtonChecked (hDlq, IDD ASPECT) ? 1L : 0L ;
     hDC = GetDC (hDlg)
     MySetMapMode (hDC)
     SetMapperFlags (hDC, dwAspectMatch) ;
     hFont = SelectObject (hDC, CreateFontIndirect (&lf)) ;
     GetTextMetrics (hDC, &tm) ;
     GetTextFace (hDC, sizeof szFaceName, szFaceName) ;
     DeleteObject (SelectObject (hDC, hFont)) ;
     ReleaseDC (hDlg, hDC) ;
     for (i = 0 ; i < sizeof shorts / sizeof shorts [0] ; i++)
           SetDlqItemInt (hDlq, shorts[i].nDlqID, *shorts[i].pData, TRUE) ;
     SetDlgItemText (hDlg, TM PITCH, tm.tmPitchAndFamily & 1 ?
                                                             "VARIABLE": "FIXED") ;
     SetDlgItemText (hDlg, TM FAMILY, szFamily [tm.tmPitchAndFamily >> 4]) ;
     SetDlgItemText (hDlg, TM CHARSET, tm.tmCharSet ? "OEM" : "ANSI") ;
     SetDlgItemText (hDlg, TF_NAME, szFaceName) ;
BOOL FAR PASCAL DigProc (hDlg, iMessage, wParam, 1Param)
              hDlg ;
     HWND
     unsigned iMessage ;
     WORD
               wParam ;
     LONG
               1Param :
     switch (iMessage)
           case WM INITDIALOG:
                 CheckRadioButton (hDlg, IDD_TEXT, IDD_LTWPS, IDD_TEXT) ;
                CheckRadioButton (hDlg, IDD ANSI, IDD OEM, IDD ANSI);
CheckRadioButton (hDlg, IDD QDRAFT, IDD QPROOF, IDD QDRAFT);
CheckRadioButton (hDlg, IDD PDEF, IDD PVAR, IDD PDEF);
CheckRadioButton (hDlg, IDD DONT, IDD DEC, IDD DONT);
                 lf.lfEscapement
                                      = 0;
                 lf.lfOrientation = 0;
lf.lfOutPrecision = OUT DEFAULT PRECIS;
                 1f.lfClipPrecision = CLIP DEFAULT PRECIS ;
                 ShowMetrics (hDlg) ;
                                             /* fall through */
           case WM SETFOCUS:
                 SetFocus (GetDlgItem (hDlg, IDD_HEIGHT)) ;
                 return FALSE ;
```

Figure 15-5. Continued

```
case WM COMMAND:
     switch (wParam)
           case IDD TEXT:
           case IDD LOMET:
case IDD HIMET:
           case IDD LOENG:
           case IDD HIENG:
           case IDD TWIPS:
case IDD LTWPS:
                CheckRadioButton (hDlg, IDD_TEXT, IDD_LTWPS, wParam) ;
                nMapMode = wParam ;
                break ;
           case IDD ASPECT:
           case IDD ITALIC:
           case IDD UNDER:
           case IDD STRIKE:
                CheckDlgButton (hDlg, wParam,
                      IsDlgButtonChecked (hDlg, wParam) ? 0 : 1) ;
                break ;
           case IDD ANSI:
           case IDD OEM:
                CheckRadioButton (hDlg, IDD_ANSI, IDD_OEM, wParam);
lf.lfCharSet = (BYTE) (wParam == IDD_ANSI ? 0 : 255);
                break ;
           case IDD QDRAFT:
           case IDD QDEF:
case IDD QPROOF:
                CheckRadioButton (hDlg, IDD QDRAFT, IDD QPROOF,
                                                                   wParam) ;
                lf.lfQuality = (BYTE) (wParam - IDD QDRAFT) ;
                break ;
           case IDD PDEF:
           case IDD PFIXED:
           case IDD PVAR:
                CheckRadioButton (hDlg, IDD PDEF, IDD PVAR, wParam) ;
                lf.lfPitchAndFamily &= 0xF0 ;
                lf.lfPitchAndFamily |= (BYTE) (wParam - IDD PDEF) ;
                break ;
           case IDD DONT:
           case IDD ROMAN:
           case IDD SWISS:
           case IDD MODERN:
           case IDD SCRIPT:
           case IDD DEC:
                CheckRadioButton (hDlg, IDD_DONT, IDD_DEC, wParam) ;
                lf.lfPitchAndFamily &= 0x0F ;
                lf.lfPitchAndFamily |= (BYTE) (wParam-IDD_DONT << 4) ;
                break ;
           case IDD OK:
                ShowMetrics (hDlg)
                InvalidateRect (GetParent (hDlg), NULL, TRUE) ;
                break ;
     break ;
```

Figure 15-5. Continued

```
default:
              return FALSE ;
     return TRUE ;
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
     HWND
                 hWnd;
     unsigned
                 iMessage;
     WORD
                  wParam:
     LONG
                 1Param;
     static char szText [] =
                      "AaBbCcDdEeFfGgHhIiJjKkLlMmNnOoPgQqRrSsTtUuVvWwXxYyZz";
     static short xClient, yClient;
     HANDLE
                 hInstance ;
     HDC
                 hDC ;
    HFONT
                 hFont ;
     FARPROC
                 lpfnDlqProc ;
     PAINTSTRUCT ps ;
     RECT
                 rect ;
     switch (iMessage)
          case WM CREATE :
               hInstance = ((LPCREATESTRUCT) lParam) ->hInstance ;
               lpfnDlgProc = MakeProcInstance (DlgProc, hInstance) ;
               hDlg = CreateDialog (hInstance, szAppName, hWnd, lpfnDlgProc) ;
               break ;
          case WM SETFOCUS:
               SetFocus (hDlg) ;
               break ;
          case WM PAINT:
               hDC = BeginPaint (hWnd, &ps) ;
               MySetMapMode (hDC) ;
               SetMapperFlags (hDC, dwAspectMatch) ;
               GetClientRect (hDlg, &rect) ;
               rect.bottom += 1 ;
               DPtoLP (hDC, (LPPOINT) &rect, 2) ;
               hFont = SelectObject (hDC, CreateFontIndirect (&lf)) ;
               TextOut (hDC, rect.left, rect.bottom, szText, 52) ;
               DeleteObject (SelectObject (hDC, hFont)) ;
               EndPaint (hWnd, &ps) ;
               break ;
          case WM DESTROY:
               PostQuitMessage (0) ;
               break ;
          default :
               return DefWindowProc (hWnd, iMessage, wParam, 1Param) ;
     return OL ;
```

(continued)

Figure 15-5. Continued

```
#define IDD OK
#define IDD_HEIGHT 10
#define IDD_WIDTH 11
#define IDD WEIGHT
                                             12
#define IDD_ITALIC 13
#define IDD_UNDER 14
#define IDD_STRIKE 15
#define IDD ASPECT 16
#define IDD_TEXT 17
#define IDD_LOMET 18
#define IDD_HIMET 19
#define IDD_LOENG 20
 #define IDD HIENG
                                            21
#define IDD TWIPS 22
#define IDD LTWPS 23
#define IDD ANSI 24
#define IDD OEM
#define IDD_QDRAFT 26
#define IDD_QDEF 27
#define IDD_QPROOF 28
#define IDD_PDEF 29
 #define IDD_PFIXED 30
#define IDD PFIXED 30
#define IDD PVAR 31
#define IDD DONT 32
#define IDD ROMAN 33
#define IDD SWISS 34
#define IDD MODERN 35
#define IDD SCRIPT 36
#define IDD DEC 37
#define IDD FACE 38
#define TM HEIGHT 39
#define TM ASCENT 40
#define TM DESCENT 41
#define TM INTLEAD 42
 #define TM EXTLEAD
                                               43
#define TM_AVEWIDTH 44
#define TM_MAXWIDTH 45
 #define TM_WEIGHT
                                               46
 #define TM_PITCH
                                               47
#define TM FIRCH 47
#define TM FAMILY 48
#define TM CHARSET 49
#define TM OVER 50
#define TM DIGX 51
#define TM DIGY 52
#define TF NAME 53
```

```
#include <style.h>
#include "pickfont.h"

#define GT (WS_GROUP | WS_TABSTOP)
#define GR (WS_GROUP)
#define TA (WS_TABSTOP)

PickFont DIALOG 0, 0, 320, 170

STYLE WS_CHILD | WS_BORDER | WS_VISIBLE | DS_ABSALIGN
BEGIN
```

(continued)

Figure 15-5. Continued

LTEXT	"&Height"	-1,	6,	8,	30,	8	
EDITTEXT	- Marian III	IDD_HEIGHT,	36,	6,	30,	12	
LTEXT	"&Width"	-1,	6,	24,	30,	8	
EDITTEXT	ACTUAL CONTRACTOR	IDD_WIDTH,	36,	22,	30,	12	
LTEXT	"Weigh&t"	-1,	6,	40,	30,	8	
EDITTEXT		IDD_WEIGHT,	36,	38,	30,	12	
GROUPBOX	"&Mapping Mode"	-1,	70,	2,	116,	60	
RADIOBUTTON	"Text"	IDD TEXT,	74,	12,	50,	12,	GT
RADIOBUTTON	"Lo Metric"	IDD LOMET,	74,	24,	50,	12	
RADIOBUTTON	"Hi Metric"	IDD HIMET,	74,	36,	50,	12	
RADIOBUTTON	"Lo English"	IDD LOENG,	130,	12,	54,	12	
RADIOBUTTON	"Hi English"	IDD HIENG,	130,	24,	52,	12	
RADIOBUTTON	"Twips"	IDD TWIPS,	130,	36,	52,	12	
RADIOBUTTON	"'Logical Twips'",	IDD LTWPS,	74,	48,	80,	12	
CHECKBOX	"Match &Aspect"	IDD ASPECT.	6,	52,	60,	12,	GT
CHECKBOX	"&Italic"	IDD ITALIC,	6,	64,	60,	12,	
CHECKBOX	"&Underline"	IDD UNDER,	6,	76,	60,	12,	
CHECKBOX	"&Strike-Out"	IDD STRIKE,	6,	88,	60,	12,	
GROUPBOX	"&Char Set"	-1,	70,	66,	52,	36,	
RADIOBUTTON	"ANSI"	IDD ANSI,	74,	76,	28,	12,	
RADIOBUTTON	"OEM"	IDD OEM,		88,	28,	12	
GROUPBOX	"&Quality"	-1,		102,	62,	48,	CP
THE PARTY OF THE P	"Draft"		0	112,	42,	12,	
RADIOBUTTON		IDD QDRAFT,		124,	40,	12	GI
RADIOBUTTON	"Default"	IDD QDEF,	0,	1241			
RADIOBUTTON	"Proof"	IDD_QPROOF,	8,	136,	42,	12	an
GROUPBOX	"&Pitch"	-1,	70,	102,	52,	48,	
RADIOBUTTON	"Default"	IDD_PDEF,	74,	112,	46,	12,	GT
RADIOBUTTON	"Fixed"	IDD_PFIXED,		124,	46,	12	
RADIOBUTTON	"Variable"	IDD_PVAR,		136,	46,	12	
GROUPBOX	"&Family"	-1,	126,	66,	60,	84,	GR
RADIOBUTTON	"Don't Care"	IDD DONT,	130,	76,	54,	12,	GT
RADIOBUTTON	"Roman"	IDD ROMAN,	130,	88,	54,	12	
RADIOBUTTON	"Swiss"	IDD SWISS,	130,	100,	54,	12	
RADIOBUTTON	"Modern"	IDD MODERN,	130,		54,	12	
RADIOBUTTON	"Script"	IDD SCRIPT,		124,	54,	12	
RADIOBUTTON	"Decorative"	IDD DEC,	130,		52,	12	
LTEXT	"Face &Name"	-1,		154,	42,	8	
EDITTEXT	ruce andies	IDD FACE,	48	152,	74.	14	
	"&Ok"	IDD OK,		152,	60,	14,	CT.
DEFPUSHBUTTON			192,			164,	
GROUPBOX	"Text Metrics"	-1,	200,	14,	44,	8	40.00
LTEXT	"Height:"	-1,				8	
LTEXT	"Ascent:"	-1,	200,	24,	44,		
LTEXT	"Descent:"	-1,	200,	34,	46,	8	
LTEXT	"Int Lead:"	-1,	200,	44,	44,	8	
LTEXT	"Ext Lead:"	-1,	200,	54,	44,	8	
LTEXT	"Ave Width:"	-1,	200,	64,	44,	8	
LTEXT	"Max Width:"	-1,	200,	74,	44,	8	
LTEXT	"Weight:"	-1,	200,	84,	44,	8	
LTEXT	"Pitch:"	-1,	200,	94,	44,	8	
LTEXT	"Family:"	-1,	200,	104,	42,	8	
LTEXT	"Char Set:"	-1,		114,	44,	8	
LTEXT	"Overhang:"	-1,		124,	44,	8	
LTEXT	"X Aspect:"	-1,		134,	44,	8	
LTEXT	"Y Aspect:"	-1,		144,	44,	8	
	"Face Name:"	-1,	200,	154,	44,	8	
LTEXT	"race Name:"			127 750 750			
RTEXT		TM_HEIGHT,	250,	14,	44,	8	
RTEXT	"0"	TM_ASCENT,	250,	24,	44,	8	
RTEXT	"0"	TM_DESCENT,	250,	34,	44,	8	
RTEXT	"0"	TM_EXTLEAD,	250,	54,			
	HOH	TM INTLEAD,	250,	44,	44,	8	
RTEXT	n0n	TM AVEWIDTH,		64,	44,	8	

Figure 15-5. Continued

```
TM MAXWIDTH, 250, 74, 44, TM WEIGHT, 250, 84, 44, TM PITCH, 250, 94, 44, TM FAMILY, 250, 104, 44,
                            "O"
      RTEXT
                                                                                                            8
                            "0"
      RTEXT
                                                                                                            8
                            ...
      RTEXT
                                                                                                            8
                            ...
      RTEXT
                                                                                                           8
                                                           TM_CHARSET, 250, 114,
                            ...
      RTEXT
                                                                                                  44,
                                                                                                           8
                                                           TM OVER, 250, 124, 44, 
TM_DIGX, 250, 134, 44, 
TM_DIGY, 250, 144, 44,
                            #O#
      RTEXT
                                                                                                           8
      RTEXT
                            HOH
                                                                                                           8
                            11011
      RTEXT
                                                                                                           8
      RTEXT
                            m m
                                                           TF NAME,
                                                                               250, 154, 44,
END
```

```
NAME
               PICKFONT
DESCRIPTION
               'Font Picker Program (C) Charles Petzold, 1987'
              'WINSTUB. EXE'
STUB
CODE
              MOVEABLE
DATA
               MOVEABLE MULTIPLE
HEAPSIZE
               1024
STACKSIZE
               4096
EXPORTS
               WndProc
               DigProc
```

Figure 15-6 shows a typical PICKFONT screen. The left side of the PICKFONT display is a modeless dialog box that allows you to select most of the fields of the logical font structure. The right side shows the results of <code>GetTextMetrics</code> after the font is selected into the device context. A sample line of text using this font appears at the bottom of the screen.

		Font Picker	SHIPMARK	3	Û
Height 26 Width Weight Match Aspect	Mapping Mode Text Lo Metric Hi Metric 'Logical To	O Lo English O Hi English O Twips wips'	Text Metrics Height: Ascent: Descent: Int Lead: Ext Lead:	26 20 6 2	
☐ <u>l</u> talic ☐ <u>U</u> nderline ☐ <u>S</u> trike-Out	Char Set	Family O Bon't Care Roman	Ave Width: Max Width: Weight: Pitch:	13 33 400 VARIABLE	
Quality O Draft O Default Proof	Pitch Befault Fixed Variable	O Swiss O Modern O Script O Decorative	Family: Char Set: Overhang: X Aspect:	Roman ANSI 0 72	
Face Name		Qk)	Y Aspect: Face Name:	96 Tes Ren	
AaBbCcD	dEeFfGg	HhIiJjKk	LlMmNnC)oPqQq	R

Figure 15-6. A typical PICKFONT display

The modeless dialog box also contains some options that are not part of the logical font structure. These are the mapping mode (including my "Logical Twips" mapping mode) and the "mapper flag," which changes the way Windows matches a logical font to a real font.

Much of the PICKFONT program contains the logic necessary to maintain the dialog box, so I won't go into detail on the workings of the program. Instead, I'll explain what you're doing when you create and select a logical font.

The Logical Font Structure

You first define a structure of type LOGFONT:

```
LOGFONT logfont ;
```

When you call CreateFontIndirect, you give Windows a pointer to this structure:

```
hFont = CreateFontIndirect (&logfont) ;
```

The 14 fields of this structure are the same as the 14 parameters to CreateFont.

You don't need to set each and every field of the LOGFONT structure. If your logical font structure is defined as a static variable, it will be initialized to 0. The 0 values are defaults. You can use that structure directly without any changes, and *CreateFontIndirect* will return a handle to a font. When you select that font into the device context, you'll get a reasonable default font. You can be as specific or as vague as you want in the LOGFONT structure, and Windows will attempt to match your requests with a real font.

The first two fields of the LOGFONT structure are in logical units, so they depend on the current setting of the mapping mode:

- If Height (short integer)—This is the desired height of the characters (including
 internal leading but not external leading) in logical units. Because the point size of
 the font itself is the height of the font less internal leading, you're really specifying
 a line spacing here. You can set it to 0 for a default size. If you set If Height to a
 negative number, Windows treats the absolute value of that number as a desired
 ascent size rather than a height.
- If Width (short integer)—This is the desired width of the characters in logical
 units. In most cases you'll want to set this to 0 and let Windows choose a font
 based on the height. If you use a nonzero value, Windows might be forced to use a
 font designed for a different aspect ratio than that of the device context into which
 you later select the font.

The next two fields specify the "escapement" and "orientation" of the text. In theory, If Escapement allows character strings to be written at an angle, and If Orientation allows characters to be tilted. These two fields are not included in the PICKFONT program, however, because they currently don't work well on the screen. Before you try to use these on a device, you should use the TEXTCAPS index to GetDeviceCaps to check the device's ability to do character rotation. If Escapement (short integer)—This is an angle in tenths of a degree, measured from the horizontal in a counterclockwise direction. It specifies the placement of the string when you write text with TextOut. Here are some examples:

Value	Placement of Characters
0	Run from left to right (default)
900	Go up
1800	Run from right to left
2700	Go down

 If Orientation (short integer)—This is an angle in tenths of a degree, measured from the horizontal in a counterclockwise direction. It specifies the appearance of each character. Here are some examples:

Value	Character Appearance	
0	Normal (default)	
900	Tipped 90 degrees to the left	
1800	Upside down	
2700	Tipped 90 degrees to the right	

The remaining 10 fields follow:

 If Weight (short integer)—This field allows you to specify boldface. Currently, there are only two recommended values:

Value	Result	
400	Normal	
400 700	Boldface	

In actuality, any value from 0 to 550 is normal, and any value greater than 550 is boldface. If you like to plan for the future, WINDOWS.H has a collection of font weight identifiers:

Value	Identifier	
0	FW_DONTCARE	
100	FW_THIN	
200	FW_EXTRALIGHT or FW_ULTRALIGHT	
300	FW_LIGHT	
400	FW_NORMAL or FW_REGULAR	
500	FW_MEDIUM	
600	FW_SEMIBOLD or FW_DEMIBOLD	
700	FW_BOLD	
800	FW_EXTRABOLD or FW_ULTRABOLD	
900	FW_HEAVY or FW_BLACK	

- IfItalic (BYTE)—When nonzero, this specifies italics. Windows can synthesize
 italics on GDI-based fonts. To determine what a particular device can do with a
 device-based font, check the TC_IA_ABLE bit of the TEXTCAPS value returned
 from GetDeviceCaps.
- If Underline (BYTE)—When nonzero, this specifies underlining, which is synthesized on GDI-based fonts. For device-based fonts, check the TC_UA_ABLE bit from GetDeviceCaps.
- If StrikeOut (BYTE)—When nonzero, this specifies that the font should have a line drawn through the characters. This also is synthesized on GDI-based fonts. For device-based fonts, check the TC_SO_ABLE bit.
- IfCharSet (BYTE)—This is the character set of the font. WINDOWS.H currently
 contains three identifiers for the character set:

Value	Identifier	
0	ANSI_CHARSET	
128	SHIFTJIS_CHARSET (Japanese Kanji)	
255	OEM_CHARSET	

The Kanji character sets are not, of course, included with American or European releases of Windows.

If OutPrecision (BYTE)—This specifies how Windows should attempt to match the
desired font sizes and characteristics with actual fonts. This field is not yet
implemented and is not included in the PICKFONT program. WINDOWS.H contains
four identifiers for the field:

Value	Identifier	
0	OUT_DEFAULT_PRECIS	
1	OUT_STRING_PRECIS	
2	OUT_CHARACTER_PRECIS	
3	OUT_STROKE_PRECIS	

IfClipPrecision (BYTE)—This specifies how to clip characters that are partly
outside the clipping region. The field is not yet implemented and is not included in
the PICKFONTS program. WINDOWS.H contains three identifiers:

Value	Identifier	
0	CLIP_DEFAULT_PRECIS	
1	CLIP_CHARACTER_PRECIS	
2	CLIP_STROKE_PRECIS	

 If Quality (BYTE)—This is actually an instruction to Windows regarding the matching of a desired font with a real font. There are three identifiers you can use:

Value	Identifier	
0	DEFAULT_QUALITY	
1	DRAFT_QUALITY	
2	PROOF_QUALITY	

If you specify PROOF_QUALITY, you're telling Windows that you don't want a font to be increased to a larger size to match the character height or width that you request. The PROOF_QUALITY fonts are the most attractive, but they may be smaller than what you request.

 If PitchAnd Family (BYTE)—This byte is composed of two parts. You can use the C OR operator to combine two identifiers for this field. The lowest two bits specify the pitch of the font:

Value	Identifier	
0	DEFAULT_PITCH	
1	FIXED_PITCH	
2	VARIABLE_PITCH	

If you specify FIXED_PITCH, Windows will pick a font that has a fixed pitch, because you're essentially telling Windows that your program can't deal with variable-pitch fonts.

The upper half of this byte specifies the font family:

Value	Identifier	
0x00	FF_DONTCARE	
0x10	FF_ROMAN	
0x20	FF_SWISS	
0x30	FF_MODERN	
0x40	FF_SCRIPT	
0x50	FF_DECORATIVE	

 If FaceName (BYTE array)—This is the name of a typeface (such as Courier, Helv, or Tms Rmn). WINDOWS.H includes a LF_FACESIZE identifier that equals 32, which is the maximum number of characters allowed for the typeface name.

The Font-Mapping Algorithm

After you set up the logical font structure, you call *CreateFontIndirect* to get a handle to the logical font. When you use *SelectObject* to select that logical font into a device context, Windows finds the real font that most closely matches the request. In doing so, it uses a "font-mapping algorithm." Certain fields of the structure are more important than other fields.

The best way to get a feel for font mapping is to spend an hour or so experimenting with PICKFONT. Here are some general guidelines:

- The If CharSet (character set) field is very important. For the display, if you specify
 OEM_CHARSET, you'll get either one of the vector fonts or the terminal font,
 because these are the only fonts that do not use the ANSI character set. You have to
 use OEM_CHARSET if you want a GDI-based vector font. A value of ANSI_CHARSET
 always gives you a raster font.
- A pitch value of FIXED_PITCH (in the If PitchAndFamily field) is important, because you are in effect telling Windows that you don't want to deal with a variable-pitch font.
- The If FaceName field is important, because you're being specific about the
 typeface of the font that you want. If you leave If FaceName set to NULL and set the
 If Family field to a value other than FF_DONTCARE, then the latter field becomes
 important, because you're being specific about the font family.
- Windows will attempt to match the lfHeight value even if it needs to increase the size of a smaller font. The height of the actual font will always be less than or equal to that of the requested font unless there is no font small enough to satisfy your request.
- You can prevent Windows from scaling a font by setting IfQuality to PROOF_QUALITY. By doing so, you're telling Windows that the requested height of the font is less important than the appearance of the font.
- If you specify If Height and If Width values that are out of line for the particular aspect ratio of the display, Windows can map to a font that is designed for a display or other device of a different aspect ratio. You can use this trick to get a particularly thin or fat font. In general, however, you'll probably want to avoid this situation, which you do in PICKFONT by clicking the check box marked Match Aspect. PICKFONT makes a call to SetMapperFlags with a flag set to 1:

SetMapperFlags (hDC, 1L) ;

This specifies that Windows should only match fonts that have the same aspect ratio as the display. You can get fonts of other aspect ratios by setting the mapper flag back to the default value:

SetMapperFlags (hDC, OL) ;

Finding Out About the Font

At the right side of its client area, PICKFONT shows you the type of information you can obtain after you select the logical font into the device context. GetTextMetrics tells you the real characteristics of the font, and GetTextFace tells you the typeface name.

To obtain the typeface name, you first define a character array to receive the name:

```
char szFaceName [LF_FACESIZE] ;
```

The LF_FACESIZE identifier is the maximum number of characters in the typeface name. You then tell Windows to copy the typeface name into this array:

```
GetTextFace (hDC, sizeof szFaceName, szFaceName) ;
```

The GetTextMetrics function retrieves information on the size and other characteristics of the font currently selected in the device context:

```
TEXTMETRIC tm;
[other program lines]
GetTextMetrics (hDC, &tm);
```

All the size values that Windows copies into the TEXTMETRIC structure are in logical units except for the digitized aspect ratios. The fields of the TEXTMETRIC structure are as follows:

- tmHeight (short integer)—The height of the character in logical units. This is
 the value that should approximate the lfHeight field specified in the LOGFONT
 structure. It is the sum of the tmAscent and tmDescent fields. Like the lfHeight
 field in the LOGFONT structure, it actually represents the line spacing of the font
 rather than the size, because it includes internal leading.
- tmAscent (short integer)—The height of the character above the baseline in logical units. This should approximate the absolute value of the lfHeight field in the LOGFONT structure if lfHeight is set to a negative value.
- tmDescent (short integer)—The height of the character below the baseline in logical units.
- tmInternalLeading (short integer)—The area used for diacritics on some capital letters. As noted above, the actual internal leading is included in the tmHeight value. You can calculate the point size of the font by subtracting the tmInternalLeading value from the tmHeight value.
- tmExternalLeading (short integer)—An additional amount of line spacing (beyond tmHeight) recommended by the designer of the font.
- tmAveCharWidth (short integer)—The average width of the characters in logical units.
- tmMaxCharWidth (short integer)—The width of the widest character in logical units. This value is the same as tmAveCharWidth for a fixed-pitch font.

THE GRAPHICS DEVICE INTERFACE

- tmWeight (short integer)—The weight of the font, ranging from 0 to 999. Currently, it will be set to either 400 (normal) or 700 (boldface).
- tmltalic (BYTE)—Nonzero for an italic font.
- tmUnderlined (BYTE)—Nonzero for an underlined font.
- tmStruckOut (BYTE)—Nonzero for a strikethrough font.
- tmPitchAndFamily (BYTE)—A value comprising the pitch in the lower two bits
 and the family in the higher four bits. This field is coded the same way as the
 lfPitchAndFamily field in the LOGFONT structure, and you can use the same
 identifiers to extract the information.
- tmCharSet (BYTE)—The character set. Under most circumstances, it will be either 0 (ANSI_CHARSET) or 255 (OEM_CHARSET).
- tmOverhang (short integer)—The amount of extra width (in logical units) that
 Windows adds to a character when synthesizing italic or boldface. When a font is
 italicized, the tmAveCharWidth value remains unchanged, because a string of
 italicized characters has the same overall width as the same string of normal
 characters. For boldfacing, Windows must slightly expand the width of each
 character. For a boldfaced font, the tmAveCharWidth value less the tmOverhang
 value equals the tmAveCharWidth value for the same font without boldfacing.
- tmDigitizedAspectX and tmDigitizedAspectY (short integers)—The aspect ratio for
 which the font is appropriate. If you specify Proof (under Quality) and check
 Match Aspect in PICKFONT, then for most devices these values will be equivalent
 to the pixels-per-logical-inch values returned from GetDeviceCaps. Note, however,
 that these two TEXTMETRIC fields are switched around in relation to the
 corresponding GetDeviceCaps parameters: tmDigitizedAspectX is equivalent to the
 GetDeviceCaps value for the LOGPIXELSY parameter, and tmDigitizedAspectY is
 equivalent to the value for LOGPIXELSX. If the font is scaled to a larger size, then the
 tmDigitizedAspectX and tmDigitizedAspectY values increase accordingly.

Because of space restrictions, the following four fields were not included in the display screen of the PICKFONTS program:

- tmFirstChar(BYTE)—The character code of the first character in the font. For ANSI_CHARSET fonts, this is normally 32, the space character.
- tmLastChar(BYTE)—The character code of the last character in the font. For ANSI_CHARSET fonts, this is normally 255.

- tmDefaultChar(BYTE)—The character that Windows uses to display characters that are not in the font. For ANSI_CHARSET fonts, this is normally 128.
- tmBreakChar(BYTE)—The character that Windows (and your programs) should
 use to determine word breaks when justifying text. For ANSI_CHARSET fonts, this
 is normally 32, the space character.

Working with Variable-Pitch Text

Before this chapter, we worked mostly with the system font, which has a fixed pitch, so we were able to use *tmAveCharWidth* to obtain the width of each character. Now that we're dealing with variable-pitch fonts and with such complexities as additional overhang for italic and boldface fonts, the *tmAveCharWidth* value is no longer appropriate.

To the rescue comes the function GetTextExtent, which calculates the height and width of a character string based on the font currently selected in the device context. The function returns a doubleword:

The height of the font (in logical units) is in the high word; the width is in the low word. You can either use the LOWORD or HIWORD macro to get this information or convert the doubleword to a point structure:

```
POINT ptExtent ;

[other program lines]

ptExtent = MAKEPOINT (dwExtent) ;
```

When you use GetTextExtent, the sum of the parts doesn't necessarily equal the whole. For instance, if an italic font is selected in the device context and you use GetTextExtent to find the width of a single character, the value is the normal width plus the overhang. If you use GetTextExtent to find the width of a two-character italic string, the value is the normal width of the two characters plus the overhang for the second character only.

The sum of the parts also won't equal the whole if the device is a laser printer that can perform "kerning," which is placing letters closer together than is possible using normal character cell arrays. The most obvious example of kerning is a capital W followed by a lower case o. The o actually fits partly underneath the rightmost stroke of the W, so that the width of the two-character string Wo is less than the sum of the individual widths of the two characters. We'll use GetTextExtent (and its companion function SetTextJustification) in the JUSTIFY program later in this chapter.

ENUMERATING THE FONTS

Earlier in the chapter, we covered the particular typefaces and sizes that are available when you're writing a program to display text on the screen. If you want to send this text to a printer, however, how do you know what fonts the printer has? Windows WRITE knows. When you change the current printer, WRITE often comes up with a different list of typeface names and sizes that you can choose from. The function that lets WRITE do this is *Enum-Fonts*. *EnumFonts* uses a call-back function that Windows calls once for each typeface or font that is available on the device.

You use EnumFonts in one of two ways. The first requires that the second parameter be NULL:

```
EnumFonts (hDC, NULL, lpfnEnumFunction, lpData) ;
```

The *lpfnEnumFunction* parameter is a pointer to the call-back function. *EnumFonts* calls this call-back function once for each typeface name available on the device indicated by the *hDC* parameter. Normally, you use *EnumFonts* this way first to get a list of all typefaces supported by the device.

After you have the list of typeface names, you can call EnumFonts once for each typeface:

```
EnumFonts (hDC, szTypeFace, lpfnEnumFunction, lpData);
```

For each call you make to *EnumFonts* in this format, Windows calls *EnumFunction* once for each available size of the particular typeface.


The call-back function has the format:

The function must be listed in the EXPORTS section of the module definition (.DEF) file, and you must obtain a pointer to the function with MakeProcInstance:

The call-back function receives a far pointer to the particular LOGFONT structure that you can use to create this particular font, a far pointer to the TEXTMETRIC structure that will be obtained when you select this font into the device context, a short integer that indicates the type (raster or vector) of the font, and a pointer to programmer-supplied data specified in

the EnumFonts call. (This last parameter simply provides a clean way of passing information to the call-back function without using global data.)

The lower two bits of the nFontType parameter to the EnumFunction call-back function indicate the type of the font:



You can use the identifiers RASTER_FONTTYPE (which equals 1) to determine if the font is raster or vector and DEVICE_FONTTYPE (which equals 2) to determine if the font is device-based or GDI-based. Windows will continue calling the call-back function until all the fonts are enumerated or until the function returns a 0.

The FONTLIST program, shown in Figure 15-7, uses *EnumFonts* to obtain the fonts available on either the display or the current printer. If no printer is available, then *EnumFonts* displays nothing when the Printer option is selected from the menu. (The WINUNDOC.H file from Figure 11-7 is required to compile FONTLIST.)

```
fontlist.obj : fontlist.c fontlist.h
    cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp fontlist.c

fontlist.res : fontlist.rc fontlist.h
    rc -r fontlist.rc

fontlist.exe : fontlist.obj fontlist.def fontlist.res
    link4 fontlist, /align:16, /map, slibw, fontlist
    rc fontlist.res
```

Figure 15-7. The FONTLIST program

```
typedef struct (
     short
                   nFontType ;
               1f ;
     LOGFONT
     TEXTMETRIC tm ;
     ) FONT :
long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG) ;
int FAR PASCAL EnumallFaces (LPLOGFONT, LPTEXTMETRIC, short, ENUMER FAR *); int FAR PASCAL EnumallFonts (LPLOGFONT, LPTEXTMETRIC, short, ENUMER FAR *);
char szAppName [] = "FontList" :
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
     HANDLE
              hInstance, hPrevInstance;
     LPSTR
               lpszCmdLine ;
     int
               nCmdShow :
     HWND
              hWnd ;
     MSG
              msq :
     WNDCLASS wndclass ;
     if (!hPrevInstance)
           wndclass.style
                                  = CS HREDRAW | CS VREDRAW;
           wndclass.lpfnWndProc = WndProc ;
          wndclass.cbClsExtra = 0;
           wndclass.cbWndExtra
                                   = 0;
          wndclass.hInstance = hInstance;
          wndclass.hIcon = LoadIcon (NULL, IDI_APPLICATION) ;
wndclass.hCursor = LoadCursor (NULL, IDC_ARROW) ;
           wndclass.hbrBackground = GetStockObject (WHITE_BRUSH) ;
           wndclass.lpszMenuName = szAppName ;
          wndclass.lpszClassName = szAppName ;
           if (!RegisterClass (&wndclass))
                return FALSE ;
     hWnd = CreateWindow (szAppName, "Font Enumeration",
                           WS OVERLAPPEDWINDOW | WS VSCROLL,
                           CW_USEDEFAULT, 0,
CW_USEDEFAULT, 0,
                           NULL, NULL, hinstance, NULL) ;
     ShowWindow (hWnd, nCmdShow) ;
     UpdateWindow (hWnd) ;
     while (GetMessage (&msg, NULL, 0, 0))
          TranslateMessage (&msg) ;
          DispatchMessage (&msg) ;
     return msg.wParam ;
int FAR PASCAL EnumAllFaces (1f, tm, nFontType, enumer)
     LPLOGFONT
                  1f ;
     LPTEXTMETRIC tm ;
     short
                   nFontType ;
     ENUMER FAR
                   *enumer ;
     LPSTR
                   lpFaces ;
```

```
if (NULL == GlobalReAlloc (enumer->hGMem,
                            (DWORD) LF FACESIZE * (1 + enumer->nCount),
                            GMEM MOVEABLE))
           return 0 ;
     lpFaces = GlobalLock (enumer->hGMem) ;
     lstrcpy (lpFaces + enumer->nCount * LF FACESIZE, lf->lfFaceName) ;
     GlobalUnlock (enumer->hGMem) ;
     enumer->nCount ++ ;
     return 1 ;
int FAR PASCAL EnumAllFonts (1f, tm, nFontType, enumer)
     LPLOGFONT
                  lf :
     LPTEXTMETRIC tm ;
     short nFontType;
ENUMER FAR *enumer;
     FONT FAR
                   *font :
     if (NULL == GlobalReAlloc (enumer->hGMem,
                            (DWORD) sizeof (FONT) * (1 + enumer->nCount),
                            GMEM MOVEABLE))
           return 0 ;
     font = (FONT FAR *) GlobalLock (enumer->hGMem) + enumer->nCount ;
     font->nFontType = nFontType ;
     font->lf = *lf ;
     font->tm = *tm ;
     GlobalUnlock (enumer->hGMem) ;
     enumer->nCount ++ ;
     return 1 ;
void Display (hDC, xChar, yChar, font)
           hDC ;
     HDC
     short
                   xChar, yChar ;
     FONT FAR
                   *font ;
     static FONT f ;
     static char *szYN [] = { "No", "Yes" };

static char *szCS [] = ( "ANSI", "?????", "Kanji", "OEM" );

static char *szOP [] = ( "Default", "String", "Char", "Stroke" );

static char *szCP [] = ( "Default", "Char", "Stroke", "?????" );

static char *szQU [] = ( "Draft", "Default", "Proof", "?????" );
                                                  "Default", "Proof", "?????");
"Fixed", "Variable", "?????");
     static char *szPl [] = { "Default",
     static char *szVR [] = ( "Vector",
                                                  "Raster" ) ;
     static char *szGD [] = ( "GDI",
                                                  "Device" ) :
     static struct
           short x ;
           short y ;
           char *szFmt ;
           short *pData ;
```

Figure 15-7. Continued

```
shorts [] =
                      1, 1, "LOGFONT", NULL,
1, 2, "----", NULL,
1, 3, "Height: $10d", $f.lf.lfHeight,
1, 4, "Width: $10d", $f.lf.lfWidth,
1, 5, "Escapement: $10d", $f.lf.lfEscapement,
1, 6, "Orientation: $10d", $f.lf.lfOrientation,
1, 7, "Weight: $10d", $f.lf.lfWeight,
28, 1, "TEXTMETRIC", NULL,
22 2 "------", NULL,
                    28, 1, "TEXTMETRIC", NULL,
28, 2, "----", Std", &f.tm.tmHeight,
28, 4, "Ascent: %5d", &f.tm.tmAscent,
28, 5, "Descent: %5d", &f.tm.tmDescent,
28, 6, "Int. Leading: %5d", &f.tm.tmInternalLeading,
28, 7, "Ext. Leading: %5d", &f.tm.tmExternalLeading,
28, 8, "Ave. Width: %5d", &f.tm.tmAveCharWidth,
28, 9, "Max. Width: %5d", &f.tm.tmMaxCharWidth,
28, 10, "Weight: %5d", &f.tm.tmWeight,
51, 10, "Overhang: %10d", &f.tm.tmOverhang,
51, 11, "Digitized X: %10d", &f.tm.tmDigitizedAspectX,
51, 12, "Digitized Y: %10d", &f.tm.tmDigitizedAspectY
static struct
                      short x ;
                       short y ;
                       char *szFmt ;
                      BYTE *pData ;
                      bytes [] =
                      151, 3, "First Char: $10d", &f.tm.tmFirstChar,
51, 4, "Last Char: $10d", &f.tm.tmLastChar,
51, 5, "Default Char: $10d", &f.tm.tmDefaultChar,
51, 6, "Break Char: $10d", &f.tm.tmBreakChar
static struct
                      short x ;
                      short y ;
                      char *szFmt;
BYTE *pData;
char **szArray;
                      short sAnd ;
                      short sShift ;
                       strings [] =
                     1, 8, "Italic: $10s", &f.lf.lfItalic, szYN, 1, 0, 1, 9, "Underline: $10s", &f.lf.lfUnderline, szYN, 1, 0, 1, 10, "Strike-Out: $10s", &f.lf.lfStrikeOut, szYN, 1, 0, 1, 11, "Char Set: $10s", &f.lf.lfStrikeOut, szCN, 0xCO, 6, 1, 12, "Out Prec: $10s", &f.lf.lfCharSet, szCS, 0xCO, 6, 1, 13, "Clip Prec: $10s", &f.lf.lfOutPrecision, szCP, 3, 0, 1, 14, "Quality: $10s", &f.lf.lfClipPrecision, szCP, 3, 0, 1, 15, "Pitch: $10s", &f.lf.lfQuality, szQU, 3, 0, 1, 15, "Pitch: $10s", &f.lf.lfPitchAndFamily, szP1, 3, 0, 1, 16, "Family: $10s", &f.lf.lfPitchAndFamily, szFA, 0x70, 4, 28, 11, "Italic: $5s", &f.tm.tmItalic, szYN, 1, 0,
```

```
28, 12, "Underline: %5s", &f.tm.tmUnderlined,
                                                            szYN, 1,
                                                                        0,
        0,
                                     (BYTE *) &f.nFontType, szVR, 1, (BYTE *) &f.nFontType, szGD, 2,
         55, 15, "%s",
                                                                        1
         ) ;
    char szBuffer [80] ;
    int i;
    f = *font :
    for (i = 0 ; i < sizeof shorts / sizeof shorts [0] ; i++)
         TextOut (hDC, xChar * shorts[i].x, yChar * shorts[i].y, szBuffer,
                   sprintf (szBuffer, shorts[i].szFmt, *shorts[i].pData)) ;
    for (i = 0 ; i < sizeof bytes / sizeof bytes [0] ; i++)
         TextOut (hDC, xChar * bytes[i].x, yChar * bytes[i].y, szBuffer,
                   sprintf (szBuffer, bytes[i].szFmt, *bytes[i].pData)) ;
    for (i = 0 ; i < sizeof strings / sizeof strings [0] ; i++)
         TextOut (hDC, xChar * strings[i].x, yChar * strings[i].y, szBuffer,
                   sprintf (szBuffer, strings[i].szFmt, (strings[i].szArray)
                            [(*strings[i].pData & strings[i].sAnd) >>
                                          strings[i].sShift])) ;
    HDC GetPrinterIC ()
    char szPrinter [64] ;
    char *szDevice, *szDriver, *szOutput ;
    GetProfileString ("windows", "device", "", szPrinter, 64) ;
    if ((szDevice = strtok (szPrinter, "," )) &&
                                      ", "))) &&
        (szDriver = strtok (NULL,
(szOutput = strtok (NULL,
              return CreateIC (szDriver, szDevice, szOutput, NULL) ;
    return NULL ;
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
     HWND
                   hwnd ;
     unsigned
                   iMessage ;
     WORD
                   wParam ;
     LONG
                   lParam ;
                  bHaveInfo = FALSE :
     static BOOL
     static ENUMER enumer1, enumer2;
     static FARPROC lpfnEnumAllFaces, lpfnEnumAllFonts;
     static short
                   xChar, yChar, nCurrent;
                   wCurrentDC = IDM SCREEN ;
     static WORD
     HANDLE
                   hInstance ;
```

Figure 15-7. Continued

```
HDC
               hDC ;
HFONT
               hFont ;
HMENU
               hMenu ;
FONT FAR
               *font ;
               lpFaces ;
LPSTR
PAINTSTRUCT
               ps ;
short
               1 ;
TEXTMETRIC
               tm ;
switch (iMessage)
     case WM CREATE:
         hInstance = ((LPCREATESTRUCT) 1Param) -> hInstance ;
         lpfnEnumAllFaces = MakeProcInstance (EnumAllFaces, hInstance) ;
          lpfnEnumAllFonts = MakeProcInstance (EnumAllFonts, hInstance) :
         hDC = GetDC (hWnd) ;
         GetTextMetrics (hDC, (LPTEXTMETRIC) &tm) ;
          xChar = tm.tmAveCharWidth ;
          yChar = tm.tmHeight + tm.tmExternalLeading ;
          ReleaseDC (hWnd, hDC) ;
         break ;
    case WM COMMAND:
          if (wParam == IDM EXIT)
               SendMessage (hWnd, WM CLOSE, 0, 0L) ;
               break ;
          else if (wParam == wCurrentDC)
              break ;
         hMenu = GetMenu (hWnd) ;
         CheckMenuItem (hMenu, wCurrentDC, MF_UNCHECKED) ;
         CheckMenuItem (hMenu, wCurrentDC = wParam, MF CHECKED) ;
                                   /* fall through */
    case WM DEVMODECHANGE:
    case WM FONTCHANGE:
         bHaveInfo = FALSE ;
         InvalidateRect (hWnd, NULL, TRUE) ;
         break ;
    case WM PAINT:
         if (!bHaveInfo)
               if (enumer2.hGMem)
                    GlobalFree (enumer2.hGMem) ;
               enumer1.hGMem = GlobalAlloc (GHND, 1L) ;
              enumer1.nCount = 0 ;
              enumer2.hGMem = GlobalAlloc (GHND, 1L) ;
              enumer2.nCount = 0 ;
              if (NULL == enumer1.hGMem || NULL == enumer2.hGMem)
                   goto MEMORY ERROR ;
```

Figure 15-7. Continued

```
if (wCurrentDC == IDM SCREEN)
               hDC = CreateIC ("DISPLAY", NULL, NULL, NULL) ;
               hDC = GetPrinterIC () ;
          if (hDC)
               if (0 == EnumFonts (hDC, NULL, lpfnEnumAllFaces,
                                          (LPSTR) &enumer1))
                    goto MEMORY ERROR ;
               lpFaces = GlobalLock (enumer1.hGMem) ;
               for (i = 0 ; i < enumer1.nCount ; i++)
                    lpfnEnumAllFonts,
                                     (LPSTR) &enumer2))
                          goto MEMORY ERROR ;
               GlobalUnlock (enumer1.hGMem) ;
               enumer2.nCount--;
               DeleteDC (hDC) ;
               bHaveInfo = TRUE ;
          GlobalFree (enumer1.hGMem) ;
          SetScrollRange (hWnd, SB_VERT, 0, enumer2.nCount, FALSE);
SetScrollPos (hWnd, SB_VERT, nCurrent = 0, TRUE);
     hDC = BeginPaint (hWnd, &ps) ;
     if (bHaveInfo)
          font = (FONT FAR *) GlobalLock (enumer2.hGMem) + nCurrent ;
          Display (hDC, xChar, yChar, font) ;
hFont = SelectObject (hDC, CreateFontIndirect (&font->lf));
          TextOut (hDC, 1 * xChar, 19 * yChar,
               "AaBbCcDdEeFfGgHhIiJjKkLlMmNnOoPpQqRrSsTtUuVvWwXxYyZz",
               52) ;
          GlobalUnlock (enumer2.hGMem) ;
          DeleteObject (SelectObject (hDC, hFont)) ;
     EndPaint (hWnd, &ps) ;
     break ;
case WM KEYDOWN:
     switch (wParam)
          case VK HOME:
                SendMessage (hWnd, WM_VSCROLL, SB_TOP, OL) ;
                break ;
          case VK END:
                SendMessage (hWnd, WM VSCROLL, SB BOTTOM, OL) ;
                break ;
```

Figure 15-7. Continued

```
case VK LEFT:
                 case VK UP:
                 case VK PRIOR:
                       SendMessage (hWnd, WM VSCROLL, SB LINEUP, OL) ;
                       break ;
                 case VK RIGHT:
                 case VK_DOWN:
case VK_NEXT:
                       SendMessage (hWnd, WM_VSCROLL, SB_LINEDOWN, OL) ;
                       break ;
           break :
      case WM VSCROLL:
            switch (wParam)
                 case SB TOP:
                       nCurrent = 0 ;
                       break ;
                 case SB BOTTOM:
                      nCurrent = enumer2.nCount ;
                       break ;
                 case SB_LINEUP:
                 case SB PAGEUP:
                       nCurrent -- ;
                       break :
                 case SB LINEDOWN:
                 case SB PAGEDOWN:
                       nCurrent ++ ;
                       break ;
                 case SB THUMBPOSITION:
                       nCurrent = LOWORD (1Param) ;
                       break :
                 default:
                       return OL ;
           nCurrent = min (max (0, nCurrent), enumer2.nCount) ;
SetScrollPos (hWnd, SB VERT, nCurrent, TRUE) ;
InvalidateRect (hWnd, NULL, TRUE) ;
           break ;
      MEMORY ERROR:
           MessageBox (hWnd, "Cannot allocate memory, must end.",
                 szAppName, MB OK | MB ICONHAND | MB SYSTEMMODAL) ;
                                             /* fall through */
      case WM CLOSE:
           DestroyWindow (hWnd) ;
           break ;
      case WM DESTROY:
           PostQuitMessage (0) ;
           break ;
      default:
           return DefWindowProc (hWnd, iMessage, wParam, lParam) ;
return OL ;
```

Figure 15-7. Continued

```
#define IDM_SCREEN 1
#define IDM_PRINTER 2
#define IDM_EXIT 3
```

```
#include "fontlist.h"

FontList MENU

BEGIN

POPUP "&Device"

BEGIN

MENUITEM "&Screen", IDM SCREEN, CHECKED

MENUITEM "&Printer", IDM_PRINTER

MENUITEM SEPARATOR

MENUITEM "E&xit", IDM_EXIT

END

END
```

```
NAME FONTLIST
DESCRIPTION 'Font Enumeration Program (C) Charles Petzold, 1987'
STUB 'WINSTUB.EXE'
CODE MOVEABLE
DATA MOVEABLE MULTIPLE
HEAPSIZE 1024
STACKSIZE 4096
EXPORTS WndProc
EnumAllFaces
EnumAllFonts
```

FONTLIST uses two separate call-back functions to enumerate the fonts. The first, called *EnumAllFaces*, accumulates the typeface names. The second, *EnumAllFonts*, accumulates all the sizes for each typeface name. The program uses global memory blocks to store this information. If FONTLIST runs out of memory space, the program aborts after displaying a message box.

After FONTLIST is finished getting the fonts, it displays both the logical font structure and the text metrics structure for each font, one font per screen, with a sample line of text at the bottom of the screen. You can move through the fonts using the vertical scroll bar or the cursor keys. A large part of the program (the *Display* function) is devoted to formatting the information for display. Figure 15-8 (on the following page) shows a typical FONTLIST screen.




Figure 15-8. A typical FONTLIST display

FONTLIST intercepts the WM_DEVMODECHANGE message (which indicates a change of the printer) and the WM_FONTCHANGE message (which indicates a change in the font resources). You can use FONTLIST to examine the fonts available on different printers by changing the current printer using the CONTROL program. If you choose to list the fonts for the current printer, you may wonder how FONTLIST is able to display a device-based printer font at the bottom of the client area. Although FONTLIST shows the logical font and text metrics structures for device-based printer fonts, the sample text is a normal GDI-based font that Windows picks based on the logical font structure for the printer font. It's the closest approximation of the printer font that Windows can display on the screen.

FORMATTING TEXT

Now that you know how to determine the fonts available on a particular device, how to create a font and select it into the device context, and how to determine the sizes and characteristics of the fonts, it's time to try your hand at text formatting. The process involves placing each line of text within margins in one of four ways: aligned on the left margin, aligned on the right margin, centered between the margins, or justified—that is, running from one margin to the other, with equal spaces between the words. For the first three jobs, you can use the <code>DrawText</code> function with the <code>DT_WORDBREAK</code> parameter, but this approach has

limitations. For instance, you can't determine what part of the text *DrawText* was able to fit within the rectangle. *DrawText* is convenient for some simple jobs, but for more complex formatting tasks, you'll probably want to employ *TextOut*.

One of the most useful functions for working with text is GetTextExtent. This function tells you the width and height of a character string based on the current font selected in the device context:

```
dwExtent = GetTextExtent (hDC, lpString, nCount) ;
```

The width of the text in logical units is in the low word of *dwExtent*, and the height of the text in logical units is in the high word. Although you can also obtain the text height from the *tmHeight* field of the TEXTMETRIC structure, the TEXTMETRIC width is inadequate when you're working with variable-pitch fonts or with italic or boldface text.

Breaking text into lines involves searching for break characters. In theory, you should determine the font's break character from the *tmBreakChar* field of the TEXTMETRIC structure, but you can also simply assume that it's the space character (ASCII number 32). In theory, you should also use the *AnsiNext* and *AnsiPrev* functions to step through the string, but you'll get better performance if you use normal C pointer arithmetic. (Of course, if you hope eventually to convert your programs to languages that use other character sets, which might have 2 or more bytes per character, then you had best follow these "in theory" rules right from the start.)

One-Line Text Alignment

I'll begin with an example using one line of text. Let's say that you have selected a font into your device context and now want to write the text:

```
char *szText [] = "Hello, how are you?" ;
```

You want the text to start at the vertical coordinate yStart, within margins set by the coordinates xLeft and xRight. Your job is to calculate the xStart value for the horizontal coordinate where the text begins.

First, you get the text extents of the string:

```
dwExtent = GetTextExtent (hDC, szText, strlen (szText)) ;
```

If the low word of dwExtent is larger than (xRight - xLeft), then the line is too long to fit within the margins. Let's assume it can fit.

To align the text on the left margin, you simply set xStart equal to xLeft and then write the text:

```
TextOut (hDC, xStart, yStart, szText, strlen (szText)) ;
```

This is easy. You can now add the high word of dwExtent to yStart, and you're ready to write the next line of text.

To align the text on the right margin, you use this formula for xStart:

```
xStart = xRight - LOWORD (dwExtent) ;
```

To center the text between the left and right margins, use this formula:

```
xStart = (xLeft + xRight - LOWORD (dwExtent)) / 2 ;
```

Now here's the tough job—to justify the text within the left and right margins. The distance between the margins is (xRight - xLeft). Without justification, the text is LOWORD (dwExtent) wide. The difference between these two values, which is:

```
xRight - xLeft - LOWORD (dwExtent)
```

must be equally distributed among the three space characters in the character string. It sounds like a terrible job, but it's not too bad. To do it, you call:

```
SetTextJustification (hDC, xRight - xLeft - LOWORD (dwExtent), 3) ;
```

The second parameter is the amount of space that must be distributed among the space characters in the character string. The third parameter is the number of space characters—in this case, 3.

Now set xStart equal to xLeft and write the text with TextOut.

```
TextOut (hDC, xStart, yStart, szText, strlen (szText));
```

The text will be justified between the xLeft and xRight margins.

Whenever you call *SetTextfustification*, it accumulates an error term if the amount of space doesn't distribute evenly among the space characters. This error term will affect subsequent *GetTextExtent* calls. Each time you start a new line, you should clear out the error term by calling:

```
SetTextJustification (hDC, 0, 0);
```

Working with Paragraphs

If you're working with a whole paragraph, you have to start at the beginning and scan through the string looking for blanks. Every time you encounter a blank, you call GetText-Extent to determine if the text still fits between the left and right margins. When the text exceeds the space allowed for it, then you backtrack to the previous blank. Now you have determined the character string for the line. If you want to justify the line, call SetTextJustification and TextOut, clear out the error term, and proceed to the next line.

The JUSTIFY program, shown in Figure 15-9, does this job for the first paragraph of Herman Melville's *Moby-Dick*. (The WINUNDOC.H file from Figure 11-7 is required to compile JUSTIFY.) You choose a screen font, and the Alignment menu lets you align the text on the left or right, center it, or justify it. Figure 15-10 (on page 696) shows a typical JUSTIFY screen.

```
justify.obj : justify.c justify.h
    cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp justify.c

justify.res : justify.rc justify.asc justify.h
    rc -r justify.rc

justify.exe : justify.obj justify.def justify.res
    link4 justify, /align:16, /map, slibw, justify
    rc justify.res
```

```
/* JUSTIFY.C -- Justified Type Program */
#include <windows.h>
#include <string.h>
#include <stdio.h>
#include "winundoc.h"
#include "justify.h"
typedef struct (
     short nNumFaces; char szFaceNames [MAX_FACES] [LF_FACESIZE];
     ENUMFACE ;
typedef struct (
     short
                 nNumSizes :
     short
                 nAspect ;
     LOGFONT 1f [MAX SIZES] ;
     TEXTMETRIC tm [MAX SIZES] ;
     ENUMSIZE ;
long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG) ;
int FAR PASCAL EnumallFaces (LPLOGFONT, LPTEXTMETRIC, short, ENUMFACE FAR *); int FAR PASCAL EnumallSizes (LPLOGFONT, LPTEXTMETRIC, short, ENUMSIZE FAR *);
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
     HANDLE hInstance, hPrevInstance;
     LPSTR
               lpszCmdLine ;
               nCmdShow ;
     int
     static
               char szAppName [] = "Justify" ;
     HWND
               hWnd ;
     MSG
               msg ;
     WNDCLASS wndclass ;
```

Figure 15-9. The JUSTIFY program

Figure 15-9. Continued

```
if (!hPrevInstance)
          wndclass.style
                                  = CS HREDRAW | CS VREDRAW | CS OWNDC ;
          wndclass.lpfnWndProc = WndProc ;
          wndclass.cbClsExtra
                                 = 0 :
                                = 0;
          wndclass.cbWndExtra
          wndclass.hInstance
                                 = hInstance ;
         wndclass.hlcon
                                  = LoadIcon (NULL, IDI APPLICATION) ;
          wndclass.hCursor = LoadCursor (NULL, IDC ARROW);
wndclass.hbrBackground = GetStockObject (WHITE BRUSH);
          wndclass.lpszMenuName = szAppName ;
          wndclass.lpszClassName = szAppName ;
          if (!RegisterClass (&wndclass))
               return FALSE ;
     hWnd = CreateWindow (szAppName, "Justified Type",
                          WS OVERLAPPEDWINDOW,
                          CW_USEDEFAULT, 0,
CW_USEDEFAULT, 0,
                          NULL, NULL, hInstance, NULL) ;
     ShowWindow (hWnd, nCmdShow) ;
     UpdateWindow (hWnd) ;
     while (GetMessage (&msg, NULL, 0, 0))
          TranslateMessage (&msg) ;
          DispatchMessage (&msg) ;
     return msg.wParam ;
int FAR PASCAL EnumAllFaces (lplf, lptm, nFontType, lpef)
     LPLOGFONT
                 lplf ;
     LPTEXTMETRIC lptm ;
     short
                  nFontType 1
     ENUMFACE FAR *lpef ;
     if (nFontType & RASTER FONTTYPE)
          istrcpy (lpef->szFaceNames[lpef->nNumFaces], lplf->lfFaceName) ;
          if (++lpef->nNumFaces == MAX_FACES)
               return 0 ;
     return 1 ;
int FAR PASCAL EnumAllSizes (lplf, lptm, nFontType, lpes)
     LPLOGFONT lplf ;
     LPTEXTMETRIC lptm ;
     short
                  nFontType ;
     ENUMSIZE FAR *1pes ;
     if (lpes->nAspect == (100 * lptm->tmDigitizedAspectY /
                                   lptm->tmDigitizedAspectX))
```

```
lpes->lf [lpes->nNumSizes] = *lplf ;
          lpes->tm [lpes->nNumSizes] = *lptm ;
          if (++1pes->nNumSizes == MAX SIZES)
               return 0 ;
     return 1 ;
short MakeSizeMenu (hWnd, lpfnEnumAllSizes, pes, szFaceName)
                    hWnd ;
                    lpfnEnumAllSizes ;
     FARPROC
     ENUMSIZE
                     *pes ;
     char
                    *szFaceName ;
     static LOGFONT lfBlank ;
     char
                    szBuffer [20] ;
                    hDC = GetDC (hWnd) ;
     HDC
     HMENU
                    hPopup = GetSubMenu (GetMenu (hWnd), SIZE MENU) ;
     short
     pes->nNumSizes = 0 ;
     EnumFonts (hDC, szFaceName, lpfnEnumAllSizes, (LPSTR) pes) ;
     ReleaseDC (hWnd, hDC) ;
     while (GetMenuItemCount (hPopup) > 0)
          ChangeMenu (hPopup, 0, NULL, NULL, MF DELETE | MF BYPOSITION) ;
     if (pes->nNumSizes)
          for (i = 0 ; i < pes->nNumSizes ; i++)
               sprintf (szBuffer, "%i %2d / %2d", i + 1,
                     (pes->tm[i].tmHeight - pes->tm[i].tmInternalLeading + 10)
               (pes->tm[i].tmHeight + 10) / 20) ;
ChangeMenu (hPopup, 0, szBuffer, IDM ISIZE + i, MF APPEND) ;
     else
                     /* no fonts found that match aspect ratio of display */
          pes->lf[0] = lfBlank ;
          strcpy (pes->lf[0].lfFaceName, szFaceName) ;
          ChangeMenu (hPopup, 0, "Default", IDM ISIZE, MF APPEND) ;
     CheckMenuItem (hPopup, IDM ISIZE, MF CHECKED) ;
     return 0 ;
void DrawRuler (hDC, ptClient)
                  hDC ;
                            HDC
                                           hDC ;
     POINT
                  ptClient ;
     static short nRuleSize [16] = { 360, 72, 144, 72, 216, 72, 144, 72, 288, 72, 144, 72, 216, 72, 144, 72 };
     short
                  1, 1 :
```

```
MoveTo (hDC, 0, -360);
LineTo (hDC, ptClient.x, -360);
     MoveTo (hDC, -360, 0);
LineTo (hDC, -360, ptClient.y);
     for (i = 0, j = 0 ; i <= ptClient.x ; i += 1440 / 16, j++)
          MoveTo (hDC, i, -360);
          LineTo (hDC, i, -360 - nRuleSize [j % 16]) ;
     for (i = 0, j = 0 ; i \le ptClient.y ; i += 1440 / 16, j++)
          MoveTo (hDC, -360, i) ;
LineTo (hDC, -360 - nRuleSize [j % 16], i) ;
void Justify (hDC, hResource, ptClient, nCurAlign)
     HDC hDC;
HANDLE hResource;
     POINT ptClient;
short nCurAlign;
     DWORD dwExtent;
     LPSTR lpText, lpBegin, lpEnd;
     short i, xStart, yStart, nBreakCount;
     lpText = LockResource (hResource) ;
     yStart = 0 ;
                                     /* for each text line */
     do
          nBreakCount = 0;
          while (*lpText == ' ')
                                    /* skip over leading blanks */
                lpText++ ;
          lpBegin = lpText ;
                                     /* until the line is known */
                lpEnd = lpText ;
                while (*lpText != '\0' && *lpText++ != ' ') ;
                if (*1pText == '\0')
                     break ;
                                     /* for each space, calculate extents */
                nBreakCount++;
                SetTextJustification (hDC, 0, 0);
                dwExtent = GetTextExtent (hDC, lpBegin, lpText - lpBegin - 1) ;
          while (LOWORD (dwExtent) < ptClient.x) ;
          nBreakCount -- ;
          while (*(lpEnd - 1) == ' ') /* eliminate trailing blanks */
                lpEnd-- ;
                nBreakCount -- ;
```

```
if (*lpText == '\0' || nBreakCount <= 0)
               lpEnd = lpText ;
         SetTextJustification (hDC, 0, 0) ;
         dwExtent = GetTextExtent (hDC, lpBegin, lpEnd - lpBegin) ;
                                             /* use alignment for xStart */
         if (nCurAlign == IDM LEFT)
               xStart = 0 ;
         else if (nCurAlign == IDM RIGHT)
               xStart = ptClient.x - LOWORD (dwExtent) ;
         else if (nCurAlign == IDM CENTER)
              xStart = (ptClient.x - LOWORD (dwExtent)) / 2 ;
         olse
               if (*lpText != '\0' && nBreakCount > 0)
                    SetTextJustification (hDC, ptClient.x - LOWORD (dwExtent),
                                                    nBreakCount) ;
               xStart = 0 ;
          TextOut (hDC, xStart, yStart, lpBegin, lpEnd - lpBegin) ;
          yStart += HIWORD (dwExtent) ;
lpText = lpEnd ;
     while (*lpText && yStart < ptClient.y) ;
     GlobalUnlock (hResource) ;
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
     HWND
                   hWnd ;
     unsigned
                      iMessage ;
     WORD
                     wParam :
     LONG
                     lParam ;
     static ENUMFACE ef ;
     static ENUMSIZE es ;
     static FARPROC lpfnEnumAllFaces, lpfnEnumAllSizes;
     static HANDLE hResource;
static POINT ptClient;
static short nCurSize, nCurFace, nCurAttr, nCurAlign = IDM_LEFT;
     HANDLE
                    hInstance ;
                     hDC ;
     HDC
     HFONT
                     hFont ;
                    hMenu, hPopup ;
     HMENU
     PAINTSTRUCT ps ;
     short
                     xLogPixPerInch, yLogPixPerInch, i ;
     switch (iMessage)
          case WM CREATE:
               hDC = GetDC (hWnd) ;
               xLogPixPerInch = GetDeviceCaps (hDC, LOGPIXELSX) ;
               yLogPixPerInch = GetDeviceCaps (hDC, LOGPIXELSY) ;
```

```
/* Set Map Mode */
     SetMapMode (hDC, MM_ANISOTROPIC) ;
     SetWindowExt (hDC, 1440, 1440)
     SetViewportExt (hDC, xLogPixPerInch, yLogPixPerInch) ;
SetWindowOrg (hDC, -720, -720) ;
     es.nAspect = (100 * xLogPixPerInch) / yLogPixPerInch ;
                      /* MakeProcInstance for 2 routines */
     hInstance = ((LPCREATESTRUCT) 1Param) -> hInstance ;
     lpfnEnumAllFaces = MakeProcInstance (EnumAllFaces, hInstance) ;
lpfnEnumAllSizes = MakeProcInstance (EnumAllSizes, hInstance) ;
                       /* Enumerate the Font Faces */
     EnumFonts (hDC, NULL, lpfnEnumAllFaces, (LPSTR) &ef) ;
     ReleaseDC (hWnd, hDC) ;
                       /* Initialize the Menus */
     hMenu = GetMenu (hWnd) ;
     hPopup = CreateMenu () ;
     for (i = 0 ; i < ef.nNumFaces ; i++)
           ChangeMenu (hPopup, 0, ef.szFaceNames[i],
                                             IDM IFACE + 1, MF APPEND) ;
     ChangeMenu (hMenu, IDM_FACE, "&FaceName", hPopup,
                                             MF_CHANGE | MF_POPUP) ;
     CheckMenuItem (hMenu, IDM IFACE, MF CHECKED) ;
     nCurSize = MakeSizeMenu (hWnd, lpfnEnumAllSizes, &es,
                            ef.szFaceNames [nCurFace]) ;
                       /* Load the Text Resource */
     hResource = LoadResource (hInstance,
                   FindResource (hInstance, "Ismael", "TEXT"));
     break ;
case WM SIZE:
     hDC = GetDC (hWnd) ;
     ptClient = MAKEPOINT (1Param) ;
     DPtoLP (hDC, &ptClient, 1) ;
     ptClient.x -= 360 ;
   ReleaseDC (hWnd, hDC) ;
     break ;
case WM COMMAND:
     hMenu = GetMenu (hWnd) ;
     if (wParam >= IDM_IFACE && wParam < IDM_IFACE + MAX_FACES)
           CheckMenuItem (hMenu, nCurFace + IDM_IFACE, MF_UNCHECKED) ;
CheckMenuItem (hMenu, wParam, MF_CHECKED) ;
nCurFace = wParam - IDM_IFACE ;
```

```
nCurSize = MakeSizeMenu (hWnd, lpfnEnumAllSizes, &es,
                                  ef.szFaceNames [nCurFace]) ;
     else if (wParam >= IDM ISIZE && wParam < IDM ISIZE + MAX SIZES)
           CheckMenuItem (hMenu, nCurSize + IDM ISIZE, MF UNCHECKED) ;
           CheckMenuItem (hMenu, wParam, MF CHECKED) ;
           nCursize = wParam - IDM ISIZE ;
     else switch (wParam)
          case IDM BOLD:
           case IDM ITALIC:
          case IDM STRIKE:
           case IDM UNDER:
                CheckMenuItem (hMenu, wParam, MF CHECKED &
                      GetMenuState (hMenu, wParam, MF_BYCOMMAND) ?
                MF_UNCHECKED : MF_CHECKED) ;
ncurAttr = wParam ;
                break ;
           case IDM NORM:
                nCurAttr = 0 ;
                 CheckMenuItem (hMenu, IDM_BOLD, MF_UNCHECKED) ;
                CheckMenuItem (hMenu, IDM ITALIC, MF UNCHECKED);
CheckMenuItem (hMenu, IDM STRIKE, MF UNCHECKED);
CheckMenuItem (hMenu, IDM UNDER, MF UNCHECKED);
                break ;
           case IDM LEFT:
           case IDM RIGHT:
           case IDM CENTER:
           case IDM JUST:
                 CheckMenuItem (hMenu, nCurAlign, MF UNCHECKED) ;
                 nCurAlign = wParam ;
                 CheckMenuItem (hMenu, nCurAlign, MF CHECKED) ;
                 break ;
     InvalidateRect (hWnd, NULL, TRUE) ;
     break ;
case WM PAINT:
     hDC = BeginPaint (hWnd, &ps) ;
     es.lf[nCurSize].lfWeight
                                    = nCurAttr & IDM BOLD ? 700 : 400 ;
                                   = (BYTE) (nCurattr & IDM_ITALIC) ;
     es.lf[nCurSize].lfItalic
     es.lf[nCurSize].lfUnderline = (BYTE) (nCurAttr & IDM UNDER);
es.lf[nCurSize].lfStrikeOut = (BYTE) (nCurAttr & IDM STRIKE);
     hFont = CreateFontIndirect (&es.lf[nCurSize]) ;
     hFont = SelectObject (hDC, hFont) ;
     DrawRuler (hDC, ptClient) ;
     Justify (hDC, hResource, ptClient, nCurAlign) ;
```

```
DeleteObject (SelectObject (hDC, hFont)) ;
          EndPaint (hWnd, &ps) ;
         break ;
     case WM DESTROY:
         FreeResource (hResource) ;
         PostQuitMessage (0) ;
         break ;
     default:
         return DefWindowProc (hWnd, iMessage, wParam, 1Param) ;
return OL ;
```

JUSTIFY

```
#define SIZE MENU
#define MAX FACES
                    16
#define MAX SIZES 16
#define IDM_BOLD
#define IDM_ITALIC
                    2
#define IDM STRIKE
#define IDM_UNDER
                    8
#define IDM FACE
                   0x10
#define IDM SIZE
                   0x11
#define IDM NORM
                   0x12
#define IDM LEFT
                   0x13
#define IDM_RIGHT 0x14
#define IDM CENTER 0x15
#define IDM_JUST
                   0x16
#define IDM_IFACE 0x20
#define IDM ISIZE (IDM IFACE + MAX FACES)
```

```
JUST-FY-RC
```

```
#include "justify.h"
Ismael TEXT justify.asc
Justify MENU
     BEGIN
           MENUITEM "&FaceName",
POPUP "&PointSize"
                                                    IDM FACE
                 BEGIN
                       MENUITEM "temp",
                                                    IDM SIZE
                 END
```

Figure 15-9. Continued

```
POPUP
               "&Attributes"
         BEGIN
               MENUITEM "&Bold",
                                         IDM BOLD
               MENUITEM "&Italic",
                                         IDM_ITALIC
               MENUITEM "&StrikeOut",
                                         IDM STRIKE
               MENUITEM "&Underline",
                                         IDM UNDER
               MENUITEM SEPARATOR
               MENUITEM "&Normal",
                                         IDM NORM
          END
     POPUP
               "A&lignment"
          BEGIN
               MENUITEM "&Left",
                                         IDM_LEFT, CHECKED
               MENUITEM "&Right"
                                         IDM RIGHT
               MENUITEM "&Centered",
                                         IDM CENTER
               MENUITEM "&Justified",
                                        IDM JUST
          END
END
```

Call me Ishmael. Some years ago -- never mind how long precisely -- having litt le or no money in my purse, and nothing particular to interest me on shore, I th ought I would sail about a little and see the watery part of the world. It is a way I have of driving off the spleen, and regulating the circulation. Whenever I find myself growing grim about the mouth; whenever it is a damp, drizzly Nove mber in my soul; whenever I find myself involuntarily pausing before coffin ware houses, and bringing up the rear of every funeral I meet; and especially whenever my hypos get such an upper hand of me, that it requires a strong moral princip le to prevent me from deliberately stepping into the street, and methodically knocking people's hats off -- then, I account it high time to get to sea as soon as I can. This is my substitute for pistol and ball. With a philosophical flour ish Cato throws himself upon his sword; I quietly take to the ship. There is no thing surprising in this. If they but knew it, almost all men in their degree, some time or other, cherish very nearly the same feelings towards the ocean with

JUSTIFY NAME 'Demonstration of Justified Text (C) Charles Petzold, 1987' DESCRIPTION 'WINSTUB.EXE' STUB CODE MOVEABLE MOVEABLE MULTIPLE DATA HEAPSIZE 1024 4096 STACKSIZE EXPORTS WndProc EnumAllFaces EnumAllSizes




Figure 15-10. A typical JUSTIFY display

Like the FONTLIST program, JUSTIFY uses the *EnumFonts* function to obtain the fonts available for the screen. The two call-back functions are called *EnumAllFaces* and *EnumAllSizes*. The program can store up to 16 typeface names and up to 16 font sizes for a particular typeface. During the WM_CREATE message, JUSTIFY calls *EnumFonts* with a NULL second parameter and puts the typeface names into the FaceName menu.

When you select a typeface from the FaceName menu, JUSTIFY calls *EnumFonts* again to get the available sizes of that typeface. JUSTIFY must then reconstruct the PointSize menu, which displays the font sizes in this format:

24 / 28

which means a 24-point font on a 28-point line spacing. The Attributes menu offers the options Bold, Italic, StrikeOut, and Underline, and the aforementioned Alignment menu has the options Left, Right, Centered, and Justified.

JUSTIFY uses the "Logical Twips" mapping mode to facilitate the translation into point sizes of the information available from the TEXTMETRIC structure. To avoid setting this mapping mode every time it obtains a device context, JUSTIFY uses the CS_OWNDC class style.

JUSTIFY displays a ruler (in logical inches, of course) across the top and down the left side of the client area. The *DrawRuler* function draws the ruler. The window origin is adjusted to begin a half inch from the left and top of the client area. JUSTIFY also leaves a quarter-inch margin at the right of the client area.

The text is a user-defined resource. It is in a one-line-per-paragraph format and is NULL-terminated. The bulk of the work involved with formatting this text is in the *Justify* function. JUSTIFY starts searching for blanks at the beginning of the text and uses *GetText-Extent* to measure each line. When the length of the line exceeds the width of the display area, JUSTIFY returns to the previous space and uses the line up to that point. Depending on the Alignment choice, the line is left aligned, right aligned, centered, or justified.

JUSTIFY isn't perfect. First, the justification logic falls apart when there are fewer than two words in each line. Even if we solve this problem (which isn't a difficult one), the program still won't work properly when a single word is too long to fit within the left and right margins. JUSTIFY also won't work well if no available fonts have the same aspect ratio as the display. Fonts designed for other aspect ratios are excluded in the *EnumAll Sizes* function. Because many of the drivers that allow the use of a "super-EGA" board in a 640-by-480 board don't also come with fonts appropriate for this aspect ratio, JUSTIFY won't show any font sizes when such a driver is installed. If we wanted, we could add more lengthy logic to JUSTIFY that would cause the program to search through the fonts for those that come closest to the aspect ratio of the display.

Of course, matters can become even more complex when you start working with programs that can use multiple fonts on the same line (as Windows WRITE can). But nobody ever claimed this stuff was easy. It's just easier than if you were doing all the work yourself.

Chapter 16

Using the Printer

The concept of device independence may have seemed all well and good in the past four chapters, when we were using the video display for text and graphics, but how well does the concept hold up for printers and plotters? In general, the news is good. Under Windows, printers and plotters have a device-independent graphics interface. You can forget about printer control sequences and communications protocols when programming for the printer. Retail Windows programs conspicuously lack the disks of specialized printer drivers that have characterized recent word-processing software and graphics programs for MS-DOS. When a retail Windows program includes printer drivers, they are usually enhanced versions of existing printer drivers.

From a Windows program, you can print text and graphics on paper using the same GDI functions that we've been using for the video display. Many of the issues of device independence that we've explored in the past four chapters—mostly related to the size and resolution of the display surface and its color capabilities—can be approached and resolved in the same way. Yet a printer or plotter is not simply a display that uses paper rather than a cathode ray tube. There are some very significant differences. For example, we have never had to consider the problem of a video display not being connected to the display adapter or of the display "running out of screen." But it is common for a printer to be off line or to run out of paper.

Nor have we worried about the video display adapter being incapable of performing certain graphics operations. Either the display adapter can handle graphics or it can't. And if it can't, then it can't be used with Windows at all. But some printers can't print graphics (although they can still be used with Windows), and plotters can do vector graphics but have a real problem with bit-block transfers.

Here are some other issues to consider:

- Printers are slower than video displays. Although we have on occasion tried to
 tune our programs for best performance, we haven't really worried about the time
 required for the video display to be refreshed. But nobody wants to wait for a
 printer to finish before getting back to work.
- Programs reuse the surface of the video display as they overwrite previous display output with new output. This can't be done on a printer. Instead, a printer must eject a completed page and go on to the next page.
- On the video display, different applications are windowed. On a printer, output from different applications must be separated into distinct documents or print jobs.

To add printer support to the rest of GDI, Windows includes only one new function, called *Escape*. Well, it's actually more than one. *Escape* has many subfunctions that are indicated by one of the *Escape* parameters. For example, the three most common *Escape* subfunctions are STARTDOC and ENDDOC (which begin and end a printing job) and NEWFRAME, which ends one page and goes on to the next.

PRINTING, SPOOLING, AND ESCAPE

When you use a printer in Windows, you're actually initiating a complex interaction involving the GDI library module, the printer device driver library module (which has a .DRV extension), and the Windows SPOOLER program, as well as some other modules that get into the act. Before we start programming for the printer, let's examine how this process works.

When an application program wants to begin using a printer, it first obtains a handle to the printer device context using CreateDC. This causes the printer device driver library module to be loaded into memory (if it's not present already) and to initialize itself. The program then calls the Escape subfunction named STARTDOC, which signals the beginning of a new document. The Escape function is handled by the GDI module. The GDI module calls the Control function (which is equivalent to Escape) in the printer device driver. The device driver performs some initialization and calls OpenJob, which is in the GDI module. The GDI module then attempts to load the Windows SPOOLER program into memory.

Following the STARTDOC *Escape* call, the program can make the appropriate GDI calls for the first page of the document. For example, if the program wants to draw an ellipse on the page, it calls *Ellipse*, just as it does when drawing an ellipse on the screen. The GDI module generally stores all these GDI calls in a disk-based metafile, which is located in the subdirectory indicated by the TEMP variable in the MS-DOS envionment. (If no TEMP variable exists, Windows uses the root directory of the first fixed disk on the system.) The file begins with the characters ~MF and has a .TMP extension.

When the application program is finished with the GDI calls that define the first page, the program calls the NEWFRAME subfunction of *Escape*. Now the real work begins. The printer driver must translate the various drawing commands stored in the metafile into output for the printer. The printer output required to define a page of graphics can be very large, particularly if the printer has no high-level page-composition language. For example, a 300dots-per-inch laser printer using 8½-by-11-inch paper might require more than a megabyte of data to define one page of graphics.

For this reason, printer drivers often implement a technique called "banding," which divides the page into smaller rectangles called bands. (We'll examine banding in detail later in this chapter.) The GDI module obtains the dimensions of each band from the printer driver. It then sets a clipping region equal to this band and calls the printer device driver Output function for each of the drawing functions contained in the metafile. This process is called "playing the metafile into the device driver." The GDI module must play the entire metafile into the device driver for each band that the device driver defines on the page. After the process is completed, the metafile can be deleted.

For each band, the device driver translates these drawing functions into the output necessary to realize them on the printer. The format of this output will be specific to the printer. For dot-matrix printers, it will be a collection of control sequences, including graphics sequences. (For some assistance with constructing this output, the printer driver can call various "helper" routines also located in the GDI module.) For laser printers with a high-level page-composition language (such as PostScript), the printer output will be in this language.

The printer driver uses the WriteSpool function to pass the printer output for each band to the GDI module, which then stores this printer output in a temporary file also located in the TEMP subdirectory. This file begins with the characters "SPL and has a .TMP extension. When the entire page is finished, the GDI module uses the SendMessage function to send a message to SPOOLER indicating that a new print job is ready. The application program then goes on to the next page. When the application is finished with all the pages it must print, it makes the ENDDOC Escape call to signal that the print job is completed. Figure 16-1 (on the following page) shows the interaction of the program, the GDI module, and the printer driver.

The SPOOLER.EXE program that comes with Windows is a print spooler that relieves application programs of some of the work involved with printing. The GDI module loads SPOOLER.EXE automatically when a program begins printing. The GDI module then creates the files that contain printer output. SPOOLER's job is to send these files out to the printer. SPOOLER is notified of a new print job by a message from the GDI module. It then begins reading the file and transferring it directly to the printer. To transfer the files, SPOOLER uses the various communications functions (*OpenComm*, *WriteComm*, and so forth included in the USER module) for the parallel or serial port that the printer is connected to. During the time that SPOOLER is writing the printer output to the output port, other Windows programs can function normally. When SPOOLER is done sending a file to a printer, it can delete the temporary file holding the output. This process is shown in Figure 16-2 (on the following page).

Most of this process is transparent to the application program. From the perspective of the program, "printing" occurs only during the time required for the GDI module to save all the printer output in disk files. After that, the program is freed up to do other things. The actual




Figure 16-1. The interaction of the application program, the GDI module, and the printer driver




Figure 16-2. The operation of the SPOOLER program

printing of the document becomes SPOOLER's reponsibility rather than the program's. A user can direct SPOOLER to pause print jobs, to change their priority, or to cancel print jobs. This arrangement allows programs to "print" faster than would be possible if they were printing in real time and had to wait for the printer to finish one page before proceeding to the next.

Although I've described how printing works in the general case, there are some variations on this theme. One is that SPOOLER doesn't have to be present in order for Windows programs to use the printer. Normally, the [windows] section of WIN.INI contains this line:

spooler=yes

But a user can change that to:

spooler=no

If this line is present, SPOOLER doesn't allow itself to be executed.

Why would a user not want SPOOLER to be loaded? Well, perhaps the user has a hardware or software print spooler that works faster than SPOOLER.EXE. Or perhaps the printer is on a network that has its own spooler. The general rule is that one spooler is faster than two. Removing the Windows SPOOLER program would speed up printing, because the printer output doesn't have to be stored on disk. It can go right out to the printer and be intercepted by the external hardware or software print spooler.

If SPOOLER can't be loaded, the GDI module doesn't store the printer output from the device driver in a file. Instead, GDI itself sends the output directly to the parallel or serial printer port. Unlike the printing done by SPOOLER, the printing done by GDI has the potential of holding up the operation of application programs (particularly the program doing the printing) until the printing is completed.

The possibility of SPOOLER.EXE being disengaged from the printing process is of concern to us because the GDI module treats printing a little differently if SPOOLER is not available. In short, GDI can't assume that another print spooler besides SPOOLER is present, and Windows won't allow itself to be effectively shut down while a program is printing in "real time" without SPOOLER helping out. The program that is printing must allow other programs a chance to run. This involves another *Escape* subfunction called SETABORTPROC, which I'll discuss later.

Here's another variation on the general theme. Normally, the GDI module stores all the functions necessary to define a page in a metafile and then plays this metafile into the printer driver once for each band defined by the driver. If the printer driver doesn't require banding, however, the metafile isn't created; GDI simply passes the drawing functions directly to the driver. In a further variation, it is also possible for an application to assume responsibility for dividing printer output into bands. This makes the printing code in the application program more complex, but it relieves the GDI module of creating the metafile. Once again, GDI simply passes the functions for each band to the printer driver.

Now perhaps you're starting to see how printing from a Windows program might involve a bit more overhead than that required for using the video display. Several problems can occur—particularly, for example, if the GDI module runs out of disk space while creating the metafile or the printer output files. You can either get very involved in reporting these problems to the user and attempting to do something about them, or you can remain relatively aloof.

We'll examine several different approaches to printing in the pages that follow. But first things first—let's begin by obtaining a printer device context.

THE PRINTER DEVICE CONTEXT

Just as you must obtain a handle to a device context before you paint on the video display, you must obtain a printer device context handle before printing. Once you have this handle (and have made the *Escape* calls necessary to announce your intention of creating a new document), you can use this printer device context handle the same way you use the video display device context handle—as the first parameter to the various GDI calls we've covered in the last four chapters.

In Chapter 12, you learned that you can get a handle to a device context for the entire video display by calling:

```
hDC = CreateDC ("DISPLAY", NULL, NULL, NULL) ;
```

You obtain a printer device context handle using this same function. However, for a printer device context, the first three parameters are not fixed. The general syntax of CreateDC is:

```
hDC = CreateDC (lpszDriverName, lpszDeviceName, lpszOutputPort, lpInitializationData);
```

Although *IpInitializationData* is generally set to NULL, the first three parameters must be far pointers to character strings that tell Windows the name of the printer driver, the name of the printer device, and the output port to which the device is connected. Before you can set these three parameters, you must do a little fishing in the WIN.INI file.

Getting the CreateDC Parameters

Printers are listed in two different sections of the WIN.INI file, reflecting the possibility that a system can have more than one printer attached to it. A single printer is listed in the *[windows]* section with the keyword *device*. The string that follows contains the device name, driver name, and output port required in the *CreateDC* call:

```
[windows]
[other lines]
device=IBM Graphics, IBMGRX, LPT1:
```

In this case, the device name is IBM Graphics, the driver name is IBMGRX, and the output port is LPT1. The printer listed in this section of WIN.INI is the most recent printer that the user has selected using the CONTROLEXE program supplied with Windows. This printer is chosen

from the dialog box invoked by the Printer option in the Setup menu. It can be considered the "current printer" or the "default printer." Most small Windows programs use this printer for printing.

Here is one way to write a function to obtain this string from WIN.INI, parse it into the three components, and call CreateDC to obtain a printer device context handle:

```
HDC GetPrinterDC ()

( char szPrinter [64] ;
 char *szDevice, *szDriver, *szOutput ;

GetProfileString ("windows", "device", "", szPrinter, 64) ;

if ((szDevice = strtok (szPrinter, ",")) &&
    (szDriver = strtok (NULL, ",")) &&
    (szOutput = strtok (NULL, ",")))

return CreateDC (szDriver, szDevice, szOutput, NULL) ;

return 0 ;
```

GetProfileString looks in the [windows] section for the keyword device and copies up to 64 characters following the equal sign into szPrinter. (The third parameter to GetProfileString is a default string if Windows can't find the [windows] section or the device keyword in WIN.INI.) The string is parsed using the normal C strtok function, which breaks a string into tokens. Note that I use only a comma to find the end of the szDevice string, because the device name can include imbedded blanks. Both a comma and space are used to separate the driver name and output port so that leading or trailing blanks are stripped from these strings. (Using strtok is not an entirely satisfactory method of parsing this string, because strtok doesn't take into account the multibyte character codes that can be used in versions of Windows for countries in the Far East. If this is of concern, you can write your own version of strtok that uses AnsiNext to advance through the string.)

The CreateDC function returns a 0 if the printer device context could not be created. This can occur if the string in WIN.INI is malformed, if Windows can't find the printer driver, or if the output port name is "none" (which means the printer is not connected to an output port). You can, however, obtain an information context for a printer connected to "none" by using CreateIC rather than CreateDC.

The [windows] section of WIN.INI lists only one printer. But multiple printers can be listed in the [devices] section of WIN.INI. A printer is listed in this section when a user chooses the Add New Printer option from the Installation menu of CONTROLEXE. The [devices] section looks something like this:

```
[devices]
IBM Graphics=IBMGRX,LPT1:
TTY=TTY,output.prn
HP 7470A=HP7470A,COM1:
Postscript/LaserWriter=PSCRIPT,COM2:
```

To the left of each equal sign is the device name; to the right is first the driver name and then the output port. Getting a device context handle using the printer specified in the [windows] section of WIN.INI is essentially the same as getting a device context handle using one of the printers from the [devices] section, except that the latter is more difficult because you have more than one choice.

Some larger Windows programs (for instance, Windows WRITE) include a File menu option called Change Printer, which invokes a dialog box that lists all the printers from the *[devices]* section with the port each printer is connected to. This option allows the user to select a printer other than the one listed in the *[windows]* section of WIN.INI. A program that includes this option must first call *GetProfileString* with a NULL second parameter:

On return, szAllDevices contains a list of the keywords (the device names) in the [devices] section. Each keyword is terminated by a NULL except for the final keyword, which is terminated by two NULLs. For the example list shown on the previous page, szAllDevices would contain (using C notation):

```
IBM Graphics\OTTY\OHP 7470A\OPostscript/LaserWriter\O\0
```

You can then present these names to the user. (We'll do this shortly in the DEVCAPS program.)

Let's assume that a user selects one of these devices and that you've set the pointer szDevice to the beginning of that device name in szAllDevices. You can then obtain the rest of the string (the driver name and output port) by calling GetProfileString again:

```
GetProfileString ("devices", szDevice, "", szPrinter, 64) ;
```

You need to parse the szPrinter string to extract the driver name and the output port name:

```
szDriver = strtok (szPrinter, ", ");
szOutput = strtok (NULL , ", ");
```

Now you have the szDevice, szDriver, and szOutput pointers necessary to call GreateDC or CreateIC.

The valid output ports on a particular system are listed in the *[ports]* section of WIN.INI. You don't need to access this section of WIN.INI to use the printer. You can assume that the user has identified a particular port for the printer using the Connections option on the Setup menu in CONTROLEXE; you can further assume that the user has properly defined the communications parameters for serial (COM) ports using the Communications Port option on the Setup menu.

The [ports] section often looks something like this:

```
[ports]
LPT1:=
LPT2:=
LPT3:=
COM1:=9600,n,8,1
COM2:=1200,n,8,1
output.prn=
```

The OUTPUT.PRN file (or any file with a .PRN extension) can be listed here to direct printer output to a file. This filename can appear as the output port for a printer in the [windows] section or [devices] section of WIN.INI.

The Revised DEVCAPS Program

The original DEVCAPS program in Chapter 12 displays all the information available from the GetDeviceCaps function for the video display and the current printer. The new version, shown in Figure 16-3, displays a menu of all the printers from the [devices] section of WIN.INI and lets you choose one. In addition to the DEVCAPS files shown here, you'll also need the DEVCAPS2.C file from Chapter 12 (Figure 12-1) and the WINUNDOC.H file from Chapter 11 (Figure 11-7).

```
/* DEVCAPS.C -- Displays Device Capability Information (Version 2) */

#include <windows.h>
#include <stdio.h>
#include <string.h>
#include "winundoc.h"
#include "devcaps.h"

void DoBasicInfo (HDC, HDC, short, short) ; /* in DEVCAPS2.C */
void DoOtherInfo (HDC, HDC, short, short) ;
void DoBitCodedCaps (HDC, HDC, short, short) ;
long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG) ;
```

Figure 16-3. The DEVCAPS program

```
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
     HANDLE hInstance, hPrevInstance;
     LPSTR
                 lpszCmdLine ;
     int
                nCmdShow ;
     static char szAppName [] = "DevCaps" ;
                 hWnd ;
     MSG
                 msg ;
     WNDCLASS
                 wndclass ;
     if (!hPrevInstance)
          wndclass.hInstance = hInstance;
wndclass.hIcon = LoadIcon (NULL, IDI APPLICATION);
wndclass.hCursor = LoadCursor (NULL, IDC ARROW);
                                 = LoadCursor (NULL, IDC ARROW) ;
          wndclass.hbrBackground = GetStockObject (WHITE BRUSH) ;
          wndclass.lpszMenuName = szAppName ;
          wndclass.lpszClassName = szAppName ;
          if (!RegisterClass (&wndclass))
               return FALSE :
     hWnd = CreateWindow (szAppName, NULL,
                          WS OVERLAPPEDWINDOW,
                          CW USEDEFAULT, 0,
                          CW USEDEFAULT, 0,
                         NULL, NULL, hinstance, NULL) ;
     ShowWindow (hWnd, nCmdShow) ;
     UpdateWindow (hWnd) ;
     while (GetMessage (&msg, NULL, 0, 0))
          TranslateMessage (&msg) ;
          DispatchMessage (&msq) ;
     return msg.wParam ;
void DoEscSupport (hDC, hIC, xChar, yChar)
     HDC hDC, hIC;
     short xChar, yChar;
     static struct
          char *szEscCode ;
          short nEscCode :
          esc [] =
          "NEWFRAME",
                              NEWFRAME,
          "ABORTDOC",
                               ABORTDOC,
          "NEXTBAND",
                              NEXTBAND,
          "SETCOLORTABLE",
                             SETCOLORTABLE,
          "GETCOLORTABLE",
                               GETCOLORTABLE,
          "FLUSHOUTPUT",
                               FLUSHOUTPUT,
```

Figure 16-3. Continued

```
"DRAFTMODE",
                               DRAFTMODE,
                               OUERYESCSUPPORT.
         "QUERYESCSUPPORT",
         "SETABORTPROC",
                               SETABORTPROC,
         "STARTDOC",
                               STARTDOC.
         "ENDDOC"
                               ENDDOC,
                             GETPHYSPAGESIZE,
         "GETPHYSPAGESIZE",
         "GETPRINTINGOFFSET", GETPRINTINGOFFSET, "GETSCALINGFACTOR", GETSCALINGFACTOR);
    static char *szYesNo [] = ( "Yes", "No" ) ;
    char
           szBuffer [32] ;
                pt ;
    POINT
                n, nReturn :
    short
    Textout (hDC, xChar, yChar, "Escape Support", 14) ;
    for (n = 0 ; n < sizeof esc / sizeof esc [0] ; n++)
         nReturn = Escape (hIC, QUERYESCSUPPORT, 1,
                                   (LPSTR) & esc[n].nEscCode, NULL) ;
         TextOut (hDC, 6 * xChar, (n + 3) * yChar, szBuffer, sprintf (szBuffer, "%-24s %3s", esc[n].szEscCode,
                                   szYesNo [nReturn > 0 ? 0 : 1])) ;
         if (nReturn > 0 && esc[n].nEscCode >= GETPHYSPAGESIZE
                          && esc[n].nEscCode <= GETSCALINGFACTOR)
               Escape (hIC, esc[n].nEscCode, 0, NULL, (LPSTR) &pt) ;
              long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
    HWND
                   hWnd ;
     unsigned
                   iMessage ;
     WORD
                   wParam ;
    LONG
                   1Param ;
    static char
                   szAllDevices [4096], szDevice [32], szDriver [16],
                   szDriverFile [16], szWindowText [64] ;
     static HANDLE hLibrary ;
    static short n, xChar, yChar, nCurrentDevice = IDM_SCREEN,
                                    nCurrentInfo = IDM BASIC ;
    char
                   *szOutput, *szPtr ;
     FARPROC
                   lpfnDM ;
    HDC
                   hDC, hIC ;
    HMENU
                   hMenu ;
     PAINTSTRUCT
                   ps ;
    TEXTMETRIC
                   tm :
    switch (iMessage)
          case WM CREATE:
               hDC = GetDC (hWnd) ;
               GetTextMetrics (hDC, &tm) ;
               xChar = tm.tmAveCharWidth ;
               yChar = tm.tmHeight + tm.tmExternalLeading ;
               ReleaseDC (hWnd, hDC) ;
```

Figure 16-3. Continued

```
lParam = NULL :
                                         /* fall through */
case WM WININICHANGE:
     if (lParam != NULL && lstrcmp ((LPSTR) lParam, "devices") != 0)
          break ;
     hMenu = GetSubMenu (GetMenu (hWnd), 0) ;
     while (GetMenuItemCount (hMenu) > 1)
          ChangeMenu (hMenu, 1, NULL, 0, MF DELETE | MF BYPOSITION) ;
     n = IDM_SCREEN + 1 ;
     szPtr = szAllDevices ;
     while (*szPtr)
          ChangeMenu (hMenu, O, szPtr, n, MF_APPEND
                         (n % 16 ? 0 : MF MENUBARBREAK)) ;
          n++ ;
          szPtr += strlen (szPtr) + 1 ;
     ChangeMenu (hMenu, 0, NULL, 0, MF APPEND);
ChangeMenu (hMenu, 0, "Device Mode", IDM_DEVMODE, MF_APPEND);
     wParam = IDM SCREEN ;
                                         /* fall through */
case WM COMMAND:
     hMenu = GetMenu (hWnd) ;
     if (wParam < IDM DEVMODE)
                                         /* IDM SCREEN & Printers */
          CheckMenuItem (hMenu, nCurrentDevice, MF UNCHECKED) ;
          nCurrentDevice = wParam ;
          CheckMenuItem (hMenu, nCurrentDevice, MF CHECKED) ;
     else if (wParam == IDM DEVMODE)
          GetMenuString (hMenu, nCurrentDevice, szDevice, sizeof szDevice, MF_BYCOMMAND) ;
          GetProfileString ("devices", szDevice, ""
                              szDriver, sizeof szDriver) ;
          szOutput = strtok (szDriver, ", ") ;
          strcat (strcpy (szDriverFile, szDriver), ".DRV") ;
          if (hLibrary >= 32)
               FreeLibrary (hLibrary) ;
          hLibrary = LoadLibrary (szDriverFile) ;
          if (hLibrary >= 32)
               lpfnDM = GetProcAddress (hLibrary, "DEVICEMODE") ;
               (*lpfnDM) (hWnd, hLibrary, (LPSTR) szDevice,
                                           (LPSTR) szOutput) ;
    else
                                        /* info menu items */
          CheckMenuItem (hMenu, nCurrentInfo, MF UNCHECKED) ;
```

Figure 16-3. Continued

```
nCurrentInfo = wParam ;
           CheckMenuItem (hMenu, nCurrentInfo, MF CHECKED) ;
     InvalidateRect (hWnd, NULL, TRUE) ;
     break ;
case WM INITMENUPOPUP:
     if (lParam == 0)
           EnableMenuItem (GetMenu (hWnd), IDM DEVMODE,
                nCurrentDevice == IDM SCREEN ?
                     MF GRAYED : MF ENABLED) ;
     break :
case WM PAINT:
     strcpy (szWindowText, "Device Capabilities: ") ;
     if (nCurrentDevice == IDM SCREEN)
     strcpy (szDriver, "DISPLAY") ;
     strcat (szWindowText, szDriver) ;
hIC = CreateIC (szDriver, NULL, NULL, NULL) ;
else
     hMenu = GetMenu (hWnd) ;
     GetMenuString (hMenu, nCurrentDevice, szDevice,
     sizeof szDevice, MF_BYCOMMAND) ;
GetProfileString ("devices", szDevice, "",
     szDriver, 10) ;
szOutput = strtok (szDriver, ", ") ;
     strcat (szWindowText, szDevice) ;
     hIC = CreateIC (szDriver, szDevice, szOutput, NULL) ;
SetWindowText (hWnd, szWindowText) ;
hDC = BeginPaint (hWnd, &ps) ;
if (hIC)
      switch (nCurrentInfo)
           case IDM BASIC:
                 DoBasicInfo (hDC, hIC, xChar, yChar) ;
                 break ;
           case IDM OTHER:
                 DoOtherInfo (hDC, hIC, xChar, yChar) ;
                 break ;
           case IDM CURVE:
           case IDM LINE:
           case IDM POLY:
case IDM TEXT:
                 DoBItCodedCaps (hDC, hIC, xChar, yChar, nCurrentInfo - IDM_CURVE) ;
                 break ;
           case IDM ESC:
                 DoEscSupport (hDC, hIC, xChar, yChar) ;
```

Figure 16-3. Continued

```
break;

DeleteDC (hIC);

EndPaint (hWnd, &ps);
break;

case WM_DESTROY:
    if (hLibrary >= 32)
        FreeLibrary (hLibrary);

PostQuitMessage (0);
break;

default:
    return DefWindowProc (hWnd, iMessage, wParam, lParam);

return OL;
}

return OL;
}
```

```
#define IDM_DEVMODE 0x100

#define IDM_BASIC 0x101
#define IDM_OTHER 0x102
#define IDM_CURVE 0x103
#define IDM_LINE 0x104
#define IDM_POLY 0x105
#define IDM_TEXT 0x106
#define IDM_TEXT 0x106
#define IDM_ESC 0x107
```

```
#include "devcaps.h"
DevCaps MENU
     BEGIN
           POPUP "&Device"
                BEGIN
                       MENUITEM "&Screen",
                                                                  IDM SCREEN, CHECKED
                 END
           POPUP "&Capabilities"
                 BEGIN
                       MENUITEM "&Basic Information",
                                                                  IDM BASIC, CHECKED
                       MENUITEM "&Other Information",
MENUITEM "&Curve Capabilities",
                                                                 IDM OTHER
                                                                 IDM CURVE
                       MENUITEM "&Line Capabilities", IDM POLY MENUITEM "&Polygonal Capabilities", IDM TEXT
                       MENUITEM SEPARATOR
                       MENUITEM "&Escape Support",
                                                                 IDM ESC
                 END
     END
```

Figure 16-3. Continued

NAME DEVCAPS 'Displays Device Capability Info (C) Charles Petzold, 1987' DESCRIPTION 'WINSTUB. EXE' STUB MOVEABLE CODE MOVEABLE MULTIPLE DATA HEAPSIZE 1024 STACKSIZE 4096 WndProc EXPORTS

Because DEVCAPS obtains only an information context for the printer, you can select printers from DEVCAPS's menu even though they may have an output port of "none." If you want to compare the capabilities of different printers, you can first use the CONTROL program to add various printer drivers to WIN.INI. Select the Add New Printer option from the Installation menu and have a disk of printer drivers ready.

The new version of DEVCAPS has an additional option on the Capabilities menu called Escape Support, which lets you see which of the more common *Escape* subfunctions are supported by the device driver. This information will become more meaningful to you a little later in this chapter, when we discuss the *Escape* function and its subfunctions.

The DeviceMode Call

The Device menu of the new DEVCAPS program includes an option called Device Mode. To use it, first select a printer from the Device menu, and then select Device Mode: Up pops a dialog box. Where did the dialog box come from? It is invoked by the printer driver, and—at the very least—it requests that you make a choice of paper size. Most printer drivers also give you a choice of "portrait" or "landscape" mode. In portrait mode (often the default), the short side of the paper is the top; in landscape mode, the long side is the top. If you change this mode, the change is reflected in the information the DEVCAPS program obtains from the GetDeviceCaps function: The horizontal size and resolution are switched with the vertical size and resolution. Device Mode dialog boxes for color plotters can be quite extensive, requesting the colors of the pens installed in the plotter and the type of paper (or transparencies) being used.

All printer drivers contain an exported function called *DeviceMode* that invokes this dialog box and saves the information that the user enters. Some printer drivers store this information in their own section of the WIN.INI file, and some don't. Those that store the information have access to it during the next Windows session.

Windows programs that allow the user a choice of printers generally call the DeviceMode function of the printer driver so that the user can make changes in preparation for printing. Calling this function from a program requires a technique that we'll learn more about in Chapter 18. Here's how DEVCAPS does it. The program first obtains the name of the printer currently selected in the Device menu and saves it in a character array named szDevice:

```
GetMenuString (hMenu, nCurrentDevice, szDevice,
sizeof szDevice, MF_BYCOMMAND);
```

Then it obtains the driver name and output port of this device using GetProfileString. This information is stored in szDriver:

The output port is separated from the szDriver string using strtok, and the pointer is saved in szOutput:

```
szOutput = strtok (szDriver, ", ") ;
```

The szDriver string contains the name of the driver, which is the driver's filename without the .DRV extension. This statement creates the full name of the driver file and saves it in szDriverFile:

```
strcat (strcpy (szDriverFile, szDriver), ".DRV");
```

This driver file is a dynamic link library module. (Library modules are the subject of Chapter 18.) We can obtain a handle to this module (which is actually the instance handle of the module) by calling *LoadLibrary*. If *LoadLibrary* returns a value greater than or equal to 32, the function was successful. Otherwise, the return value indicates an MS-DOS error code.

The library can be freed by a call to *FreeLibrary*. If no other program is using this library, then it can be deleted from memory. DEVCAPS holds the library handle (or whatever was returned from *LoadLibrary*) in a static variable, so before trying to load a new library, it first frees the old one if the handle was valid:

```
if (hLibrary >= 32)
    FreeLibrary (hLibrary);
hLibrary = LoadLibrary (szDriverFile);
```

Before proceeding, the program checks to see if this new handle is valid:

```
if (hLibrary >= 32)
```

It then calls GetProcAddress to obtain the address of the DeviceMode function:

```
lpfnDM = GetProcAddress (hLibrary, "DEVICEMODE") ;
```

The *DeviceMode* function can be called indirectly by prefacing it with an asterisk. The function is passed the window handle, library module handle, device name, and output port:

```
(*lpfnDM) (hWnd, hLibrary, (LPSTR) szDevice, (LPSTR) szOutput) ;
```

This invokes the dialog box. Note that you must explicitly cast the strings into far pointers, because this function has no template in WINDOWS.H or anywhere else.

The currently loaded driver file is freed when the program terminates:

```
case WM_DESTROY:
    if (hLibrary >= 32)
        FreeLibrary (hLibrary) ;
    lother program lines/
```

The LoadLibrary call increments the library module's "reference count" (a number Windows maintains that indicates the number of programs using a module), and the FreeLibrary call decrements it. The library can be freed from memory when the reference count is 0. Calls to CreateDC and CreateIC for a printer driver also increment the reference count, and DeleteDC decrements it.

Checking for BitBIt Capability

You can use the GetDeviceCaps function to obtain the size and resolution of the printable area of the page. (In most cases, this area won't be the same as the entire size of the paper.) You can also obtain the relative pixel width and height, if you want to do your own scaling.

You can obtain another important printer characteristic from the RC_BITBLT bit of the value returned from *GetDeviceCaps* with a parameter of RASTERCAPS ("raster capabilities"). This bit indicates whether the device is capable of bit-block transfers. Most dot-matrix and laser printers are capable of bit-block transfers, but most plotters are not. Devices that can't handle bit-block transfers do not support the following GDI functions: *CreateCompatibleDC*, *CreateCompatibleBitmap*, *PatBlt*, *BitBlt*, *StretchBlt*, *GrayString*, *DrawIcon*, *SetPixel*, *Get-Pixel*, *FloodFill*, *FillRgn*, *FrameRgn*, *InvertRgn*, *PaintRgn*, *FillRect*, *FrameRect*, and *Invert-Rect*. This is the single most important distinction between using GDI calls on a video display and using them on a printer. We'll test printers for RC_BITBLT capability in the WINPRTSC program shown later in this chapter.

PRINTING FUNDAMENTALS

We're now ready to print, and we're going to start as simply as possible. In fact, our first two printing programs will be so simple that they won't work unless the SPOOLER program gets loaded when printing begins. SPOOLER doesn't get loaded if a user specifies *spooler=no* in the WIN.INI file or if Windows can't find the SPOOLER.EXE file.

The Escape Function

The Windows GDI module includes only one function—*Escape*—to support the additional requirements of printers. The name of this function implies that it is ignored by the GDI module and that it goes straight to the printer driver. In some cases, this is true, but often GDI also does some work during *Escape* calls.

The general syntax of Escape is:

```
nResult = Escape (hPrinterDC, nEscapeCode, nCount,
lpsDataIn, lpsDataOut);
```

The *nEscapeCode* parameter is a subfunction code that is specified using an identifier defined in WINDOWS.H. The last three parameters depend on the subfunction. Although the last two parameters are declared as far pointers to character strings, they are sometimes far pointers to structures. To cast the pointers into far pointers to strings, use (LPSTR).

Not all *Escape* subfunctions are implemented in all device drivers. In fact, *Escape* has been designed to be open-ended so that manufacturers of display devices can define their own *Escape* subfunctions to access certain unique facilities of the devices. The following *Escape* subfunctions are the ones I discuss in this chapter. They are implemented in all printer drivers:

nEscapeCode	Description	
STARTDOC	Starts a document	
ENDDOC	Ends a document	
SETABORTPROC	Sets a pointer to the "abort function"	
NEWFRAME	Ends the current page	
NEXTBAND	Gets rectangle coordinates for the next band	
ABORTDOC	Aborts printing of a document	
GETPHYSPAGESIZE	Gets the physical size of the paper	
QUERYESCSUPPORT	Finds out if the driver supports an Escape code	

DEVCAPS used the QUERYESCSUPPORT subfunction to list supported *Escape* functions. The GETPHYSPAGESIZE subfunction returns the size of the paper, which will generally be larger than the printable area obtained from *GetDeviceCaps*. We'll use other subfunctions in programs later in this chapter. *Escape* always returns a 0 if the subfunction is not implemented and a negative value if an error occurs. A positive value indicates success.

The FORMFEED Program

Our first printing program does nothing but cause a printer formfeed to eject the page. The FORMFEED program, shown in Figure 16-4, demonstrates the absolute minimum requirements for printing.

```
formfeed.obj: formfeed.c
cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp formfeed.c

formfeed.exe: formfeed.obj formfeed.def
link4 formfeed, /align:16, /map, slibw, formfeed
```

Figure 16-4. The FORMFEED program

Figure 16-4. Continued

```
/* FORMFEED.C -- Advances printer to next page */
#include <windows.h>
#include <string.h>
HDC GetPrinterDC (void) ;
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
                 hInstance, hPrevInstance;
     LPSTR
                   lpszCmdLine :
     int
                   nCmdShow ;
     static char szMsg [] = "FormFeed" ;
                  hPrintDC :
     if (hPrintDC = GetPrinterDC ())
           if (Escape (hPrintDC, STARTDOC, sizeof szMsg - 1, szMsg, NULL) > 0)
if (Escape (hPrintDC, NEWFRAME, 0, NULL, NULL) > 0)
Escape (hPrintDC, ENDDOC, 0, NULL, NULL) ;
           DeleteDC (hPrintDC) ;
     return FALSE ;
HDC GetPrinterDC ()
     char szPrinter [64] ;
     char *szDevice, *szDriver, *szOutput;
     GetProfileString ("windows", "device", "", szPrinter, 64) ;
     if ((szDevice = strtok (szPrinter, "," )) &&
                                            ", ")) &&
          (szDriver = strtok (NULL,
          (szOutput = strtok (NULL,
                return CreateDC (szDriver, szDevice, szOutput, NULL) ;
     return 0 ;
```

```
NAME FORMFEED
DESCRIPTION 'Printer Form Feed Program (C) Charles Petzold, 1987'
STUB 'WINSTUB.EXE'
CODE MOVEABLE
DATA MOVEABLE MULTIPLE
HEAPSIZE 1024
STACKSIZE 4096
```

FORMFEED includes the *GetPrinterDC* function shown earlier. Other than obtaining the printer device context (and later deleting it), the program makes only three *Escape* calls. The first uses the STARTDOC subfunction to start a new document. It tests the return value from *Escape* and proceeds only if the value is positive:

```
if (Escape (hPrintDC, STARTDOC, sizeof szMsg - 1, szMsg, NULL) > 0)
```

The fourth parameter is a far pointer to the string that SPOOLER will display in its client area to identify the document being printed. Generally, this string includes the name of the application doing the printing and the file being printed. In this case, it's simply the name "FormFeed." The third parameter is the length of this string.

If STARTDOC is successful (indicated by a positive return value), then FORMFEED calls the NEWFRAME *Escape* subfunction, which advances the printer to a new page. Once again, the return value is tested:

```
if (Escape (hPrintDC, NEWFRAME, 0, NULL, NULL) > 0)
```

The third, fourth, and fifth parameters are not used in this Escape call.

Finally, if everything has proceeded without error to this point, the document is ended:

```
Escape (hPrintDC, ENDDOC, 0, NULL, NULL) ;
```

Again, the last three parameters are not used. Note that the ENDDOC *Escape* function is called only if no printing errors have been reported. If one of the other *Escape* functions returns an error code, then GDI has already aborted the document. If the printer is not currently printing, such a error code often results in the printer being reset.

Simply testing the return values from the *Escape* calls is the easiest way to check for errors. However, WINDOWS.H includes identifiers for the error codes, which you can use if you want to report the particular error to the user. For example, the NEWFRAME *Escape* call could return the SP_OUTOFDISK error (-4), indicating insufficient disk space for GDI to store the printer output necessary to trigger the printer to do a formfeed. For most printers, this occurrence is extremely unlikely. For your own amusement, however, you might try specifying the *PostScript* printer driver as your current printer, with the output port OUTPUT.PRN. Run FORMFEED and check the size of the file.

The NEWFRAME Escape call will return an SP_APPABORT error (-2) if the SPOOLER is not loaded when printing begins. The SP_APPABORT error code is defined as indicating that the program's abort function returned 0. Well, FORMFEED doesn't even have an abort function, and the program won't work unless SPOOLER.EXE is loaded.

If you've ever written a simple formfeed program for MS-DOS, you know that ASCII number 12 does a formfeed for most printers. Why not simply write an ASCII number 12 to the printer through the IBM PC's BIOS functions? Well, nothing prevents you from doing this. You first have to determine the parallel port or the serial port the printer is attached to—that's available from WIN.INI. You then have to determine if another program (SPOOLER, for instance) is currently using the printer. You don't want the formfeed to be output in the middle of a document, do you? Finally, you have to determine if ASCII number 12 is a formfeed character for the connected printer. It's not universal, you know. In fact, the formfeed command in PostScript isn't a 12; it's the word eject. Stick with the Windows functions for printing.

PRINTING GRAPHICS AND TEXT

Printing from a Windows program usually involves more overhead than shown in the FORMFEED program, as well as some GDI calls to actually print something. Let's write a program that prints one page of text and graphics. We'll start with the methodology shown in the FORMFEED program and then add some enhancements. We'll be looking at four versions of this program called PRINT1, PRINT2, PRINT3, and PRINT4. To avoid a lot of duplicated source code, each of these programs will use functions contained in the PRINT.C file, which is shown in Figure 16-5.

```
/* PRINT.C -- Common Routines for Print1, Print2, Print3, and Print4 */
#include <windows.h>
#include <string.h>
long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG) ;
BOOL PrintMyPage (HWND) ;
extern HANDLE hinst ;
extern char szAppName []
extern char szCaption [] ;
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
     HANDLE hInstance, hPrevInstance;
     LPSTR
              lpszCmdLine ;
     int
              nCmdShow :
     HWND
              hWnd ;
     MSG
              msq ;
     WNDCLASS wndclass ;
     if (!hPrevInstance)
          wndclass.style
                                  = CS HREDRAW | CS VREDRAW;
          wndclass.lpfnWndProc = WndProc ;
          wndclass.cbClsExtra = 0 ;
          wndclass.cbWndExtra = 0;
wndclass.hInstance = hInstance;
          wndclass.hCon = LoadCon (NULL, IDI APPLICATION);
wndclass.hCursor = LoadCursor (NULL, IDC_ARROW);
          wndclass.hbrBackground = GetStockObject (WHITE BRUSH)
          wndclass.lpszMenuName = NULL ;
          wndclass.lpszClassName = szAppName ;
          if (!RegisterClass (&wndclass))
               return FALSE ;
     hInst = hInstance ;
     hWnd = CreateWindow (szAppName, szCaption,
                           WS OVERLAPPEDWINDOW,
                          CW USEDEFAULT, 0,
                           CW USEDEFAULT, 0,
                           NULL, NULL, hInstance, NULL) ;
```

Figure 16-5. The PRINT: Gile of the PRINT1, PRINT2, PRINT3, and PRINT4 programs

Figure 16-5. Continued

```
ShowWindow (hWnd, nCmdShow) ;
     UpdateWindow (hWnd) ;
     while (GetMessage (&msg, NULL, 0, 0))
           TranslateMessage (&msg) ;
           DispatchMessage (&msg) ;
     return msg.wParam ;
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
     HWND
              hWnd ;
     unsigned iMessage ;
     WORD
             wParam ;
     LONG
               lParam :
     HMENU hMenu ;
     switch (iMessage)
           case WM CREATE:
                hMenu = GetSystemMenu (hWnd, FALSE);
                ChangeMenu (hMenu, 0, NULL, 0, MF APPEND | MF SEPARATOR);
ChangeMenu (hMenu, 0, "&Print", 1, MF APPEND | MF STRING);
                break :
           case WM_SYSCOMMAND:
                if (wParam == 1)
                      if (PrintMyPage (hWnd))
    MessageBox (hWnd, "Could not print page",
                                 szappName, MB OK | MB ICONEXCLAMATION) ;
                      break :
                return DefWindowProc (hWnd, iMessage, wParam, 1Param) ;
           case WM DESTROY:
                PostQuitMessage (0) ;
                break ;
           default:
                return DefWindowProc (hWnd, iMessage, wParam, 1Param) ;
      return OL ;
HDC GetPrinterDC ()
     char szPrinter [64] ;
     char *szDevice, *szDriver, *szOutput ;
     GetProfileString ("windows", "device", "", szPrinter, 64) ;
      if ((szDevice = strtok (szPrinter, "," )) &&
                                           ", "))) 56
          (szDriver = strtok (NULL,
          (szOutput = strtok (NULL,
                return CreateDC (szDriver, szDevice, szOutput, NULL) ;
     return 0 ;
      )
```

Figure 16-5. Continued

```
void PageGDICalls (hPrnDC, xPage, yPage)
    HDC hPrnDC;
short xPage, yPage;
     static char szTextStr [] = "Hello Printer!" ;
     DWORD dwExtent;
POINT ptExtent;
                  ptExtent ;
     Rectangle (hPrnDC, 0, 0, xPage, yPage) ;
     MoveTo (hPrnDC, 0, 0) ;
     LineTo (hPrnDC, xPage, yPage) ;
     MoveTo (hPrnDC, xPage, 0) ;
LineTo (hPrnDC, 0, yPage) ;
     SaveDC (hPrnDC) ;
     SetMapMode (hPrnDC, MM ISOTROPIC)
     SetWindowExt (hPrnDC, 1000, 1000);
SetViewportExt (hPrnDC, xPage / 2, -yPage / 2);
SetViewportOrg (hPrnDC, xPage / 2, yPage / 2);
     Ellipse (hPrnDC, -500, 500, 500, -500);
     dwExtent = GetTextExtent (hPrnDC, szTextStr, sizeof szTextStr - 1) ;
      ptExtent = MAKEPOINT (dwExtent) ;
      TextOut (hPrnDC, -ptExtent.x / 2, ptExtent.y / 2, szTextStr,
                                                            sizeof szTextStr - 1) ;
      RestoreDC (hPrnDC, -1) ;
```

PRINT.C contains the functions WinMain, WndProc, and GetPrinterDC and a function called PageGDICalls, which expects to receive a handle to the printer device context and two variables containing the width and height of the printer page. PageGDICalls draws a rectangle that encompasses the entire page, two lines between opposite corners of the page, a circle in the middle of the page (its diameter half the lesser of the printer height and width), and the text "Hello Printer!" in the center of this ellipse.

During processing of the WM_CREATE message, WndProc adds a Print option to the system menu. Selecting this option causes a call to PrintMyPage, a function that we'll enhance over the course of the four versions of the program. PrintMyPage returns TRUE (nonzero) if it encounters an error during printing and FALSE otherwise. If PrintMyPage returns TRUE, WndProc displays a message box to inform you of the error.

Bare-Bones Printing

PRINT1, the first version of the printing program, is shown in Figure 16-6 (beginning on the following page). After compiling PRINT1, you can execute it and then select Print from the system menu. If your WIN.INI file has the line *spooler=yes* and if Windows can find SPOOLER.EXE, you should see the SPOOLER icon appear at the bottom of the screen. If the

PRINT1.C

TEMP variable in your MS-DOS environment indicates a fixed disk (or if you have no TEMP variable), then you should see some disk activity as the GDI module saves the printer output to a temporary file. You won't be able to do anything in Windows during this time. After PRINT1 has finished, SPOOLER should display the text "Print1: Printing" in its client area and begin sending the disk file out to the printer. You'll be able to work normally in Windows again.

```
print.obj : print.c
     cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp print.c

printl.obj : printl.c
     cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp printl.c

printl.exe : print.obj printl.obj printl.def
     link4 printl print, /align:16, /map, slibw, printl
```

```
/* PRINT1.C -- Bare Bones Printing */
#include <windows.h>
                                        /* in PRINT.C */
HDC GetPrinterDC (void) ;
void PageGDICalls (HDC, short, short) ;
HANDLE hInst ;
char szAppName [] = "Printl" ;
char szCaption [] = "Print Program 1" ;
BOOL PrintMyPage (hWnd)
                hWnd ;
    HWND
    static char szMessage [] = "Printl: Printing" ;
     BOOL bError = FALSE ;
HDC hPrnDC ;
    short xPage, yPage ;
    if (NULL == (hPrnDC = GetPrinterDC ()))
         return TRUE ;
    xPage = GetDeviceCaps (hPrnDC, HORZRES) ;
    yPage = GetDeviceCaps (hPrnDC, VERTRES) ;
     if (Escape (hPrnDC, STARTDOC, sizeof szMessage - 1, szMessage, NULL) > 0)
          PageGDICalls (hPrnDC, xPage, yPage) ;
          if (Escape (hPrnDC, NEWFRAME, 0, NULL, NULL) > 0)
               Escape (hPrnDC, ENDDOC, 0, NULL, NULL) ;
          else
               bError = TRUE ;
     else
          bError = TRUE ;
```

Figure 16-6. The PRINT1 program

Figure 16-6. Continued

```
DeleteDC (hPrnDC) ;
return bError ;
)
```

```
NAME
               PRINT1
DESCRIPTION
               'Printing Program No. 1 (C) Charles Petzold, 1987'
STUB
               'WINSTUB.EXE'
CODE
               MOVEABLE
DATA
               MOVEABLE MULTIPLE
HEAPSIZE
               1024
STACKSIZE
               4096
EXPORTS
               WndProc
```

Let's look at the code in PRINTI.C. If *PrintMyPage* can't obtain a device context handle for the printer, it returns a TRUE value, and *WndProc* displays the message box indicating an error. If the function succeeds in obtaining the device context handle, it then determines the horizontal and vertical size of the page in pixels by calling *GetDeviceCaps*.

```
xPage = GetDeviceCaps (hPrnDC, HORZRES) ;
yPage = GetDeviceCaps (hPrnDC, VERTRES) ;
```

This is *not* the full size of the paper but rather its printable area. After that call, the code in PRINT1's *PrintMyPage* function is structurally the same as the code in FORMFEED, except that PRINT1 calls *PageGDICalls* between the STARTDOC and NEWFRAME *Escape* calls. Only if both the STARTDOC and NEWFRAME calls are successful does PRINT1 call ENDDOC *Escape*.

Like FORMFEED, PRINT1 won't work if SPOOLER isn't loaded, a fact that the NEWFRAME Escape call will indicate by returning an SP_APPABORT error (equal to -2). If Windows allowed PRINT1 or a similar program to print without SPOOLER loaded, the user would be unable to do anything else during the entire time the document was printing. With some dot-matrix printers, the time required to print a full page of graphics can be considerable. Not being able to print without SPOOLER loaded is a problem, however. Let's fix it.

Setting an Abort Function

Although the enhancement we'll add in the PRINT2 version of our program solves the problem of printing without SPOOLER, the real purpose of that enhancement is to prevent problems related to disk space. If you try to run PRINT1 when the drive containing the TEMP subdirectory lacks sufficient space to store the full page of graphics output, the NEWFRAME Escape call will return an SP_OUTOFDISK error. This error could result from the presence in the TEMP subdirectory of other temporary print files created by GDI for printing. If SPOOLER were given enough time to send these files to the printer, then the program currently

printing could continue. It wouldn't be necessary for Windows to return an SP_OUTOFDISK error to the program. However, SPOOLER cannot transfer these files to the printer because—like all other Windows programs—it isn't receiving messages during the time your program is printing.

This problem is solved with something called an "abort function" (also called an "abort procedure"). The abort function is a small exported function in your program. You give Windows the address of this function using the *Escape* SETABORTPROC subfunction. If GDI runs out of disk space while creating temporary print files, and if enough space could eventually become available by having SPOOLER send existing print files to the printer, then the GDI module calls the program's abort function. The abort function then effectively yields control to allow SPOOLER to print.

Let's look first at what's required to add an abort function to the printing logic and then examine some of the ramifications. The abort function is commonly called *AbortProc*, and it takes the following form:

```
BOOL FAR PASCAL AbortProc (hPrnDC, nCode)
HDC hPrnDC;
short nCode;
(
[other program lines]
```

The function must be listed in the EXPORTS section of your module definition file. Before printing, you must obtain a pointer to this function from *MakeProcInstance*.

You then set the abort function using the *Escape* SETABORTPROC subfunction. The *lpsDataIn* parameter is the pointer returned from *MakeProcInstance*.

```
Escape (hPrnDC, SETABORTPROC, 0, (LPSTR) lpfnAbortProc, NULL) ;
```

You make this call before the STARTDOC Escape call. You don't need to "unset" the abort function after you finish printing.

While processing the NEWFRAME *Escape* call (that is, while playing the metafile into the device driver and creating the temporary printer output files), GDI frequently calls the abort function. The *hPrnDC* parameter is the printer device context handle. The *nCode* parameter is 0 if all is going well and SP_OUTOFDISK if the GDI module has run out of disk space because of the temporary printer output files.

AbortProc must return a TRUE (nonzero) value if the print job is to be continued and a FALSE (0) value if the print job is to be aborted. If AbortProc receives an nCode parameter of SP_OUTOFDISK and returns a FALSE, then the NEWFRAME Escape call currently in progress returns an SP_APPABORT error code (equal to -2), and the print job is aborted.

The abort function can be as simple as this:

```
BOOL FAR PASCAL AbortProc (hPrnDC, nCode)

HDC hPrnDC;
short nCode;
{
   MSG msg;

while (PeekMessage (&msg, NULL, 0, 0, PM_REMOVE))
   (
   TranslateMessage (&msg);
   DispatchMessage (&msg);
}
return TRUE;
```

This function may seem a little peculiar. In fact, it looks suspiciously like a message loop. What's a message loop doing here of all places? Well, it is a message loop. You'll note, however, that this message loop calls PeekMessage rather than GetMessage. I discussed PeekMessage in connection with the RANDRECT program at the end of Chapter 13. You'll recall that PeekMessage returns control to a program with a message from the program's message queue (just like GetMessage) but also returns control if there are no messages waiting in any program's message queue.

The message loop in the AbortProc function repeatedly calls PeekMessage while it returns TRUE. This TRUE value means that PeekMessage has retrieved a message that can be sent to one of the program's window functions using TranslateMessage and DispatchMessage. When there are no more messages in the program's message queue, Windows allows other programs to process messages from their queues. When there are no more messages in any program's message queue, Windows returns control to the program calling PeekMessage (that is, to the AbortProc function). The return value of PeekMessage is then FALSE, so AbortProc returns control to Windows.

The PRINT1 version of our program doesn't yield control during the entire time it is printing. Windows is essentially frozen during that time because no other program can process messages. As you've probably discovered by now, the *PrintMyPage* function in PRINT1 can take a while. Only when the function is finished can SPOOLER actually start to print. An abort function gives SPOOLER—and other programs running under Windows—a chance to run while a program is printing.

How Windows Uses AbortProc

When a program is printing, the bulk of the work takes place during the NEWFRAME Escape call. Before that call, the GDI module simply adds another record to the disk-based metafile every time the program calls a GDI drawing function. When GDI gets the NEWFRAME Escape call, it plays this metafile into the device driver once for each band the device driver defines on a page. GDI then stores the printer output created by the printer driver in a file. If SPOOLER isn't loaded, the GDI module itself must write this printer output to the printer.

During the NEWFRAME Escape call, the GDI module calls the abort function you've set. Normally, the nCode parameter is 0, but if GDI has run out of disk space because of the presence of other temporary files that haven't been printed yet, then the nCode parameter is SP_OUTOFDISK. (You wouldn't normally check this value, but you can if you want.) The abort function then goes into its PeekMessage loop. The loop first retrieves messages from the program's own message queue and then yields control so that other programs can retrieve and process their own messages. When no messages remain in any program's queue, control passes to another program currently waiting for its own PeekMessage call to return.

One of those programs is SPOOLER, which also uses a *PeekMessage* call to retrieve messages. When SPOOLER returns from the *PeekMessage* call in its own message loop, it can transfer part of a disk file to the printer. SPOOLER then calls *PeekMessage* again in its own message loop. If there are still no messages in any program's message queue, control returns to *AbortProc*, and *PeekMessage* returns FALSE. The abort function then drops out of its message loop and returns a TRUE value to the GDI module to indicate that printing should continue. The GDI module then continues to process the NEWFRAME *Escape* call.

While the main purpose of the abort function is to allow SPOOLER the opportunity to transfer existing files to the printer to free up disk space, it also allows all other programs to run during the time a program is printing. This effect of the abort function is particularly important if SPOOLER isn't installed, which is why an abort function is required for printing without SPOOLER. Windows won't allow the whole system to be suspended while it waits for the printer; the abort function avoids this.

Implementing an Abort Function

Let's quickly review the mechanics of the abort function. You define an abort function that looks like this:

```
BOOL FAR PASCAL AbortProc (hPrnDC, nCode)

HDC hPrnDC;
short nCode;
{
MSG msg;
while (PeekMessage (&msg, NULL, 0, 0, PM_REMOVE))
{
TranslateMessage (&msg);
DispatchMessage (&msg);
}
return TRUE;
```

You list AbortProc in the EXPORTS section of your module definition file. You obtain a pointer to the function using MakeProcInstance.

```
lpfnAbortProc = MakeProcInstance (AbortProc, hInstance) ;
```

When you want to print something, you give Windows this pointer with an Escape call:

```
Escape (hPrnDC, SETABORTPROC, 0, (LPSTR) lpfnAbortProc, NULL) ;
```

You make this Escape call before the Escape call for STARTDOC. And that's it.

Well, not quite. We've overlooked a problem with that *PeekMessage* loop in *AbortProc*—a big problem. *AbortProc* is called only while your program is in the midst of printing. Some very ugly things can happen if you retrieve a message in *AbortProc* and dispatch it to your own window function. A user could select Print from the menu again. But the program is already in the middle of the printing routine. A user could load a new file into the program while the program is trying to print the previous file. A user could even quit your program! If that happens, all your program's windows will be destroyed. You'll eventually return from the printing routine, but you'll have nowhere to go except to a window function that's no longer valid.

This stuff boggles the mind. Your program isn't prepared for it. For this reason, when you set an abort function, you should first disable your program's window so that it can't receive keyboard and mouse input. You do this with:

```
EnableWindow (hWnd, FALSE) ;
```

This prevents keyboard and mouse input from getting into the message queue. The user thus can't do anything with your program during the time it's printing. When you're done printing, you reenable the window for input:

```
EnableWindow (hWnd, TRUE) ;
```

So why, you ask, do we even bother with the TranslateMessage and DispatchMessage calls in AbortProc when no keyboard or mouse messages will get into the message queue in the first place? It's true that the TranslateMessage call isn't strictly needed (although it's almost always included). But we must use DispatchMessage in case a WM_PAINT message gets in the message queue. If WM_PAINT isn't processed properly with a BeginPaint and EndPaint pair in the window function, the message will remain in the queue and clog up the works, because PeekMessage will never return a FALSE.

When you disable your window during the time you're printing, your program remains inert on the display. But a user can switch to another program and do some work there, and SPOOLER can continue sending output files to the printer.

The PRINT2 program, shown in Figure 16-7 (beginning on the following page), adds an abort function (and the necessary support) to the logic in PRINT1. More specifically, PRINT2 adds the abort function (including a listing in the EXPORTS section of PRINT2.DEF), a call to MakeProcInstance and Escape using the SETABORTPROC subfunction, a FreeProcInstance call at the end, and two calls to EnableWindow, the first to disable the window and the second to reenable it.

```
print.obj : print.c
    cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp print.c

print2.obj : print2.c
    cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp print2.c

print2.exe : print.obj print2.obj print2.def
    link4 print2 print, /align:16, /map, slibw, print2
```

```
/* PRINT2.C -- Printing with Abort Function */
#include <windows.h>
HDC GetPrinterDC (void);
void PageGDICalls (HDC, short, short);
                                          /* in PRINT.C */
HANDLE hinst ;
char szAppName [] = "Print2";
char szCaption [] = "Print Program 2 (Abort Function)" ;
BOOL FAR PASCAL AbortProc (hPrnDC, nCode)
     HDC hPrnDC ;
     short nCode :
     MSG
          msq ;
     while (PeekMessage (&msg, NULL, 0, 0, PM REMOVE))
          TranslateMessage (&msg) ;
          DispatchMessage (&msg) ;
     return TRUE ;
BOOL PrintMyPage (hWnd)
     HWND
                hWnd :
     static char szMessage [] = "Print2: Printing";
              bError = FALSE ;
     FARPROC
                  lpfnAbortProc ;
     HDC
            hPrnDC ;
             rect;
     RECT
     short
                 xPage, yPage ;
     if (NULL == (hPrnDC = GetPrinterDC ()))
          return TRUE ;
     xPage = GetDeviceCaps (hPrnDC, HORZRES) ;
     yPage = GetDeviceCaps (hPrnDC, VERTRES) ;
     EnableWindow (hWnd, FALSE) ;
     lpfnAbortProc = MakeProcInstance (AbortProc, hInst) ;
Escape (hPrnDc, SETABORTPROC, 0, (LPSTR) lpfnAbortProc, NULL) ;
     if (Escape (hPrnDC, STARTDOC, sizeof szMessage - 1, szMessage, NULL) > 0)
          PageGDICalls (hPrnDC, xPage, yPage) ;
```

Figure 16-7. The PRINT2 program

Figure 16-7. Continued

```
PRINT2
NAME
NAME PRINT2
DESCRIPTION 'Printing Program No. 2 (C) Charles Petzold, 1987'
               'WINSTUB.EXE'
STUB
              MOVEABLE
CODE
DATA
              MOVEABLE MULTIPLE
HEAPSIZE
               1024
STACKSIZE
                4096
EXPORTS
               WndProc
                AbortProc
```

Adding a Printing Dialog Box

PRINT2 is not entirely satisfactory. First, the program doesn't directly indicate when it is printing and when it is finished with printing. Only when you poke at the program with the mouse and find that it doesn't respond can you determine that it must still be processing the <code>PrintMyPage</code> routine. Nor does PRINT2 give the user the opportunity to cancel the print job before it shows up in SPOOLER's client area.

You're probably aware that most Windows programs give users a chance to cancel a printing operation currently in progress. A small dialog box comes up on the screen; it contains some text and a push button labeled Cancel. The program displays this dialog box during the entire time that GDI is saving the printer output in a disk file or (if SPOOLER isn't loaded) while the printer is printing. This is a modeless dialog box, and you must supply the dialog function. As for all dialog boxes, you include the name of the dialog function in the EXPORTS section of the module definition file and use *MakeProcInstance* to obtain a pointer to the function.

This dialog box is often called the "abort dialog box," and the dialog function is often called the "abort dialog function." To distinguish it more clearly from the "abort function," I'll call this dialog function the "printing dialog function." The abort function (with the name *AbortProc*) and the printing dialog function (which I'll name *PrintDlgProc*) are two separate

PR-NT3.C

exported functions. If you want to print in a professional Windows-like manner, you must have both of them.

These two functions interact as follows. The <code>PeekMessage</code> loop in <code>AbortProc</code> must be modified to send messages for the modeless dialog box to the dialog box window function. <code>PrintDlgProc</code> must process WM_COMMAND messages to check the status of the Cancel button. If the Cancel button is pressed, it sets a variable called <code>bUserAbort</code> to TRUE. The value returned from <code>AbortProc</code> is the inverse of <code>bUserAbort</code>. You'll recall that <code>AbortProc</code> returns TRUE to continue printing and <code>FALSE</code> to abort printing. In PRINT2 we always returned TRUE. Now we'll return <code>FALSE</code> if the user clicks the Cancel button in the printing dialog box. This logic is implemented in the <code>PRINT3</code> program, shown in Figure 16-8.

```
print.obj : print.c
    cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp print.c

print3.obj : print3.c
    cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp print3.c

print.res : print.rc
    rc -r print.rc

print3.exe : print.obj print3.obj print3.def print.res
    link4 print3 print, /align:16, /map, slibw, print3
    rc print.res print3.exe
```

```
/* PRINT3.C -- Printing with Dialog Box */
#include <windows.h>
                                        /* in PRINT.C */
HDC GetPrinterDC (void) ;
void PageGDICalls (HDC, short, short) ;
HANDLE hInst ;
char szAppName [] = "Print3" ;
char szCaption [] = "Print Program 3 (Dialog Box)" ;
BOOL bUserAbort;
HWND hDlgPrint;
BOOL FAR PASCAL PrintDlgProc (hDlg, iMessage, wParam, 1Param)
    HWND hDlq :
     unsigned iMessage
     WORD
           wParam ;
     DWORD 1Param ;
     switch (iMessage)
          case WM INITDIALOG:
              SetWindowText (hDlg, szAppName) ;
               EnableMenuItem (GetSystemMenu (hDlg, FALSE), SC CLOSE,
                                                            MF GRAYED) ;
               break ;
```

Figure 16-8. The PRINT3 program

Figure 16-8. Continued

```
case WM COMMAND:
               bUserAbort = TRUE ;
               EnableWindow (GetParent (hDlg), TRUE) ;
               DestroyWindow (hDlg) ;
               hDlgPrint = 0 :
              break :
          default:
              return FALSE ;
     return TRUE ;
BOOL FAR PASCAL AbortProc (hPrnDC, nCode)
     HDC hPrnDC :
     short nCode ;
    MSG
          msg ;
    while (!bUserAbort && PeekMessage (&msq, NULL, 0, 0, PM REMOVE))
          if (!hDlgPrint || !IsDialogMessage (hDlgPrint, &msg))
               TranslateMessage (&msq) ;
               DispatchMessage (&msg) ;
     return !bUserAbort ;
BOOL PrintMyPage (hWnd)
     HWND
                hWnd ;
     static char szMessage [] = "Print3: Printing" ;
               bError = FALSE
     FARPROC
                 lpfnAbortProc, lpfnPrintDlgProc ;
     HDC
                hPrnDC ;
                rect ;
     RECT
     short
                 xPage, yPage ;
     if (NULL == (hPrnDC = GetPrinterDC ()))
          return TRUE ;
     xPage = GetDeviceCaps (hPrnDC, HORZRES) ;
     yPage = GetDeviceCaps (hPrnDC, VERTRES) ;
     EnableWindow (hWnd, FALSE) ;
     bUserAbort = FALSE ;
     lpfnPrintDlqProc = MakeProcInstance (PrintDlqProc, hInst) ;
     hDlgPrint = CreateDialog (hInst, "PrintDlgBox", hWnd, lpfnPrintDlgProc) ;
     lpfnAbortProc = MakeProcInstance (AbortProc, hInst) ;
     Escape (hPrnDC, SETABORTPROC, 0, (LPSTR) lpfnAbortProc, NULL) ;
     if (Escape (hPrnDC, STARTDOC, sizeof szMessage - 1, szMessage, NULL) > 0)
          PageGDICalls (hPrnDC, xPage, yPage) ;
          if (Escape (hPrnDC, NEWFRAME, 0, NULL, NULL) > 0)
               Escape (hPrnDC, ENDDOC, 0, NULL, NULL) ;
```

```
else
         bError = TRUE ;
else
     bError = TRUE ;
if (!bUserAbort)
     EnableWindow (hWnd, TRUE) ;
     DestroyWindow (hDlgPrint) ;
FreeProcInstance (lpfnPrintDlgProc) ;
FreeProcInstance (lpfnAbortProc) ;
DeleteDC (hPrnDC) ;
return bError || bUserAbort ;
```

PRINTSIRC

```
#include <style.h>
PrintDlgBox DIALOG 40, 40, 120, 40
STYLE WS_POPUP | WS_CAPTION | WS_SYSMENU | WS_VISIBLE
     BEGIN
                            "Cancel Printing", -1, 4, 6, 120, 12
           DEFPUSHBUTTON "Cancel", IDCANCEL, 44, 22, 32, 14, WS GROUP
     END
```

PR-NT3.DEF

```
PRINT3
NAME
DESCRIPTION
              'Printing Program No. 3 (C) Charles Petzold, 1987'
              'WINSTUB.EXE'
STUB
              MOVEABLE
CODE
              MOVEABLE MULTIPLE
DATA
              1024
HEAPSIZE
STACKSIZE
               4096
              WndProc
EXPORTS
               AbortProc
               PrintDlqProc
```

Two global variables are added to PRINT3: a BOOL called bUserAbort and a handle to the dialog box window called hDlgPrint. The PrintMyPage function initializes bUserAbort to FALSE, and as in PRINT2, the program's main window is disabled. PrintMyPage then calls MakeProcInstance for both AbortProc and PrintDlgProc. The pointer to AbortProc is used in the SETABORTPROC Escape call, and the pointer to PrintDlgProc is used in a CreateDialog call. The window handle returned from CreateDialog is saved in hDlgPrint.

The message loop in AbortProc now looks like this:

```
while (!bUserAbort && PeekMessage (&msg, NULL, 0, 0, PM_REMOVE))
{
   if (!hDlgPrint || !IsDialogMessage (hDlgPrint, &msg))
        {
        TranslateMessage (&msg) ;
        DispatchMessage (&msg) ;
     }
}
return !bUserAbort ;
```

It calls *PeekMessage* only if *bUserAbort* is FALSE, that is, if the user hasn't yet aborted the printing operation. The *IsDialogMessage* function is required to send the message to the modeless dialog box. As is normal with modeless dialog boxes, the handle to the dialog box window is checked before this call is made. *AbortProc* returns the inverse of *bUserAbort*. Initially, *bUserAbort* is FALSE, so *AbortProc* returns TRUE, indicating that printing is to continue. But *bUserAbort* could be set to TRUE in the printing dialog function.

The *PrintDlgProc* function is fairly simple. While processing WM_INITDIALOG, the function sets the window caption to the name of the program and disables the Close option on the system menu. If the user clicks the Cancel button, *PrintDlgProc* receives a WM_COMMAND message:

```
case WM_COMMAND:
   bUserAbort = TRUE ;
   EnableWindow (GetParent (hDlg), TRUE) ;
   DestroyWindow (hDlg) ;
   hDlgPrint = 0 ;
   break ;
```

Setting bUserAbort to TRUE indicates that the user has decided to cancel the printing operation. The main window is enabled, and the dialog box is destroyed. (It is important that you perform these two actions in this order. Otherwise, some other program running under Windows will become the active program, and your program might disappear into the background.) As is normal, hDlgPrint is set to 0 to prevent IsDialogMessage from being called in the message loop.

The only time this dialog box receives messages is when AbortProc retrieves messages with PeekMessage and sends them to the dialog box window function with IsDialogMessage. The only time AbortProc is called is when the GDI module is processing the NEWFRAME Escape function. If GDI sees that the return value from AbortProc is FALSE, it returns control from the Escape call back to PrintMyPage. It doesn't return an error code. At that point, PrintMyPage thinks that the page is complete and calls the ENDDOC Escape function. Nothing is printed, however, because the GDI module didn't finish processing the NEWFRAME Escape call.

Some cleanup remains. If the user didn't cancel the print job from the dialog box, then the dialog box is still displayed. *PrintMyPage* reenables its main window and destroys the dialog box:

```
if (!bUserAbort)
{
    EnableWindow (hWnd, TRUE) ;
    DestroyWindow (hDlgPrint) ;
}
```

Two variables tell you what happened: bUserAbort tells you if the user aborted the print job, and bErrortells you if an error occurred. You can do what you want with these variables. PrintMyPage simply performs a logical OR operation to return to WndProc.

```
return bError | bUserAbort ;
```

Adding Printing to POPPAD

Now we're ready to add a printing facility to the POPPAD program and declare POPPAD finished. Figure 16-9 shows the revised POPPADP.C file. Simply substitute it for the POPPADP.C file in Chapter 11 (Figure 11-9).

```
/* POPPADP.C -- Popup Editor Printing Functions */
#include <windows.h>
#include <string.h>
#include "filedlg.h"
                                        /* for IDD FNAME definition */
                                       /* in POPPAD.C */
extern char szAppName [] ;
BOOL bUserAbort ;
HWND hDlgPrint ;
BOOL FAR PASCAL PrintDlqProc (hDlq, iMessage, wParam, 1Param)
     HWND
             hDlg :
     unsigned iMessage ;
           wParam ;
     WORD
     LONG
             1Param ;
     switch (iMessage)
          case WM INITDIALOG:
               EnableMenuItem (GetSystemMenu (hDlg, FALSE), SC_CLOSE,
                                                             MF GRAYED) ;
               break ;
          case WM COMMAND:
               bUserAbort = TRUE ;
               EnableWindow (GetParent (hDlg), TRUE) ;
               DestroyWindow (hDlg) ;
               hDlgPrint = 0 ;
               break :
```

Figure 16-9. The POPPADP.C file, to replace POPPADP.C in the POPPAD program in Figure 11-9

Figure 16-9. Continued

```
default:
              return FALSE ;
     return TRUE ;
BOOL FAR PASCAL AbortProc (hPrinterDC, nCode)
    HDC hPrinterDC;
     short nCode ;
     MSG
         msg ;
     while (!bUserAbort && PeekMessage (&msg, NULL, 0, 0, PM REMOVE))
          if (!hDlgPrint | | !IsDialogMessage (hDlgPrint, &msg))
               TranslateMessage (&msg) ;
               DispatchMessage (&msg) ;
     return !bUserAbort ;
HDC GetPrinterDC ()
    char szPrinter [64] ;
    char *szDevice, *szDriver, *szOutput ;
    GetProfileString ("windows", "device", "", szPrinter, 64) ;
    if ((szDevice = strtok (szPrinter, "," )) &&
                                        ", ")) &&
         (szDriver = strtok (NULL,
         (szOutput = strtok (NULL,
               return CreateDC (szDriver, szDevice, szOutput, NULL) ;
     return 0 ;
BOOL PrintFile (hInst, hWnd, hWndEdit, szFileName)
               hInst ;
    HWND
               hWnd, hWndEdit;
    char
               *szFileName ;
    BOOL
               bError = FALSE ;
    char
               szMsg [40] ;
    FARPROC
               lpfnAbortProc, lpfnPrintDlgProc;
    HDC
               hPrnDC ;
    NPSTR
               psBuffer ;
    RECT
               rect ;
    short
               yChar, nCharsPerLine, nLinesPerPage,
                nTotalLines, nTotalPages, nPage, nLine, nLineNum = 0 ;
    TEXTMETRIC tm ;
     if (0 == (nTotalLines = (short) SendMessage (hWndEdit,
                                             EM GETLINECOUNT, 0, OL)))
         return FALSE ;
    if (NULL == (hPrnDC = GetPrinterDC ()))
         return TRUE ;
```

Figure 16-9. Continued

```
GetTextMetrics (hPrnDC, &tm) ;
yChar = tm.tmHeight + tm.tmExternalLeading ;
nCharsPerLine = GetDeviceCaps (hPrnDC, HORZRES) / tm.tmAveCharWidth ; nLinesPerPage = GetDeviceCaps (hPrnDC, VERTRES) / yChar ; nTotalPages = (nTotalLines + nLinesPerPage - 1) / nLinesPerPage ;
psBuffer = (NPSTR) LocalAlloc (LPTR, nCharsPerLine) ;
EnableWindow (hWnd, FALSE) :
bUserAbort = FALSE ;
lpfnPrintDlgProc = MakeProcInstance (PrintDlgProc, hInst) ;
hDlgPrint = CreateDialog (hInst, "PrintDlgBox", hWnd, lpfnPrintDlgProc); SetDlgItemText (hDlgPrint, IDD_FNAME, szFileName);
lpfnAbortProc = MakeProcInstance (AbortProc, hInst) ;
Escape (hPrnDC, SETABORTPROC, 0, (LPSTR) lpfnAbortProc, NULL) ;
strcat (strcat (strcpy (szMsg, szAppName), " - "), szFileName) ;
if (Escape (hPrnDC, STARTDOC, strlen (szMsg), szMsg, NULL) > 0)
      for (nPage = 0 : nPage < nTotalPages : nPage++)
           for (nLine = 0 ; nLine < nLinesPerPage &&
                               nLineNum < nTotalLines ; nLine++, nLineNum++)
                 *(short *) psBuffer = nCharsPerLine ;
                 TextOut (hPrnDC, 0, yChar * nLine, psBuffer,
                       (short) SendMessage (hWndEdit, EM GETLINE,
                                        nLineNum, (LONG) (LPSTR) psBuffer));
           if (Escape (hPrnDC, NEWFRAME, 0, NULL, (LPSTR) &rect) < 0)
                 bError = TRUE ;
                 break :
           if (bUserAbort)
                 break ;
else
      bError = TRUE ;
if (!bError)
      Escape (hPrnDC, ENDDOC, 0, NULL, NULL) ;
if (!bUserAbort)
      EnableWindow (hWnd, TRUE) ;
      DestroyWindow (hDlgPrint)
if (bError || bUserAbort)
      strcat (strcpy (szMsg, "Could not print: "), szFileName) ;
     MessageBox (hWnd, szMsg, szAppName, MB_OK | MB_ICONEXCLAMATION) ;
```

Figure 16-9. Continued

```
LocalFree ((LOCALHANDLE) psBuffer);
FreeProcInstance (lpfnPrintDlgProc);
FreeProcInstance (lpfnAbortProc);
DeleteDC (hPrnDC);
return bError || bUserAbort;
```

POPPADP.C is structurally similar to PRINT3.C except that it must be able to print multiple pages. The *PrintFile* routine performs some calculations to determine the number of characters it can fit on a line and the number of lines it can fit on a page. This process involves calls to *GetDeviceCaps* to determine the resolution of the page and to *GetTextMetrics* for the dimensions of a character.

The program obtains the total number of lines in the document (the variable nTotalLines) by sending an EM_GETLINECOUNT message to the edit control. A buffer for holding the contents of each line is allocated from local memory. For each line, the first word of this buffer is set to the number of characters in the line. Sending the edit control an EM_GETLINE message copies a line into the buffer; the line is then sent to the printer device context using TextOut.

The program breaks from the *for* loop incrementing the page number if the NEWFRAME *Escape* call returns an error or if *bUserAbort* is TRUE. Although the NEWFRAME call will return before GDI finishes the call if the return value of the abort function is FALSE, it doesn't return an error. For this reason, *bUserAbort* is tested explicitly before the next page is started. If no error is reported, the ENDDOC *Escape* call is made:

```
if (!bError)
Escape (hPrnDC, ENDDOC, 0, NULL, NULL);
```

You might want to experiment with POPPAD by printing a multipage file. The file being printed first shows up in SPOOLER's client area after GDI has finished processing the first NEWFRAME *Escape* call. At that time, SPOOLER starts sending the file to the printer. If you then cancel the print job from POPPAD, SPOOLER aborts the printing also—that's a result of returning FALSE from the abort function. Once the file appears in SPOOLER's client area, you can also cancel the printing by selecting Terminate from the Queue menu. In that case, the NEWFRAME *Escape* call in progress in POPPAD returns an SP_USERABORT error (equal to -3).

Programmers new to Windows often become obsessed with the ABORTDOC Escape function. This function is rarely used in printing that also uses the NEWFRAME Escape function. As you can see in POPPAD, a user can cancel a print job at almost any time, either through POPPAD's printing dialog box or through SPOOLER. Neither requires that the program use the ABORTDOC Escape function. The only time that ABORTDOC would be allowed in POPPAD is between the STARTDOC Escape call and the first NEWFRAME Escape call, but that code goes so quickly that ABORTDOC isn't necessary.

Figure 16-10 shows the correct sequence of *Escape* calls for printing a multipage document. The best place to check for a *bUserAbort* value of TRUE is after each NEWFRAME *Escape* call. The ENDDOC *Escape* function is used only when the previous *Escape* calls have proceeded without error. In fact, once you get an error from any *Escape* call, the show is over, and you can go home.




Figure 16-10. The sequence of Escape calls for multipage printing

Handling Error Codes

We have been handling the return value from the *Escape* function in a relatively simple manner: If *Escape* returns a negative value, then an error has occurred, and the printing operation is aborted. You can report more precise errors to the user by checking the *Escape* return value against five identifiers defined in WINDOWS.H. WINDOWS.H also includes an identifier called SP_NOTREPORTED, which is equal to 0x4000. If a bitwise AND of the return value from *Escape* with SP_NOTREPORTED is 0, then the error has already been reported to the user. A bitwise OR of the return value of *Escape* with SP_NOTREPORTED can be used to compare with the five error-code identifiers whether the error has been reported or not.

The following function shows one method of obtaining a text string identifying the error. The function returns NULL if no error has occurred or if the error has already been reported to the user:

The five error codes (with some likely causes) are as follows:

- SP_ERROR (0xFFFF, or -1)—Defined as indicating a "general error," this is the only
 error code that can be returned from STARTDOC. It can occur if the GDI module or
 the printer device driver can't begin a document. If SPOOLER isn't loaded, you can
 also get this error from STARTDOC if another program is currently printing or if the
 printer is off-line or has no paper.
- SP_APPABORT (0xFFFE, or -2)—This code is documented as indicating that the
 program's abort function has returned a FALSE value. However, this is the case
 only if SPOOLER isn't loaded. If SPOOLER is loaded and if the abort function is
 passed an nCode parameter of 0 and then returns a FALSE, the NEWFRAME Escape
 call will return a positive value, not an SP_APPABORT error. You'll also get this
 error code if SPOOLER isn't loaded and you don't set an abort function.
- SP_USERABORT (0xFFFD, or -3)—This code indicates that the user canceled the printing job from the SPOOLER program.

- SP_OUTOFDISK (0xFFFC, or -4)—This code indicates that no more disk space is available. You'll encounter this error code if the disk drive containing the TEMP subdirectory can't accommodate any temporary metafiles or spooler files. If the TEMP subdirectory has some existing temporary spooler files, then the abort function is called during a NEWFRAME or NEXTBAND Escape call with an nCode parameter of SP_OUTOFDISK. If the abort function then returns FALSE, the Escape call returns SP_OUTOFDISK.
- SP_OUTOFMEMORY (0xFFFB, or -5)—This code indicates that insufficient memory is available for printing.

THE TECHNIQUE OF BANDING

Banding is the technique of defining a page of graphics as a series of separately constructed rectangles called bands. This approach relieves a printer driver of the necessity of constructing an entire bitmapped page image in memory. Banding is most important for raster printers that have no high-level page-composition control, such as dot-matrix printers and some laser printers.

Banding is one of the most misunderstood aspects of programming for the printer in Windows. Part of the problem lies in the documentation for the GetDeviceCaps function. The RC_BANDING bit of the value returned from GetDeviceCaps with the RASTERCAPS index is documented as "requires banding support." Programmers looking at this documentation assume that their applications must use banding with such printers. But this isn't so. Most of the information available from GetDeviceCaps is intended solely for the GDI module. This information allows GDI to determine what the device can do by itself and what it needs help with. The banding requirement falls into this category.

In general, an application program doesn't need to include its own banding logic. As you've seen, when you make GDI calls that define a page of graphics, the GDI module stores these calls in a metafile and then uses banding to set a clipping region before playing this metafile into the printer device driver. This is transparent to the application program. Under certain conditions, however, an application might want to take over the responsibility for doing banding. When an application uses banding, the GDI module doesn't create the intermediary metafile. Instead, the drawing commands for each band are passed to the printer device driver. There are two advantages to this approach:

It can increase printing speed. The application needs to call only those GDI
functions that draw something in each particular band, which is faster than having
the GDI module play the entire metafile into the device driver for each band. Even
if the program simply draws the entire page for each band, the process can still be
faster than having the GDI module create and read the disk-based metafile,
because the program doesn't have to access a disk.

It can reduce the disk space normally required for printing. If the application is
printing bitmaps but is not doing its own banding, then these bitmaps must be
stored in the metafile that GDI creates. This situation can result in a metafile as
large as the printer output file that the GDI module eventually creates.

But banding also further complicates the printing process, as you'll see when we create PRINT4, the final version of our printing program.

Strike Up the Bands

To have your program do its own banding, you first define a variable of type RECT:

```
RECT rect ;
```

You'll recall that the RECT structure has four fields named *left*, *top*, *right*, and *bottom*. For each page, you start by making an *Escape* call for the subfunction NEXTBAND, passing to it a pointer to *rect*. On return, *rect* contains the coordinates of the first band. The coordinates are always device coordinates (pixels) regardless of the current mapping mode of the printer device context. You make GDI calls to print in that band. You then call the NEXTBAND *Escape* function again to obtain the coordinates of the next band, and you print in that band. When the RECT structure passed to *Escape* is returned empty (all fields set to 0), the page is done.

Here's what the code looks like to print a single page. For simplicity's sake, this code doesn't take into account errors that can be returned from the *Escape* functions or checks of the *bUserAbort* value:

Each NEXTBAND Escape call except the first performs a function similar to the NEWFRAME Escape call: It signals to the GDI module and the printer device driver that the entire band has been defined and that it can now be saved in a disk file (or written to the printer if SPOOLER is not loaded). You don't want to call the NEWFRAME Escape function after this loop has run its course. If you do so, you'll get a blank page between each printed page. Nor can you terminate the loop before receiving an empty rectangle and then make a NEWFRAME Escape call to skip the rest of the page. In short, you either use NEWFRAME to print a page without banding or multiple NEXTBAND calls to print a page with banding. Don't mix NEWFRAME and NEXTBAND Escape functions for the same page.

It's easiest to visualize banding for a dot-matrix printer. Before illustrating the process, we need to make a distinction between the "top of the paper" (which is always the section of the paper printed first) and the "top of the page," which depends on whether the printer driver is in portrait or landscape mode.

In portrait mode, the top of the page is the same as the top of the paper. The bands go down the page. The rect.left value in the RECT structure set by the NEXTBAND Escape call is always 0, and rect.right is always equal to the width of the printing area in pixels (the value obtained from GetDeviceCaps with a HORZRES parameter). For the first band, rect.top equals 0. For each successive band, rect.top equals the rect.bottom value of the previous band. For the last band, rect.bottom equals the height of the printing area in pixels. (See Figure 16-11.)




Figure 16-11. Banding for a dot-matrix printer in portrait mode

Thus in each band, you can print from the rect.left and rect.top coordinates up to (but not including) the rect.right and rect.bottom coordinates. If you call the function:

```
Rectangle (hPrnDC, rect.left, rect.top, rect.right, rect.bottom) ;
```

the rectangle will be printed on the outermost edges of the band. (Recall that the right and bottom sides of the rectangle drawn by *Rectangle* are actually one pixel short of the points indicated by the last two parameters.)

In landscape mode, the dot-matrix printer must print the document sideways, starting from the left side of the page. The bands are in exactly the same area on the paper, but the rectangle coordinates are different, because the left side of the page is now the top of the paper. In landscape mode, rect.top is always 0, and rect.bottom is a constant equal to the height of the printing area in pixels (the value obtained from GetDeviceCaps using the VERTRES parameter). For the first band, rect.left equals 0. For the last band, rect.right is the width of the printing area in pixels. (See Figure 16-12.)




Figure 16-12. Banding for a dot-matrix printer in landscape mode

A laser printer or a plotter might handle banding differently than a dot-matrix printer, because the printer output might not need to be sent to the printer sequentially from the top of the page to the bottom. Although Figures 16-11 and 16-12 represent the normal case, your program shouldn't assume that the banding rectangles will follow these patterns.

Separating your printer output into bands might seem like a major headache. But even if you use banding, you don't need to include a lot of banding logic. The band is a clipping region. You can make GDI calls that print outside the band, and Windows will ignore everything except what falls inside the band. This means that for each band, you can make all the GDI calls for the entire page.

You can determine whether a particular driver requires banding support by checking the RC_BANDING bit of the value returned from *GetDeviceCaps* using the RASTERCAPS parameter. As I mentioned before, this information is of concern only to GDI. Whether a driver requires banding support or not, the GDI module always supports the NEXTBAND *Escape* call. If the driver doesn't require banding support, the first NEXTBAND *Escape* call for a page returns a rectangle equal to the size of the printing area. The second NEXTBAND call for a page returns an empty rectangle.

A Different Use of the Abort Function

When a program assumes responsibility for banding, the GDI module uses the abort function somewhat differently than it does otherwise. If SPOOLER isn't loaded, the GDI module frequently calls the abort function with an *nCode* parameter of 0 while processing the NEXTBAND *Escape* call, just as it does when processing NEWFRAME. However, if SPOOLER

PRINT4.C

is loaded (the more normal case), the GDI module calls the abort function *only* if it runs out of disk space. The *nCode* parameter is SP_OUTOFDISK.

This arrangement presents a problem. Unless the GDI module runs out of disk space, the user can't switch to another program until the application currently printing is finished. Moreover, although the printing dialog box is displayed, the user can't cancel the print job, because the dialog box can't get messages until the abort function is called. The solution to this problem is fairly simple. Your printing routine can call the abort function itself between the GDI drawing functions that make up the page. Although the operation of Windows isn't as smooth as when the GDI module calls the abort function, this approach at least allows the user to cancel the print job or move on to another task.

Don't call the abort function directly. Instead, use the pointer returned from MakeProcInstance. For instance, if your abort function is called AbortProc and the pointer returned from MakeProcInstance is called IpfnAbortProc, you can call AbortProc using:

```
(*lpfnAbortProc) (hPrnDC, 0);
```

The PRINT4 program, shown in Figure 16-13, adds banding to the printing logic in PRINT3. PRINT4 also requires the PRINT.RC file in Figure 16-8 and—like all our PRINT programs—the PRINT.C file in Figure 16-5.

Figure 16-13. The PRINT4 program

```
unsigned iMessage ;
     WORD
             wParam ;
     DWORD
              lParam ;
     switch (iMessage)
           case WM INITDIALOG:
                SetWindowText (hDlg, szAppName) ;
                EnableMenuItem (GetSystemMenu (hDlg, FALSE), SC CLOSE,
                                                                MF GRAYED) ;
                break ;
          case WM COMMAND:
                bUserAbort = TRUE ;
                EnableWindow (GetParent (hDlg), TRUE) ;
                DestroyWindow (hDlg) ;
                hDlgPrint = 0 ;
                break :
           default:
                return FALSE ;
     return TRUE ;
BOOL FAR PASCAL AbortProc (hPrnDC, nCode)
     HDC hPrnDC;
     short nCode ;
          msg ;
     while (!bUserAbort && PeekMessage (&msg, NULL, 0, 0, PM REMOVE))
           if (!hDlgPrint | | !IsDialogMessage (hDlgPrint, &msg))
                TranslateMessage (&msg) ;
                DispatchMessage (&msg) ;
     return !bUserAbort ;
BOOL PrintMyPage (hWnd)
     HWND
                  hWnd ;
     static char szSpMsg [] = "Print4: Printing";
static char szText [] = "Hello Printer!";
BOOL bError = FALSE;
     DWORD
                  dwExtent ;
     FARPROC
                  lpfnAbortProc, lpfnPrintDlgProc;
                 hPrnDC ;
     HDC
                 ptExtent;
     POINT
     RECT
                  rect ;
     short
                  xPage, yPage ;
     if (NULL == (hPrnDC = GetPrinterDC ()))
          return TRUE ;
     xPage = GetDeviceCaps (hPrnDC, HORZRES) ;
     yPage = GetDeviceCaps (hPrnDC, VERTRES) ;
```

```
EnableWindow (hWnd, FALSE) ;
bUserAbort = FALSE ;
lpfnPrintDlgProc = MakeProcInstance (PrintDlgProc, hInst) ;
hDlgPrint = CreateDialog (hInst, "PrintDlgBox", hWnd, lpfnPrintDlgProc) ;
lpfnAbortProc = MakeProcInstance (AbortProc, hInst) ;
Escape (hPrnDC, SETABORTPROC, 0, (LPSTR) lpfnAbortProc, NULL) ;
if (Escape (hPrnDC, STARTDOC, sizeof szSpMsg - 1, szSpMsg, NULL) > 0 &&
     Escape (hPrnDC, NEXTBAND, 0, NULL, (LPSTR) &rect) > 0)
     while (!IsRectEmpty (&rect) && !bUserAbort)
            (*lpfnAbortProc) (hPrnDC, 0);
           Rectangle (hPrnDC, rect.left, rect.top, rect.right,
                                                        rect.bottom) ;
           (*lpfnAbortProc) (hPrnDC, 0);
           MoveTo (hPrnDC, 0, 0) ;
           LineTo (hPrnDC, xPage, yPage) ;
           (*lpfnAbortProc) (hPrnDC, 0);
           MoveTo (hPrnDC, xPage, 0) ;
           LineTo (hPrnDC, 0, yPage) ;
           SaveDC (hPrnDC) ;
           SetMapMode (hPrnDC, MM ISOTROPIC) ;
           SetWindowExt (hPrnDC, 1000, 1000);
SetViewportExt (hPrnDC, xPage / 2, -yPage / 2);
SetViewportOrg (hPrnDC, xPage / 2, yPage / 2);
           (*lpfnAbortProc) (hPrnDC, 0) ;
           Ellipse (hPrnDC, -500, 500, 500, -500) ;
           (*lpfnAbortProc) (hPrnDC, 0) ;
           dwExtent = GetTextExtent (hPrnDC, szText, sizeof szText - 1) ;
           ptExtent = MAKEPOINT (dwExtent) ;
           TextOut (hPrnDC, -ptExtent.x / 2, ptExtent.y / 2, szText,
                                                  sizeof szText - 1) ;
           RestoreDC (hPrnDC, -1) ;
           (*lpfnAbortProc) (hPrnDC, 0) ;
           if (Escape (hPrnDC, NEXTBAND, 0, NULL, (LPSTR) &rect) < 0)
                 bError = TRUE ;
                 break ;
else
     bError = TRUE ;
if (!bError)
      0
```

```
NAME
               PRINT4
DESCRIPTION
               'Printing Program No. 4 (C) Charles Petzold, 1987'
STUB
               'WINSTUB.EXE'
CODE
               MOVEABLE
DATA
               MOVEABLE MULTIPLE
HEAPSIZE
               1024
STACKSIZE
               4096
EXPORTS
               WndProc
               AbortProc
               PrintDlgProc
```

PRINT4 differs from PRINT3 in only a few particulars. In order for *AbortProc* to be called while the program is printing, the GDI drawing routines have been moved into *PrintMyPage*. You'll notice that the *Rectangle* function prints the rectangle for each band rather than a rectangle on the border of the entire page. This allows you to see where the bands are for a particular printer. The structure of the printing operation looks like this:

The while loop for the band proceeds only if the rectangle isn't empty and the if user hasn't canceled the print job from the dialog box. PRINT4 has to check the return value from each NEXTBAND Escape call and set bError if Escape returns a negative value. If no Escape call returns an error, then the print job must either be ended with the ENDDOC Escape call or be aborted with the ABORTDOC Escape call. If the user cancels printing during the NEXTBAND loop, then the print job must be aborted using the ABORTDOC call. The code to do this is as follows:

```
if (!bError)
{
   if (bUserAbort)
       Escape (hPrnDC, ABORTDOC, 0, NULL, NULL);
   else
       Escape (hPrnDC, ENDDOC, 0, NULL, NULL);
}
```

Printing the Screen

Banding doesn't significantly improve the performance of PRINT4, because the metafiles that the GDI module would otherwise store on the disk aren't very large. Where banding is of most importance is in printing bitmaps. When you use the *BitBlt* or *StretchBlt* function calls with a printer device context as a destination, the bitmap from the source device context must be stored in the metafile. This bitmap can take up as much space in the metafile as is required for the printer output files that the GDI module eventually creates.

The WINPRTSC program, shown in Figure 16-14, demonstrates one method for drawing bitmaps on the printer. The program monitors keystrokes and prints the screen to the printer whenever it detects a Ctrl-Shift-F9 key combination. WINPRTSC works best for monochrome displays.

```
winprtsc.obj : winprtsc.c
      cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp winprtsc.c

printscr.obj : printscr.c
      cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp printscr.c

winprtsc.res : winprtsc.rc winprtsc.ico
      rc -r winprtsc.rc

winprtsc.exe : winprtsc.obj printscr.obj winprtsc.def winprtsc.res
      link4 winprtsc printscr, /align:16, /map, slibw, winprtsc
      rc winprtsc.res
```

Figure 16-14. The WINPRTSC program

```
/* WINPRTSC.C -- Windows Print Screen Utility */
#include <windows.h>
#include <string.h>
#define WM PRTSC WM USER
long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG) ;
DWORD FAR PASCAL KeyboardHook (int, WORD, LONG) ;
int
    PrintScreen () ;
        szAppName [] = "WinPrtsc" ;
szSplMsg [] = "WinPrtsc - Printing Screen" ;
char
FARPROC lpfnKeyHook, lpfnOldHook;
HANDLE hinst ;
HWND.
        hWnd :
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
     HANDLE hInstance, hPrevInstance;
     LPSTR
                  lpszCmdLine ;
                  nCmdShow ;
     static char szLoadMsq [] = "Ctrl-Shift-F9 prints screen." ;
     MSG
                   msor
     WNDCLASS
                  wndclass ;
     if (!hPrevInstance)
                                    = CS VREDRAW | CS HREDRAW ;
           wndclass.style
           wndclass.lpfnWndProc = WndProc ;
          wndclass.cbClsExtra = 0;
wndclass.cbWndExtra = 0;
wndclass.hInstance = hInstance;
wndclass.hIcon = LoadIcon (hInstance, szAppName);
wndclass.hCursor = LoadCursor (NULL, IDC ARROW);
           wndclass.hbrBackground = GetStockObject (WHITE_BRUSH) ;
           wndclass.lpszMenuName = NULL ;
           wndclass.lpszClassName = szAppName ;
           if (!RegisterClass (&wndclass))
                return FALSE ;
           hInst = hInstance ;
           hWnd = CreateWindow (szAppName, szAppName,
                                 WS OVERLAPPEDWINDOW,
                                 CW USEDEFAULT, 0,
                                 CW USEDEFAULT, 0,
                                 NULL, NULL, hInstance, NULL) ;
           ShowWindow (hWnd, SW SHOWMINNOACTIVE) ;
           UpdateWindow (hWnd) ;
           lpfnKeyHook = MakeProcInstance ((FARPROC) KeyboardHook, hInstance) ;
           lpfnOldHook = SetWindowsHook (WH KEYBOARD, lpfnKeyHook) ;
     if (nCmdShow != SW SHOWMINNOACTIVE)
           MessageBox (NULL, szLoadMsg, szAppName, MB OK | MB ICONASTERISK) ;
```

```
if (hPrevInstance)
         return FALSE ;
    while (GetMessage (&msg, NULL, 0, 0))
         TranslateMessage (&msg) ;
         DispatchMessage (&msg) ;
    return msg.wParam ;
DWORD FAR PASCAL KeyboardHook (iCode, wParam, 1Param)
    int iCode ;
    WORD wParam ;
    LONG 1Param ;
    if (iCode == HC ACTION && wParam == VK F9 &&
                              GetKeyState (VK SHIFT) < 0 &&
                              GetKeyState (VK CONTROL) < 0)
          if (HIWORD (1Param) & 0x8000)
              PostMessage (hWnd, WM PRTSC, 0, 0L) ;
         return TRUE ;
     else
         return DefHookProc (iCode, wParam, 1Param, &lpfnOldHook) ;
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
               hWnd ;
    HWND
                iMessage ;
    unsigned
                wParam ;
     WORD
                1Param ;
     LONG
    static BOOL bNowPrinting = FALSE ;
    "Printer can't print bitmaps.",
                                  "Could not create bitmap of screen.",
                                  "Error encountered during printing.",
                                  "Printing aborted by user." ) ;
     int
                 nReturnCode ;
     switch (iMessage)
          case WM PRTSC:
          if (bNowPrinting)
               MessageBox (NULL, szErrMsg [0], szAppName,
MB_OK | MB_ICONEXCLAMATION) ;
          else
               bNowPrinting = TRUE ;
               if (nReturnCode = PrintScreen ())
                    MessageBox (NULL, szErrMsg [nReturnCode], szAppName, MB_OK | MB_ICONEXCLAMATION) ;
               bNowPrinting = FALSE ;
          break ;
```

```
case WM_QUERYOPEN:
    break;

case WM_DESTROY:
    UnhookWindowsHook (WH_KEYBOARD, lpfnKeyHook);
    PostQuitMessage (0);
    break;

default:
    return DefWindowProc (hWnd, iMessage, wParam, lParam);
}
return OL;
}
```

```
/* PRINTSCR.C -- Printing Functions for WinPrtSc */
#include <windows.h>
#include <string.h>
BOOL
       bUserAbort ;
HWND
      hDlgPrint ;
extern char szAppName [] ;
extern char
               szSplMsg [] ;
extern HANDLE hinst ;
extern HWND
              hWnd ;
HDC GetPrinterDC ()
     static char szPrinter [64] ;
                  *szDevice, *szDriver, *szOutput ;
     char
     GetProfileString ("windows", "device", "", szPrinter, 64) ;
     if ((szDevice = strtok (szPrinter, "," )) &&
    (szDriver = strtok (NULL, ", ")) &&
    (szOutput = strtok (NULL, ", ")))
                return CreateDC (szDriver, szDevice, szOutput, NULL) ;
     return 0 ;
BOOL FAR PASCAL PrintDlgProc (hDlg, iMessage, wParam, 1Param)
     HWND
             hDlg ;
     unsigned iMessage ;
     WORD wParam;
DWORD 1Param;
     switch (iMessage)
           case WM INITDIALOG:
                SetWindowText (hDlg, szAppName) ;
                EnableMenuItem (GetSystemMenu (hDlg, FALSE), SC CLOSE,
                                                                   MF GRAYED) ;
                break ;
```

```
case WM COMMAND:
                bUserAbort = TRUE ;
                DestroyWindow (hDlg) ;
                hDlgPrint = 0;
                break ;
          default:
               return FALSE ;
     return TRUE ;
BOOL FAR PASCAL AbortProc (hPrnDC, nCode)
     HDC hPrnDC ;
     short nCode ;
     MSG
          msq ;
     while (!bUserAbort && PeekMessage (&msg, NULL, 0, 0, PM REMOVE))
          if (!hDlgPrint || !IsDialogMessage (hDlgPrint, &msg))
                TranslateMessage (&msg) ;
                DispatchMessage (&msg) ;
     return !bUserAbort ;
int PrintScreen ()
             bError = FALSE ;
     FARPROC lpfnAbortProc, lpfnPrintDlgProc;
     HBITMAP hBitmap ;
     HDC hScrDC, hPrnDC, hMemDC;
            nReturnCode = 0 ;
     RECT
             rect ;
     short xScreen, yScreen, xPrinter, yPrinter, xBand, yBand ;
                     /* Get Printer DC and check for RC_BITBLT */
     if (NULL == (hPrnDC = GetPrinterDC ()))
          return 1 ;
     if (!(RC BITBLT & GetDeviceCaps (hPrnDC, RASTERCAPS)))
          DeleteDC (hPrnDC) ;
          return 2 ;
     xPrinter = GetDeviceCaps (hPrnDC, HORZRES) ;
yPrinter = GetDeviceCaps (hPrnDC, VERTRES) ;
                     /* Get Screen DC and bitmap; Blt screen to Mem DC */
     hScrDC = CreateDC ("DISPLAY", NULL, NULL, NULL) ;
     xScreen = GetDeviceCaps (hScrDC, HORZRES) ;
yScreen = GetDeviceCaps (hScrDC, VERTRES) ;
```

```
if (!(hBitmap = CreateBitmap (xScreen, vScreen, 1, 1, NULL)))
     DeleteDC (hPrnDC) ;
     DeleteDC (hScrDC) :
     return 3 ;
hMemDC = CreateCompatibleDC (hScrDC) ;
SelectObject (hMemDC, hBitmap) ;
BitBlt (hMemDC, 0, 0, xScreen, yScreen, hScrDC, 0, 0, SRCCOPY) ;
DeleteDC (hScrDC) ;
                 /* Create modeless dialog box and set abort proc */
EnableWindow (hWnd, FALSE) ;
bUserAbort = FALSE :
lpfnPrintDlgProc = MakeProcInstance (PrintDlgProc, hInst) ;
hDlgPrint = CreateDialog (hInst, "PrintDlgBox", hWnd, lpfnPrintDlgProc) ;
lpfnAbortProc = MakeProcInstance (AbortProc, hInst);
Escape (hPrnDC, SETABORTPROC, 0, (LPSTR) lpfnAbortProc, NULL);
                 /* Do StretchBlt (mem DC to prn DC) for each band */
if (Escape (hPrnDC, STARTDOC, strlen (szSplMsg), szSplMsg, NULL) > 0 &&
    Escape (hPrnDC, NEXTBAND, 0, NULL, (LPSTR) &rect))
     while (!IsRectEmpty (&rect) && !bUserAbort)
            (*lpfnAbortProc) (hPrnDC, 0) ;
           xBand = rect.right - rect.left ;
           yBand = rect.bottom - rect.top ;
           StretchBlt (hPrnDC, rect.left, rect.top, xBand, yBand,
                 hMemDC, (short) ((long) rect.left * xScreen / xPrinter),
                           (short) ((long) rect.top * yScreen / yPrinter),
(short) ((long) xBand * xScreen / xPrinter),
(short) ((long) yBand * yScreen / yPrinter),
                 SRCCOPY) ;
           (*lpfnAbortProc) (hPrnDC, 0) ;
           if (Escape (hPrnDC, NEXTBAND, 0, NULL, (LPSTR) &rect) < 0)
                 bError = TRUE :
                 nReturnCode = 4 ;
                 break ;
else
```

Figure 16-14. Continued

```
bError = TRUE ;
    nReturnCode = 4 ;

    /* Clean up print termination and delete bitmap */
    /* Clean up print termination and delete bitmap */
    /*------*/

if (!bError)
    if (!bUserAbort)
        Escape (hPrnDC, ENDDOC, 0, NULL, NULL) ;

else
    Escape (hPrnDC, ABORTDOC, 0, NULL, NULL) ;

if (!bUserAbort)
    DestroyWindow (hDlgPrint) ;

else
    nReturnCode = 5 ;

EnableWindow (hWnd, TRUE) ;
FreeProcInstance (lpfnPrintDlgProc) ;
FreeProcInstance (lpfnAbortProc) ;
DeleteDC (hPrnDC) ;
DeleteDC (hMemDC) ;
DeleteObject (hBitmap) ;

return nReturnCode ;
}
```

```
#include <style.h>
WinPrtSc ICON winprtsc.ico

PrintDlgBox DIALOG 90, 80, 140, 40
STYLE WS_POPUP | WS_CAPTION | WS_SYSMENU | WS_VISIBLE | DS_ABSALIGN
BEGIN
CTEXT "Sending Screen Print to Spooler", -1, 0, 6, 140, 12
DEFPUSHBUTTON "Cancel", IDCANCEL, 54, 22, 32, 14, WS_GROUP END
```



NAME WINDRYSC DESCRIPTION 'Windows Print Screen Utility (C) Charles Petzold, 1987' 'WINSTUB.EXE' STUB CODE MOVEABLE DATA MOVEABLE MULTIPLE HEAPSIZE 1024 STACKSIZE 4096 EXPORTS WndProc KeyboardHook AbortProc PrintDlgProc

I suspect that as many readers are curious about the way that WINPRTSC intercepts keystrokes as are interested in printing bitmaps. For this reason, I've divided the program into two source code files, isolating the code required for each of these jobs. Let's look first at PRINTSCR.C, which actually does the printing.

The *PrintScreen* routine in PRINTSCR.C obtains the printer device context, the screen device context, and a memory device context. It creates a monochrome bitmap the size of the screen, selects the bitmap into the memory device context, and makes a copy of the screen using *BitBlt*. The bitmap containing the screen image is transferred to the printer with a series of *StretchBlt* calls, one for each band. *PrintScreen* scales the band dimensions to a proportional screen area using the horizontal and vertical dimensions of the screen and printer. The resultant screen image is stretched to fit the entire page.

Note that the dialog box popup window is destroyed before WINPRTSC's main window is enabled, which is opposite to the order used in PRINT3 and PRINT4. In those examples, we wanted the input focus to return to the main window when printing was completed. Because WINPRTSC is always displayed as an icon (as you'll see shortly), we don't want WINPRTSC to get the input focus. Reversing the order of the <code>DestroyWindow</code> call for the dialog box and the <code>EnableWindow</code> call for the main window prevents that.

Intercepting Keystrokes in Windows

The WINPRTSC.C file contains the WinMain and WndProc functions as well as the logic necessary to intercept all keystrokes in Windows. To accomplish this feat, we need to use the Set-WindowsHook function, which requires two parameters. The first is set to WH_KEYBOARD to intercept keystrokes. The second is a far pointer to a "hook function" that processes these keystrokes. Whenever Windows is ready to give a WM_KEYDOWN or WM_KEYUP message to a program, Windows calls the hook function first.

The hook function in WINPRTSC is called *KeyboardHook*. It must be included in the EXPORTS section of the program's module definition file. You use *MakeProcInstance* to obtain a pointer to this function:

lpfnKeyHook = MakeProcInstance ((FARPROC) KeyboardHook, hInstance);

SetWindowsHook returns the address of the previous keyboard hook function:

```
lpfnOldHook = SetWindowsHook (WH_KEYBOARD, lpfnKeyHook) ;
```

Windows maintains the address of only the most recent hook function and calls that function first. If you store this *lpfnOldHook* value in a static variable, however, several programs can call *SetWindowsHook* and get advance notice of keystrokes, thus creating what is called a "keyboard hook chain."

When a program wants to "unhook" the function and no longer receive advance notice of keystrokes, it calls *UnhookWindowsHook*. WINPRTSC does this during processing of WM_DESTROY:

```
UnhookWindowsHook (WH_KEYBOARD, lpfnKeyHook);
```

If you fail to unhook the function before your program terminates, Windows will crash the next time the user presses a key. Note that the second parameter is the original pointer returned from <code>MakeProcInstance</code> and <code>not</code> the <code>lpfnOldHook</code> pointer returned from <code>SetWindowsHook</code>.

The KeyboardHook function used in WINPRTSC looks like this:

The wParam and lParam parameters are the same as those that accompany a WM_KEYUP or WM_KEYDOWN message. The wParam parameter is the virtual key code; the high bit of lParam is 0 for a key being depressed (key down) and 1 for a key being released (key up).

KeyboardHook checks the keystroke only if iCode is equal to HC_ACTION (which is defined as 0). For all other values of iCode, the parameters and the address of the lpfnOldHook variable must be passed to DefHookProc. This function provides default processing of the keystroke.

It is important to call <code>DefHookProc</code> in the hook function. Windows relies on it. When a program unhooks itself from the keyboard hook chain using the <code>UnhookWindowsHook</code> call, Windows calls the current keyboard hook (the last keyboard hook to be registered) using an

iCode value of HC_LPLPFNNEXT (-2) or HC_LPFNNEXT (-1). Because DefHookProc passes back to Windows the address of the variable in which the program has stored the address of the previous hook function, Windows can alter the contents of this variable. For example, if you have stored in lpfnOldHook the address of a function being unhooked, Windows will change the address stored in that variable to the value stored in the equivalent variable of the program removing itself from the chain. (In Chapter 17 you'll encounter a different technique for hooking and unhooking programs that become part of the "clipboard viewer chain.")

Only if iCode is equal to HC_ACTION does KeyboardHook check to see that the key being depressed or released is VK_F9 and that both the Ctrl and Shift keys are down. If the high bit of IParam is 1 (which means that the F9 key is being released), then KeyboardHook posts a message to its own window function. If the key is being depressed or released, then KeyboardHook returns TRUE, which tells Windows to throw that key away rather than pass it to the application program that currently has the input focus.

The PostMessage call drops a message in WINPRTSC's message queue and returns. This avoids doing a lot of processing in the middle of KeyboardHook. Within KeyboardHook, things are not quite normal. Although WINPRTSC has access to its data segment (as a result of the instance thunk we created with MakeProcInstance), the stack in effect is the stack of some other program running in Windows. In Chapter 18, we'll examine some of the implications of this fact. Right now, we're taking an easy approach by doing as little processing as possible in KeyboardHook. WINPRTSC's WndProc eventually gets this posted message and calls PrintScreen. WndProc uses the bNowPrinting variable to avoid reentry problems.

Like the FREEMEM program in Chapter 6, WINPRTSC is loaded as an icon and doesn't allow itself to be displayed otherwise. When first loaded into memory, it displays the message "Ctrl-Shift-F9 prints screen" in a message box. However, when the nCmdShow parameter to WinMain is SW_SHOWMINNOACTIVE, the program doesn't display this message box. Why is this? Well, you might want to include WINPRTSC in the Load line of your WIN.INI file. This check of nCmdShow prevents WINPRTSC from displaying this message box every time you start up Windows.

THE PRINTER AND FONTS

Chapter 15 culminated in a program called JUSTIFY that uses GDI-based raster fonts to display formatted text. Programs that work with formatted text on the screen usually also need to print this text. In fact, word-processing and desktop publishing programs generally use the display solely to provide a preview of the printed output.

This is a difficult task: What you show on the display can only approximate what the printer will print. Even if the printer uses only GDI-based fonts (those fonts stored in .FON font resource files), it generally has a different resolution than the screen, meaning that the printed characters will be a slightly different size than on the display. And if the printer uses device-based fonts (fonts that are internal to the printer), the problem becomes even more

complex. For example, in the case of a printer that offers a 15-point Zapf Chancery font, you'll be approximating that on the display with a 14-point font of another typeface. Even if the user wants to print text in 14-point Times Roman, the various character widths of the printer's device-based font can differ from those of the display's GDI-based font. In short, if you're writing a program that must display formatted text destined for a printer, you can count on some work ahead. Here are some guidelines to get you started.

You'll want to let the user choose from a list of typeface names and sizes that are supported by the currently selected printer. That is, you need to enumerate the printer fonts (as we did in the FONTLIST program in Chapter 15), which requires using *EnumFonts* with a callback function. This call-back function receives a pointer to a logical font (LOGFONT) structure and a text metrics (TEXTMETRICS) structure describing each font. The call-back function also receives a short integer that indicates whether the font is a GDI-based or a device-based font. Another bit indicates whether the font is a raster font, in which case it is scalable (within limits) by integer multiples, or a vector font, in which case it is continuously scalable.

For device-based vector fonts, the call-back function will receive only one typeface size. You can check the value returned from *GetDeviceCaps* using the TEXTCAPS parameter to determine how the device can scale these vector fonts. If they can be scaled by any multiple, you might want to allow the user to specify a point size.

When you display formatted text on the screen, you want to space the text based on how it will be eventually printed. You can use GetDeviceCaps and the GETPHYSPAGESIZE Escape call to determine the size of the paper and the size of the printable area. For instance, if the paper is 8½ in. wide and the user selects left and right margins of 1 in., then you want to display text on the screen using a width of 6½ in. The "logical twips" mapping mode discussed in Chapter 15 is appropriate for this display. There's a catch, however. If the user selects a 15-point font that the printer supports, you'll have to approximate that on the display with a 14-point font—but you can't use this 14-point display font to determine the amount of 15-point text that can fit in one printed line. You must determine this instead based on the printer font. Likewise, you must use the printer font to determine how many lines fit on a page.

To format the display text, you'll need both a handle to the screen device context (to display the text on the screen) and a handle to a printer information context. You don't need a printer device context handle until you actually want to print. Follow these steps:

- Put together a logical font structure with the typeface name, the type size, and the attributes selected by the user, and select that logical font into the printer information context.
- Call GetTextMetrics for the printer information context to determine the real size and characteristics of the selected printer font. Call GetTextFace to obtain the typeface name.

- 3. Use the information obtained in Step 2 to create another logical font structure based on the size and characteristics of the printer font, and select this logical font into the screen device context. The font now selected into the screen device context closely approximates the font selected into the printer information context.
- 4. When you write the text to the display, follow the general procedure used in the fustify function of the JUSTIFY program. However, go through the GetTextExtent and SetTextJustification logic using the printer information context, but stop short of TextOut. This approach allows you to determine the amount of text that fits on each line and the number of lines that fit on a page.
- When you have established each line of text as appropriate for the printer, you can call GetTextExtent and (possibly) SetTextJustification using the screen display context. You then call TextOut to display the line.

To print the text, you'll probably use code structured like that in the POPPADP.C file combined with the logic in the *Justify* function of JUSTIFY.C. You obtain a printer device context and go through the *GetTextExtent* and *SetTextJustification* logic again, this time using *TextOut* to print each line.

SECTION V

DATA EXCHANGE AND LINKS

Chapter 17

The Clipboard

The Windows clipboard allows data to be transferred from one program to another. It is a relatively simple mechanism that doesn't require much overhead in either the program that places data in the clipboard or the program that later gets access to it.

Let's clear up one possible point of confusion right away: The CLIPBRD program that comes with Windows is *not* the clipboard. CLIPBRD.EXE is instead a "clipboard viewer" that displays the current contents of the clipboard. (We'll write our own clipboard viewer later in this chapter.) The clipboard is simply a series of functions in Windows' USER module that facilitate the exchange of memory blocks between programs.

Many programs that deal with data include an Edit menu with the options Cut, Copy, and Paste. When a user selects Cut or Copy, the program transfers data from the program to the clipboard. This data is in a particular format, such as text, a bitmap, or a metafile. When a user selects Paste from the menu, the program determines if the clipboard contains data in a format that the program can use and, if so, transfers data from the clipboard to the program.

Programs should not transfer data into or out of the clipboard without an explicit instruction from the user. For example, a user who performs a Cut or a Copy operation in one program should be able to assume that the data will remain in the clipboard until the next Cut or Copy operation or until the user employs a program—such as the revised version of BLOWUP presented in this chapter—specifically designed to manipulate the clipboard.

SIMPLE USE OF THE CLIPBOARD

We'll begin by looking at the code involved for transferring data to the clipboard (Cut and Copy) and getting access to clipboard data (Paste).

The Standard Clipboard Data Formats

Windows defines seven standard clipboard formats that have WINDOWS.H identifiers. The first five are used most frequently. These are:

- CF_TEXT—a NULL-terminated character string containing a carriage return and a
 linefeed character at the end of each line. This is the simplest form of clipboard
 data. The data to be transferred to the clipboard is stored in a global memory
 block and is transferred using the handle to the block. The memory block
 becomes the property of the clipboard, and the program that creates the block
 should not continue to use it.
- CF_BITMAP—a bitmap. The bitmap is transferred to the clipboard using the bitmap handle. Again, a program should not continue to use this bitmap after giving it to the clipboard.
- CF_METAFILEPICT—a "metafile picture." This isn't exactly the same as a metafile (described in Chapter 14). Rather, it's a metafile with some additional information in the form of a small structure of type METAFILEPICT. A program transfers a metafile picture to the clipboard using the handle to a global memory block containing this structure. The four fields of the METAFILEPICT structure are mm (int), the mapping mode for the metafile; xExt (int) and yExt (int), in simple terms, the width and height of the metafile image; and hMF (HANDLE), the handle to the metafile. (We'll discuss the xExt and yExt fields in detail later in this chapter.) After a program transfers a metafile picture to the clipboard, it should not continue to use either the global memory block containing the METAFILEPICT structure or the metafile handle, because both will be under the control of the USER module.
- CF_SYLK—a global memory block containing data in the Microsoft "Symbolic Link" format. This format is used for exchanging data between Microsoft's MultiPlan, Chart, and Excel programs. It is an ASCII format with each line terminated with a carriage return and linefeed.
- CF_DIF—a global memory block containing data in the Data Interchange Format (DIF). This is a format devised by Software Arts for use with transferring data to the VisiCalc spreadsheet program. The format is now under the control of Lotus Corporation. This is also an ASCII format with lines terminated with carriage returns and linefeeds.

The CF_SYLK and CF_DIF formats are conceptually similar to the CF_TEXT format. However, character strings containing SYLK or DIF data are not necessarily NULL-terminated, because the formats define the end of the data. (For descriptions of these two formats, see Jeff Walden, File Formats for Popular PC Software [John Wiley & Sons, 1986].)

Transferring Text to the Clipboard

Let's assume that you want to transfer a character string to the clipboard and that you have a pointer (called *pString*) to this string. This can be a near pointer if the text is stored in your program's local data segment or a far pointer if the text is stored in a global data segment. You want to transfer *wLength* bytes of this string.

First, allocate a moveable global memory block of wLength size. Include room for a terminating NULL:

```
hGlobalMemory = GlobalAlloc (GHND, (DWORD) wLength + 1) ;
```

The value of hGlobalMemory will be NULL if the block could not be allocated. If the allocation is successful, lock the block to get a far pointer to it:

```
lpGlobalMemory = GlobalLock (hGlobalMemory) ;
```

Copy the character string into the global memory block:

```
for (n = 0 ; n < wLength ; n++)
    *lpGlobalMemory++ = *pString++ ;</pre>
```

You don't need to add the terminating NULL, because the GHND flag for GlobalAlloc zeroes out the entire memory block during allocation. Unlock the block:

```
GlobalUnlock (hGlobalMemory) ;
```

Now you have a global memory handle that references a memory block containing the NULL-terminated text. To get this into the clipboard, open the clipboard and empty it:

```
OpenClipboard (hWnd) ;
EmptyClipboard () ;
```

Give the clipboard the global memory handle using the CF_TEXT identifier, and close the clipboard:

```
SetClipboardData (CF_TEXT, hGlobalMemory) ;
CloseClipboard () ;
```

You're done

Here are some rules concerning this process:

- Call OpenClipboard and CloseClipboard while processing a single message. Don't leave the clipboard open when you exit the window function. Don't let control transfer to another program (perhaps by calling SendMessage or PeekMessage) while the clipboard is open.
- Don't give the clipboard a locked memory handle.
- After you call SetClipboardData, don't continue to use the global memory block. It
 no longer belongs to your program, and you should treat the handle as invalid. If
 you need to access the data, make another copy of it or read it from the clipboard

(as described in the next section). You can also continue to reference the block between the SetClipboardData call and the CloseClipboard call, but you must use the global handle that is returned from SetClipboardData. (In most cases, this will be the same handle you pass it, but don't rely on that.) Unlock this handle before you call CloseClipboard.

Getting Text from the Clipboard

Getting text from the clipboard is only a little more complex than transferring text to the clipboard. You must first determine whether the clipboard does in fact contain data in the CF_TEXT format. One of the easiest methods is to use the call:

```
bAvailable = IsClipboardFormatAvailable (CF_TEXT) ;
```

This function returns TRUE (nonzero) if the clipboard contains CF_TEXT data. We used this function in the POPPAD program in Chapter 10 to determine whether the Paste item on the Edit menu should be enabled or grayed. *IsClipboardFormatAvailable* is one of the few clipboard functions that you can use without first opening the clipboard. However, if you later open the clipboard to get this text, you should also check again (using the same function or one of the other methods) to determine if the CF_TEXT data is still in the clipboard.

To transfer the text out, first open the clipboard:

```
OpenClipboard (hWnd) ;
```

Obtain the handle to the global memory block referencing the text:

```
hClipMemory = GetClipboardData (CF_TEXT) ;
```

This handle will be NULL if the clipboard doesn't contain data in the CF_TEXT format. This is another way to determine if the clipboard contains text. If *GetClipboardData* returns NULL, close the clipboard without doing anything else.

The handle you receive from GetClipboardData doesn't belong to your program—it belongs to the clipboard. The handle is valid only between the GetClipboardData and CloseClipboard calls. You can't free that handle or alter the data it references. If you need to have continued access to the data, you should make a copy of the memory block.

Here's one method for copying the data into your global memory segment. First, allocate a global memory block of the same size as that referenced by hClipMemory:

```
hMyMemory = GlobalAlloc (GHND, GlobalSize (hClipMemory));
```

You should check for a NULL value from GlobalAlloc to determine if the block was really allocated. If it was allocated, lock both handles and get pointers to the beginning of the blocks:

```
lpClipMemory = GlobalLock (hClipMemory) ;
lpMyMemory = GlobalLock (hMyMemory) ;
```

Because the character string is NULL-terminated, you can transfer the data using Windows' Istrcpy function (discussed in Chapter 11):

```
lstrcpy (lpMyMemory, lpClipMemory);
Or you can use some simple C code:
    while (*lpMyMemory++ = *lpClipMemory++);
Unlock both blocks:
    GlobalUnlock (hClipMemory);
    GlobalUnlock (hMyMemory);
Finally, close the clipboard:
    CloseClipboard ();
```

Now you have a global handle called hMyMemory that you can later lock to access this data.

What the Clipboard Does

The clipboard works primarily by altering the memory allocation flags of global memory blocks. When a program allocates a global memory block using the GHND flag (a combination of the GMEM_MOVEABLE and GMEM_ZEROINIT flags), the memory block is marked as belonging to the program (more precisely, the particular instance of the program). Normally, Windows deletes this memory block when the instance terminates. When a program uses SetClipboardData to give the global handle to the clipboard, Windows must transfer ownership of the memory block from the program to itself. This action requires that Windows modify the memory allocation flags of the global memory block by calling:

```
GlobalReAlloc (hMem, OL, GMEM_MODIFY | GMEM_DDESHARE) ;
```

The USER module establishes ownership of the memory block. After the SetClipboard-Data call, the global memory handle no longer belongs to the program that allocated it, and the block won't be freed when the program terminates. The program that created the memory block can't continue to use it except when the clipboard gives the program access to the block. Now the USER module must explicitly free the memory block, which it does when a program calls EmptyClipboard.

When a program calls GetClipboardData, Windows gives the program making the call the handle to the global memory block and allows the program temporary access to the memory block. The program can then copy this data into another global memory block or a local memory block. Thus the clipboard is really just a manager of shared memory segments. One program gives the clipboard a block of global memory. Other programs can get access to the block. The clipboard retains ownership of it.

Opening and Closing the Clipboard

Only one program can have the clipboard open at any time. The purpose of the *OpenClip-board* call is to prevent the clipboard contents from changing while a program is using the clipboard. *OpenClipboard* returns a BOOL value indicating whether the clipboard was successfully opened. It will not be opened if another application failed to close it. During the early stages of programming for the clipboard, you should probably check this value, but the check isn't crucial in a nonpreemptive multitasking environment. If every program politely opens and then closes the clipboard during a single message without giving control to other programs, then you'll never run into the problem of being unable to open the clipboard.

I've already mentioned avoiding the use of SendMessage or PeekMessage while the clipboard is open, but watch out for a more subtle problem involving message boxes: If you can't allocate a global memory segment to copy the contents of the clipboard, you might want to display a message box. If this message box isn't system modal, however, the user can switch to another application while the message box is displayed. You should either make the message box system modal or close the clipboard before you display the message box.

You can also run into problems if you leave the clipboard open while you display a dialog box. Edit fields in a dialog box use the clipboard for cutting and pasting text.

Using the Clipboard with Bitmaps

In using the CF_BITMAP format, you give the clipboard a handle to a bitmap when calling SetClipboardData. The GetClipboardData function returns a handle to a bitmap.

You may recall the BLOWUP program from Chapter 5, which allowed you to block out any part of the display and copy it to BLOWUP's client area. BLOWUP used *StretchBlt* to expand or compress the size of the blocked-out area so that it exactly fit the client area. The program had a problem, however: If part of BLOWUP's client area was destroyed (perhaps by an overlapping window from another program), BLOWUP couldn't recreate it. We could have solved that problem by creating a bitmap based on the size of the area BLOWUP was copying. When BLOWUP needed to redisplay the bitmap in its client area, it could have selected the bitmap into a memory device context and used *StretchBlt* to copy it to the client area.

Let's go one step further and write a revised version of BLOWUP that uses the clipboard to hold onto this bitmap. This approach provides two advantages:

- Any part of the display can now be copied in bitmap format and stored in the clipboard.
- Any bitmap that is stored in the clipboard can be copied into and scaled to the size
 of BLOWUP's client area. You can then block out all or part of this display and copy
 that to the clipboard. This provides an easy manual approach to scaling or
 cropping bitmaps.

Later in this chapter, we'll write a program called CLIPFILE, through which a bitmap in the clipboard can be saved to a file with the extension .BMP. When you use CLIPFILE in conjunction with BLOWUP, you can block out almost any part of the display and save it as a bitmap file.

The Revised BLOWUP Program

The revised BLOWUP program is shown in Figure 17-1. You use it the same way as the earlier BLOWUP program. First, click the mouse in BLOWUP's client area. The cursor changes to a cross hair. Now place the cursor on one corner of the rectangle you want to capture, press the mouse button, drag the mouse to the opposite corner, and release the button.

```
blowup.obj : blowup.c
cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp blowup.c
blowup.exe : blowup.obj blowup.def
link4 blowup, /align:16, /map, slibw, blowup
```

```
/* BLOWUP.C -- Capture Screen Image to Clipboard */
#include <windows.h>
#include <stdlib.h>
long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG) ;
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
    HANDLE hInstance, hPrevInstance;
LPSTR lpszCmdLine;
             nCmdShow ;
    static char szAppName [] = "Blowup" ;
    HWND hWnd;
             msq ;
    WNDCLASS wndclass ;
    if (!hPrevInstance)
        wndclass.cbWndExtra = 0;
        wndclass.hInstance = hInstance ;
        wndclass.hbrBackground = GetStockObject (WHITE BRUSH) ;
        wndclass.lpszMenuName = NULL ;
        wndclass.lpszClassName = szAppName ;
        if (!RegisterClass (&wndclass))
            return FALSE ;
```

Figure 17-1. The BLOWUP program

Figure 17-1. Continued

```
hWnd = CreateWindow (szAppName, szAppName,
                          WS OVERLAPPEDWINDOW,
                          CW USEDEFAULT, 0,
                          CW USEDEFAULT, 0,
NULL, NULL, hInstance, NULL) ;
     ShowWindow (hWnd, nCmdShow) ;
     UpdateWindow (hWnd) :
     while (GetMessage (&msg, NULL, 0, 0))
          TranslateMessage (&msg) ;
          DispatchMessage (&msg) ;
     return msg.wParam ;
void InvertBlock (hWnd, org, len)
     HWND hWnd ;
     POINT org, len ;
     HDC
           hDC :
    hDC = CreateDC ("DISPLAY", NULL, NULL, NULL) ;
    ClientToScreen (hWnd, &org);
PatBlt (hDC, org.x, org.y, len.x, len.y, DSTINVERT);
     DeleteDC (hDC) ;
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
    HWND
                hWnd ;
     unsigned
                 iMessage ;
                  wParam ;
     WORD
     LONG
                 lParam :
     static BOOL bCapturing, bBlocking ;
     static POINT org, len ;
     static short xClient, yClient ;
                  bm ;
     BITMAP
     HDC
                  hDC, hMemDC ;
     HBITMAP
                 hBitmap ;
     PAINTSTRUCT ps ;
     switch (iMessage)
          case WM SIZE:
               xClient = LOWORD (lParam) ;
               yClient = HIWORD (1Param) ;
               break ;
          case WM LBUTTONDOWN:
               if (!bCapturing)
                     bCapturing = TRUE ;
                     SetCapture (hWnd) ;
                     SetCursor (LoadCursor (NULL, IDC CROSS)) ;
               else if (!bBlocking)
                     bBlocking = TRUE ;
                     org = MAKEPOINT (1Param) ;
               break ;
```

```
case WM MOUSEMOVE:
     if (bCapturing)
           SetCursor (LoadCursor (NULL, IDC CROSS)) ;
     if (bBlocking)
           len = MAKEPOINT (1Param) ;
          len.x -= org.x ;
           len.y -= org.y :
          InvertBlock (hWnd, org, len) :
InvertBlock (hWnd, org, len) ;
     break ;
case WM LBUTTONUP:
     if (!bBlocking)
          break ;
     bCapturing = bBlocking = FALSE ;
SetCursor (LoadCursor (NULL, IDC_ARROW)) ;
ReleaseCapture () ;
     if (len.x == 0 || len.y == 0)
           break ;
     hDC = GetDC (hWnd) ;
     hMemDC = CreateCompatibleDC (hDC) ;
     hBitmap = CreateCompatibleBitmap (hDC,
                           abs (len.x), abs (len.y)) ;
     if (hBitmap)
           SelectObject (hMemDC, hBitmap) ;
           StretchBlt (hMemDC, 0, 0, abs (len.x), abs (len.y),
                hDC, org.x, org.y, len.x, len.y, SRCCOPY) ;
           OpenClipboard (hWnd) ;
           EmptyClipboard () ;
           SetClipboardData (CF_BITMAP, hBitmap) ;
           CloseClipboard () ;
           InvalidateRect (hWnd, NULL, TRUE) ;
      else
           MessageBeep (0) ;
      DeleteDC (hMemDC) ;
      ReleaseDC (hWnd, hDC) ;
      break ;
case WM PAINT:
      InvalidateRect (hWnd, NULL, TRUE) ;
      hDC = BeginPaint (hWnd, &ps) ;
      OpenClipboard (hWnd) ;
      if (hBitmap = GetClipboardData (CF_BITMAP))
            SetCursor (LoadCursor (NULL, IDC_WAIT)) ;
           hMemDC = CreateCompatibleDC (hDC) ;
           SelectObject (hMemDC, hBitmap) ;
           GetObject (hBitmap, sizeof (BITMAP), (LPSTR) &bm) ;
```

Figure 17-1. Continued

```
SetStretchBltMode (hDC, COLORONCOLOR);
StretchBlt (hDC, 0, 0, xClient, yClient,
hMemDC, 0, 0, bm.bmWidth, bm.bmHeight,
SRCCOPY);

SetCursor (LoadCursor (NULL, IDC_ARROW));
DeleteDC (hMemDC);

CloseClipboard ();
EndPaint (hWnd, &ps);
break;

case WM_DESTROY:
PostQuitMessage (0);
break;

default:
return DefWindowProc (hWnd, iMessage, wParam, lParam);

return 0L;
}

return OL;
```

```
NAME BLOWUP
DESCRIPTION 'Capture Screen Image to Clipboard (C) Charles Petzold, 1987'
STUB 'WINSTUB.EXE'
CODE MOVEABLE
DATA MOVEABLE MULTIPLE
HEAPSIZE 1024
STACKSIZE 4096
EXPORTS WndProc
```

In the earlier BLOWUP program, the blocked-out section of the display was copied to BLOWUP's client area. In the new version, the area of the display is copied to a bitmap in a memory device context, and the bitmap is transferred to the clipboard.

When you're blocking out an area of the display with the mouse, BLOWUP retains two structures of type POINT with the initial corner (org, for "origin") and the width and height of the rectangle (len, for "length"). If the org point isn't the upper left corner of the rectangle, then one or both of the values in len will be negative. When the mouse button is released (signaling to the program that the user has finished blocking out the rectangle), BLOWUP creates a memory device context and a bitmap using the absolute values of the lengths in the len point structure:

If BLOWUP succeeds in creating this bitmap, the program selects the bitmap into the memory device context and uses *StretchBlt* to copy the blocked-out area of the display:

Although we're using *StretchBlt* here, the image is not being stretched or compressed. However, if you block out the rectangle from right to left, then *StretchBlt* is needed to flip the image around a vertical axis. Similarly, if you block it out from bottom to top, then *StretchBlt* turns it upside down.

The program then opens and empties the clipboard, transfers the bitmap to the clipboard, and closes the clipboard:

```
OpenClipboard (hWnd) ;
EmptyClipboard () ;
SetClipboardData (CF_BITMAP, hBitmap) ;
CloseClipboard () ;
```

The bitmap is now the responsibility of the clipboard. Do not delete it! The clipboard will delete the bitmap itself the next time it gets an *EmptyClipboard* call.

Because the clipboard contains a new bitmap, BLOWUP invalidates its own client area:

```
InvalidateRect (hWnd, NULL, TRUE) ;
}
```

If BLOWUP wasn't successful in creating a bitmap, it beeps:

```
else
MessageBeep (0);
```

Finally, the memory device context is deleted, and the window's device context is released:

```
DeleteDC (hMemDC) ;
ReleaseDC (hWnd, hDC) ;
```

When BLOWUP gets a WM_PAINT message, it opens the clipboard and checks to see if a bitmap is available:

```
OpenClipboard (hWnd) ;
if (hBitmap = GetClipboardData (CF_BITMAP))
```

If the clipboard contains a bitmap, BLOWUP creates a memory device context and selects the bitmap from the clipboard into the device context:

```
hMemDC = CreateCompatibleDC (hDC) ;
SelectObject (hMemDC, hBitmap) ;
```

To copy the dimensions of this bitmap into a BITMAP structure, BLOWUP uses GetObject:

```
GetObject (hBitmap, sizeof (BITMAP), (LPSTR) &bm);
```

It can then copy the bitmap to the client area, stretching it to the larger or smaller dimensions:

```
SetStretchBltMode (hDC, COLORONCOLOR);
StretchBlt (hDC, 0, 0, xClient, yClient,
hMemDC, 0, 0, bm.bmWidth, bm.bmHeight,
SRCCOPY);
```

The only cleanup involved is deleting the memory device context:

```
DeleteDC (hMemDC) ;
}
```

and closing the clipboard:

```
CloseClipboard ();
```

The bitmap isn't deleted, because it belongs to the clipboard.

If we wanted to make an exact copy of the bitmap, we could use GetObject to obtain the dimensions:

```
GetObject (hBitmap, sizeof (BITMAP), (LPSTR) &bm);
```

and create a new bitmap and another memory device context:

```
hMyBitmap = CreateBitmapIndirect (&bm) ;
hMyMemDC = CreateCompatibleDC (hDC) ;
SelectObject (hMyMemDC, hMyBitmap) ;
```

A simple BitBlt copies the bitmap:

```
BitBlt (hMyMemDC, 0, 0, bm.bmWidth, bm.bmHeight,
hMemDC, 0, 0, SRCCOPY);
```

You would then delete the two memory device contexts.

Although BLOWUP will display in its client area any bitmap that is currently in the clipboard, it checks the contents of the clipboard only when it gets a WM_PAINT message. For instance, if you draw something in the Windows PAINT program, block it out, and copy it to the clipboard, BLOWUP's client area won't show this new bitmap until BLOWUP gets a WM_PAINT message. For this reason, BLOWUP isn't a true clipboard viewer. We'll examine clipboard viewers later in this chapter.

The Metafile and the Metafile Picture

Using the clipboard to transfer metafiles from one program to another involves complexities not present when dealing with text and bitmaps. You can determine the length of a NULL-terminated string by simply searching for the NULL terminator. You can determine the dimensions of a bitmap using *GetObject*. But if you have a handle to a metafile, how can you determine how large the image will be when you play the metafile? Unless you start digging into the internals of the metafile itself, you can't.

Moreover, when a program obtains a metafile from the clipboard, it has the most flexibility in working with it if the metafile has been designed to be played in an MM_ISOTROPIC or MM_ANISOTROPIC mapping mode. The program that receives the metafile can then scale the image by simply setting viewport extents before playing the metafile. But if the mapping mode is set to MM_ISOTROPIC or MM_ANISOTROPIC within the metafile, then the program that receives the metafile is stuck. The program can make GDI calls only before or after the metafile is played. It can't make a GDI call in the middle of a metafile.

To solve these problems, metafile handles are not directly put into the clipboard and retrieved by other programs. Instead, the metafile handle is part of a "metafile picture," which is a structure of type METAFILEPICT. This structure allows the program that obtains the metafile picture from the clipboard to set the mapping mode and viewport extents itself before playing the metafile.

The METAFILEPICT structure is 8 bytes long and has four fields: mm (int), the mapping mode; xExt(int) and yExt(int), the width and height of the metafile image; and hMF(WORD), the handle to the metafile. For all the mapping modes except MM_ISOTROPIC and MM_ANISOTROPIC, the xExt and yExt values are the size of the image in units of the mapping mode given by mm. With this information, the program that copies the metafile picture structure from the clipboard can determine how much display space the metafile will encompass when it is played. The program that creates the metafile can set these values to the largest x and y coordinates it uses in the GDI drawing functions that enter the metafile.

For the MM_ISOTROPIC and MM_ANISOTROPIC mapping modes, the xExt and yExt fields function differently. You will recall from Chapter 12 that a program uses the MM_ISOTROPIC or MM_ANISOTROPIC mapping mode when it wants to use arbitrary logical units in GDI functions independent of the measurable size of the image. A program uses MM_ISOTROPIC when it wants to maintain an aspect ratio regardless of the size of the viewing surface and MM_ANISOTROPIC when it doesn't care about the aspect ratio. You will also recall from Chapter 12 that after a program sets the mapping mode to MM_ISOTROPIC or MM_ANISOTROPIC, it generally makes calls to SetWindowExt and SetViewportExt. The Set-WindowExt call uses logical units to specify the units the program wants to use when drawing. The SetViewportExt call uses device units based on the size of the viewing surface (for instance, the size of the window's client area).

If a program creates an MM_ISOTROPIC or MM_ANISOTROPIC metafile for the clipboard, the metafile should not itself contain a call to SetViewportExt, because the device units in that call would be based on the display surface of the program creating the metafile and not on the display surface of the program that reads the metafile from the clipboard and plays it. Instead, the xExt and yExt values should assist the program that obtains the metafile from the clipboard in setting appropriate viewport extents for playing the metafile. But the metafile itself contains a call to set the window extent when the mapping mode is MM_ISOTROPIC or MM_ANISOTROPIC. The coordinates of the GDI drawing functions within the metafile are based on these window extents.

The program that creates the metafile and metafile picture follows these rules:

- The mm field of the METAFILEPICT structure is set to specify the mapping mode.
- For mapping modes other than MM_ISOTROPIC and MM_ANISOTROPIC, the xExt and yExt fields are set to the width and height of the image in units corresponding to the mm field. For metafiles to be played in an MM_ISOTROPIC or MM_ANISOTROPIC environment, matters get a little more complex. For MM_ANISOTROPIC, 0 values of xExt and yExt are used when the program is suggesting neither a size nor an aspect ratio for the image. For MM_ISOTROPIC or MM_ANISOTROPIC, positive values of xExt and yExt indicate a suggested width and height of the image in units of 0.01 mm (MM_HIMETRIC units). For MM_ISOTROPIC, negative values of xExt and yExt indicate a suggested aspect ratio of the image but not a suggested size.
- For the MM_ISOTROPIC and MM_ANISOTROPIC mapping modes, the metafile itself
 contains calls to SetWindowExt and (possibly) SetWindowOrg. That is, the
 program that creates the metafile calls these functions in the metafile device
 context. Generally, the metafile will not contain calls to SetMapMode,
 SetViewportExt, or SetViewportOrg.
- The metafile should be a memory-based metafile, not a disk-based metafile.

Here's some sample code for a program creating a metafile and copying it to the clipboard. If the metafile uses the MM_ISOTROPIC or MM_ANISOTROPIC mapping mode, the first calls in the metafile should be to set the window extent. (The window extent is fixed in the other mapping modes.) Regardless of the mapping mode, the window origin can also be set:

```
hMetaDC = CreateMetaFile (NULL);
SetWindowExt (hMetaDC, ...);
SetWindowOrg (hMetaDC, ...);
```

The coordinates in the drawing functions of the metafile are based on these window extents and the window origin. After the program uses GDI calls to draw on the metafile device context, the metafile is closed to get a handle to the metafile:

```
hMF = CloseMetaFile (hMetaDC) ;
```

The program also needs to define a far pointer to a structure of type METAFILEPICT and allocate a block of global memory for this structure:

```
GLOBALHANDLE hGMem;
LPMETAFILEPICT lpMFP;

[other program lines]

hGMem = GlobalAlloc (GHND, (DWORD) sizeof (METAFILEPICT));

lpMFP = (LPMETAFILEPICT) GlobalLock (hGMem);
```

Next, the program sets the four fields of this structure.

```
lpMFP->mm = MM_...;
lpMFP->xExt = ...;
lpMFP->yExt = ...;
lpMFP->hMF = hMF;
GlobalUnlock (hGMem);
```

The program then transfers the global memory block containing the metafile picture structure to the clipboard:

```
OpenClipboard (hWnd) ;
EmptyClipboard () ;
SetClipboardData (CF_METAFILEPICT, hGMem) ;
CloseClipboard () ;
```

Following these calls, the hGMem handle (the memory block containing the metafile picture structure) and the hMF handle (the metafile itself) become invalid for the program that created them.

Now for the hard part—when a program obtains a metafile from the clipboard and plays this metafile, it must do the following:

- The program uses the mm field of the metafile picture structure to set the mapping mode.
- For mapping modes other than MM_ISOTROPIC or MM_ANISOTROPIC, the program
 uses the xExt and yExt values to set a clipping rectangle or simply to determine
 the size of the image. For the MM_ISOTROPIC and MM_ANISOTROPIC mapping
 modes, the program uses xExt and yExt to set the viewport extents.
- The program then plays the metafile.

Here's the code. You first open the clipboard, get the handle to the metafile picture structure, and lock it:

```
OpenClipboard (hWnd) ;
hGMem = GetClipboardData (CF_METAFILEPICT) ;
lpMFP = (LPMETAFILEPICT) GlobalLock (hGMem) ;
```

You can then save the attributes of your current device context and set the mapping mode to the mm value of the structure:

```
SaveDC (hDC);
SetMappingMode (lpMFP->mm);
```

If the mapping mode isn't MM_ISOTROPIC or MM_ANISOTROPIC, you can set a clipping rectangle to the values of xExt and yExt. Because these values are in logical units, you have to use LPtoDP to convert the coordinates to device units for the clipping rectangle. Or you can simply save the values so you know how large the image is.

For the MM_ISOTROPIC or MM_ANISOTROPIC mapping mode, you use xExt and yExt to set the viewport extent. One possible function to perform this task is shown below. This function assumes that xClient and yClient represent the pixel height and width of the area in which you want the metafile to appear if no suggested size is implied by xExt and yExt.

```
void PrepareMetaFile (hDC, lpmfp, xClient, yClient)
    HDC
                   hDC ;
    LPMETAFILEPICT lpmfp ;
    short
                  xClient, yClient;
    long
                  xlScale, ylScale, lScale;
    SetMapMode (hDC, 1pmfp->mm);
    if (lpmfp->mm == MM_ISOTROPIC | lpmfp->mm == MM_ANISOTROPIC)
         if (lpmfp->xExt == 0)
              SetViewportExt (hDC, xClient, yClient);
         else if (lpmfp->xExt > 0)
              SetViewportExt (hDC,
                   (short) ((long) lpmfp->xExt *
                             GetDeviceCaps (hDC, HORZRES) /
                        GetDeviceCaps (hDC, HORZSIZE) / 100),
                   (short) ((long) lpmfp->yExt *
                             GetDeviceCaps (hDC, VERTRES) /
                             GetDeviceCaps (hDC, VERTSIZE) / 100));
         else if (lpmfp->xExt < 0)
              xiScale = 100L * (long) xClient *
                                       GetDeviceCaps (hDC, HORZSIZE) /
                                       GetDeviceCaps (hDC, HORZRES) /
                                            -lpmfp->xExt ;
              ylScale = 100L * (long) yClient *
                                       GetDeviceCaps (hDC, VERTSIZE) /
                                       GetDeviceCaps (hDC, VERTRES) /
                                            -lpmfp->yExt ;
              1Scale = min (x1Scale, y1Scale) ;
```

This code assumes that both xExt and yExt are 0, greater than 0, or less than 0, (which should be the case). If the extents are 0, no size or aspect ratio is suggested. The viewport extents are set to the area in which you want to display the metafile. Positive values of xExt and yExt are a suggested image size in units of 0.01 mm. The GetDeviceCaps function assists in determining the number of pixels per 0.01 mm, and this value is multiplied by the extent values in the metafile picture structure. Negative values of xExt and yExt indicate a suggested aspect ratio but not a suggested size. The value lScale is first calculated based on the aspect ratio of the size in millimeters corresponding to xClient and yClient. This scaling factor is then used to set a viewport extent in pixels.

With this job out of the way, you can set a viewport origin if you want, play the metafile, and return the device context to normal:

```
PlayMetaFile (lpMFP->hMF);
RestoreDC (hDC, -1);
```

Then you unlock the memory block and close the clipboard:

```
GlobalUnlock (hGMem);
CloseClipboard ();
```

We'll explore the problems of dealing with metafiles in the CLIPFILE program shown later in this chapter. You may also be interested to know that the CLIPBRD program that comes with Windows doesn't precisely follow the rules that I've stated here. If the clipboard contains an MM_ISOTROPIC or MM_ANISOTROPIC metafile picture, CLIPBRD assumes that the xExt and yExt values are 0 and simply sets the viewport extents to the size of its client area. This approach lets CLIPBRD always display the metafile image within its client area.

BEYOND SIMPLE CLIPBOARD USE

In using text and bitmaps, you've seen that transferring data to the clipboard requires four calls after the data has been prepared:

```
OpenClipboard (hWnd);
EmptyClipboard ();
SetClipboardData (wFormat, hHandle);
CloseClipboard ();
```

Getting access to this data requires three calls:

```
OpenClipboard (hWnd) ;
hHandle = GetClipboardData (wFormat) ;
    lother program lines/
CloseClipboard () ;
```

You can make a copy of the clipboard data or use it in some other manner between the *Get-ClipboardData* and *CloseClipboard* calls. That approach may be all you'll need for most purposes, but you can also use the clipboard in more sophisticated ways.

Using Multiple Data Items

When you open the clipboard to put data into it, you must call *EmptyClipboard* to signal Windows to free or delete the contents of the clipboard. You can't add something to the existing contents of the clipboard. So in this sense, the clipboard holds only one item at a time.

However, between the *EmptyClipboard* and the *CloseClipboard* calls, you can call *SetClipboardData* several times, each time using a different clipboard format. For instance, if you want to store a short string of text in the clipboard, you can create a metafile device context and write that text to the metafile. You can also create a bitmap large enough to hold the character string, select the bitmap into a memory device context, and write the string to the bitmap. In this way, you make that character string available not only to programs that can read text from the clipboard but also to programs that read bitmaps and metafiles from the clipboard. Moreover, if you select a different font into the metafile device context or memory device context before writing the text, programs that read bitmaps or metafiles will use the string with this different font. (Of course, these programs won't be able to recognize the metafile or bitmap as actually containing a character string.)

If you want to write several handles to the clipboard, you call SetClipboardData for each of them:

```
OpenClipboard (hWnd) ;
EmptyClipboard () ;

SetClipboardData (CF_TEXT, hGMemText) ;
SetClipboardData (CF_BITMAP, hBitmap) ;
SetClipboardData (CF_METAFILEPICT, hGMemMFP) ;
CloseClipboard () ;
```

While these three formats of data are in the clipboard, an *IsClipboardFormatAvailable* call with the CF_TEXT, CF_BITMAP, or CF_METAFILEPICT argument will return TRUE. A program can get access to these handles by calling:

```
hGMemText = GetClipboardData (CF_TEXT) ;

or:

hBitmap = GetClipboardData (CF_BITMAP) ;
```

or:

```
hGMemMFP = GetClipboardData (CF_METAFILEPICT) ;
```

The next time a program calls *EmptyClipboard*, Windows will free or delete all three of the handles retained by the clipboard as well as the metafile that is part of the METAFILEPICT structure.

A program can determine all the formats stored by the clipboard by first opening the clipboard and calling *EnumClipboardFormats*. Start off by setting a variable *wFormat* to 0:

```
wFormat = 0 ;
OpenClipboard (hWnd) ;
```

Now make successive *EnumClipboardFormats* calls starting with the 0 value. The function will return a positive *wFormat* value for each format currently in the clipboard. When the function returns 0, you're done:

You can obtain the number of different formats currently in the clipboard by calling:

```
nCount = CountClipboardFormats ();
```

Delayed Rendering

When you put data into the clipboard, you generally make a copy of the data and give the clipboard a handle to a global memory block that contains the copy. For very large data items, this approach can waste memory. If the user never pastes that data into another program, it will continue to occupy memory space until it is replaced by something else.

You can avoid this problem by using a technique called "delayed rendering," in which your program doesn't actually supply the data until another program needs it. Rather than give Windows a handle to the data, you simply use a NULL in the SetClipboardData call:

```
OpenClipboard (hWnd);
EmptyClipboard ();
SetClipboardData (wFormat, NULL);
CloseClipboard ();
```

You can have multiple SetClipboardData calls using different values of wFormat. You can use NULL parameters with some of them and real handles with others.

That's simple enough, but now the process gets a little more complex. When another program calls *GetClipboardData*, Windows will check to see if the handle for that format is NULL. If it is, Windows will send a message to the "clipboard owner" (your program) asking for a real handle to the data. Your program must then supply this handle.

More specifically, the "clipboard owner" is the last window that put data into the clipboard. Windows can identify the clipboard owner, because the *OpenClipboard* call requires a window handle. (Because programs can also call *OpenClipboard* when reading data from the clipboard or enumerating clipboard formats, it's really the *EmptyClipboard* call that establishes this window handle as the clipboard owner.)

A program that uses delayed rendering has to process three messages in its window function: WM_RENDERFORMAT, WM_RENDERALLFORMATS, and WM_DESTROYCLIPBOARD. Windows sends your window function a WM_RENDERFORMAT message when another program calls GetClipboardData. The value of wParam is the format requested. When you process the WM_RENDERFORMAT message, don't open and empty the clipboard. Simply create a global memory block for the format given by wParam, transfer the data to it, and call SetClipboardData with the correct format and the global handle. Obviously, you'll need to retain information in your program in order to construct this data properly when processing WM_RENDERFORMAT. When another program calls EmptyClipboard, Windows sends your program a WM_DESTROYCLIPBOARD message. This tells you that the information to construct the clipboard data is no longer needed. You are no longer the clipboard owner.

If your program terminates while it is still the clipboard owner, and the clipboard still contains NULL data handles that your program set with <code>SetClipboardData</code>, you'll receive a WM_RENDERALLFORMATS message. You should open the clipboard, empty it, put the data in global memory blocks, and call <code>SetClipboardData</code> for each format. Then close the clipboard. The WM_RENDERALLFORMATS message is one of the last messages your window function receives. It is followed by a WM_DESTROYCLIPBOARD message (because you've rendered all the data) and then the normal WM_DESTROY.

If your program can transfer only one format of data to the clipboard (text, for instance), you can combine the WM_RENDERALLFORMATS and WM_RENDERFORMAT processing. The code will look something like this:

If your program uses several clipboard formats, then you will want to process the WM_RENDERFORMAT message only for the format requested by wParam. You don't need to process the WM_DESTROYCLIPBOARD message unless it is burdensome for your program to retain the information necessary to construct the data.

Private Data Formats

So far we've dealt with only the five standard clipboard formats defined by Windows. However, you may want to use the clipboard to store a "private data format." The Windows WRITE program uses this technique to store text that contains font and formatting information.

At first, this concept may seem nonsensical. If the purpose of the clipboard is to transfer data between applications, why should the clipboard contain data that only one application understands? The answer is simple: The clipboard also exists to allow the transfer of data between different instances of the same program, and these instances obviously understand the same private formats.

There are several ways to use private data formats. The easiest involves data that is ostensibly in one of the standard clipboard formats (text, bitmap, or metafile) but that has meaning only to your program. In this case, you use one of the following *wFormat* values in your *SetClipboardData* and *GetClipboardData* calls: CF_DSPTEXT, CF_DSPBITMAP, or CF_DSPMETAFILEPICT. DSP stands for "display"—these formats allow CLIPBRD to display the data as text, a bitmap, or a metafile. However, another program that calls *GetClipboardData* using the normal CF_TEXT, CF_BITMAP, or CF_METAFILEPICT format won't obtain this data.

If you use one of these formats to put data into the clipboard, you must also use the same format to get the data out. But how do you know if the data is from another instance of your program or from another program using one of these formats? Here's one way: You can first obtain the clipboard owner by calling:

```
hWndClipOwner = GetClipboardOwner () ;
```

You can then get the name of the window class of this window handle:

If the class name is the same as your program's, then the data was put into the clipboard by another instance of your program.

The second way to use private formats involves the CF_OWNERDISPLAY flag. The global memory handle to SetClipboardData is NULL:

```
SetClipboardData (CF_OWNERDISPLAY, NULL) ;
```

This is the method that WRITE uses to show formatted text in the client area of the CLIPBRD clipboard viewer. Obviously, CLIPBRD.EXE doesn't know how to display this formatted text. When WRITE specifies the CF_OWNERDISPLAY format, WRITE is taking responsibility for painting CLIPBRD's client area.

Because the global memory handle is NULL, a program that calls SetClipboardData with the CF_OWNERDISPLAY format (the clipboard owner) must process the delayed rendering messages sent to the clipboard owner by Windows as well as five additional messages. These five messages are sent by the clipboard viewer to the clipboard owner:

- WM_ASKCBFORMATNAME—The clipboard viewer sends this message to the clipboard owner to get a name for the format of the data. The *IParam* parameter is a pointer to a buffer, and *wParam* is the maximum number of characters for this buffer. The clipboard owner must copy the name of the clipboard format into this buffer.
- WM_SIZECLIPBOARD—This message tells the clipboard owner that the size of the clipboard viewer's client area has changed. The wParam parameter is a handle to the clipboard viewer, and IParam is a pointer to a RECT structure containing the new size. If the RECT structure contains all zeroes, the clipboard viewer is being destroyed or made an icon. Although CLIPBRD.EXE allows only one instance of itself to be running, other clipboard viewers can also send this message to the clipboard owner. Handling these multiple clipboard viewers isn't impossible for the clipboard owner (given that wParam identifies the particular viewer), but it isn't easy, either.
- WM_PAINTCLIPBOARD—This message tells the clipboard owner to update the clipboard viewer's client area. Again, wParam is a handle to the clipboard viewer's window. The lParam parameter is a pointer to a PAINTSTRUCT structure. The clipboard owner can obtain a handle to the clipboard viewer's device context from the hdc field of this structure.
- WM_HSCROLLCLIPBOARD and WM_VSCROLLCLIPBOARD—These messages inform
 the clipboard owner that a user has scrolled the clipboard viewer's scroll bars. The
 wParam parameter is a handle to the clipboard viewer's window, the low word of
 lParam is the scrolling request (the same as wParam in normal scroll bar messages), and the high word of lParam is the thumb position if the low word is
 SB_THUMBPOSITION. (This value is the same as the low word of lParam in a
 normal scroll bar message.)

Handling these messages may look like more trouble than it's worth. However, the process does provide a benefit to the user: When copying text from WRITE to the clipboard, the user will find it comforting to see the text still formatted in CLIPBRD's client area.

The third way to use private clipboard data formats is to register your own clipboard format name. You supply a name for this format to Windows, and Windows gives your program a number to use as the format parameter in SetClipboardData and GetClipboardData. Programs that use this method generally also copy data to the clipboard in one of the standard formats. This approach allows CLIPBRD.EXE to display data in its client area (without

the hassles involved with CF_OWNERDISPLAY) and permits other programs to copy data from the clipboard.

As an example, let's assume we've written a vector drawing program that copies data to the clipboard in a bitmap format, a metafile format, and its own registered clipboard format. CLIPBRD.EXE will display the metafile. Other programs that can read bitmaps or metafiles from the clipboard will obtain those formats. However, when the vector drawing program itself needs to read data from the clipboard, it will copy the data in its own registered format, because that format probably contains more information than the bitmap or metafile.

A program registers a new clipboard format by calling:

```
wFormat = RegisterClipboardFormat (lpszFormatName) ;
```

The wFormat value is between 0xC000 and 0xFFFF. A clipboard viewer (or a program that obtains all the current clipboard formats by calling EnumClipboardFormats) can obtain the ASCII name of this format by calling:

```
GetClipboardFormatName (wFormat, lpsBuffer, nMaxCount) ;
```

Windows copies up to nMaxCount characters into lpsBuffer.

Programmers who use this method for copying data to the clipboard might want to publicize the format name and the actual format of the data. If the program becomes popular, other programs can then copy data in this format from the clipboard.

BECOMING A CLIPBOARD VIEWER

A program that is notified of changes in the clipboard contents is called a "clipboard viewer." The CLIPBRD program that comes with Windows is a clipboard viewer, but you can also write your own clipboard viewer program. Clipboard viewers are notified of changes to the clipboard through messages to the viewer's window function.

The Clipboard Viewer Chain

Any number of clipboard viewer applications can be running in Windows at the same time, and they can all be notified of changes to the clipboard. From Windows' perspective, however, there is only one clipboard viewer, which I'll call the "current clipboard viewer." Windows maintains only one window handle to identify the current clipboard viewer, and it sends messages only to that window when the contents of the clipboard change.

Clipboard viewer applications have the responsibility of participating in the "clipboard viewer chain," so that all running clipboard viewer programs receive the messages that Windows sends to the current clipboard viewer. When a program registers itself as a clipboard viewer, that program becomes the current clipboard viewer. Windows gives that program the window handle of the previous current clipboard viewer, and the program saves this

handle. When the program receives a clipboard viewer message, it sends that message to the window function of the next program in the clipboard chain.

Clipboard Viewer Functions and Messages

A program can become part of the clipboard viewer chain by calling the SetClipboardViewer function. If the primary purpose of the program is to serve as a clipboard viewer, the program can call this function during processing of the WM_CREATE message. The function returns the window handle of the previous current clipboard viewer. The program should save that handle in a static variable:

If your program is the first program to become a clipboard viewer during the Windows session, then hWndNextViewer will be NULL.

Windows sends a WM_DRAWCLIPBOARD message to the current clipboard viewer (the most recent window to register itself as a clipboard viewer) whenever the contents of the clipboard change. Each program in the clipboard viewer chain should use <code>SendMessage</code> to pass this message to the next clipboard viewer. The last program in the clipboard viewer chain (the first window to register itself as a clipboard viewer) will have stored a NULL <code>hWndNextViewer</code> value. If <code>hWndNextViewer</code> is NULL, the program simply returns without sending the message to another program. (Don't confuse the WM_DRAWCLIPBOARD and WM_PAINTCLIPBOARD messages. The WM_PAINTCLIPBOARD message is sent by a clipboard viewer to programs that use the CF_OWNERDISPLAY clipboard format. The WM_DRAWCLIPBOARD message is sent by Windows to the current clipboard viewer.)

The easiest way to process the WM_DRAWCLIPBOARD message is to send the message to the next clipboard viewer (unless hWndNextViewer is NULL) and invalidate the client area of your window:

```
case WM_DRAWCLIPBOARD:
    if (hWndNextViewer)
        SendMessage (hWndNextViewer, iMessage, wParam, 1Param);
    InvalidateRect (hWnd, NULL, TRUE);
    break;
```

During processing of the WM_PAINT message, you can read the contents of the clipboard by using the normal *OpenClipboard*, *GetClipboardData*, and *CloseClipboard* calls.

When a program wishes to remove itself from the clipboard viewer chain, it must call ChangeClipboardChain. This function requires the window handle of the program leaving the viewer chain and the window handle of the next clipboard viewer:

```
ChangeClipboardChain (hWnd, hWndNextViewer);
```

When a program calls ChangeClipboardChain, Windows sends a WM_CHANGECLIPBOARD message to the current clipboard viewer. The wParam parameter is the handle of the window removing itself from the chain (the first parameter to ChangeClipboardChain), and the low word of lParam is the window handle of the next clipboard viewer after the one removing itself from the chain (the second parameter to ChangeClipboardChain).

When your program receives a WM_CHANGECLIPBOARD message, you must therefore check to see if wParam is equal to the value of hWndNextViewer that you've saved. If it is, your program must set hWndNextViewer to the low word of lParam. This action ensures that any future WM_DRAWCLIPBOARD messages you get won't be sent to the window removing itself from the clipboard viewer chain. If wParam isn't equal to hWndNextViewer, and hWndNextViewer isn't NULL, send the message to the next clipboard viewer:

```
case WM_CHANGECBCHAIN:
    if (wParam == hWndNextViewer)
        hWndNextViewer = LOWORD (lParam);

else if (hWndNextViewer)
        SendMessage (hWndNextViewer, iMessage, wParam, lParam);
break;
```

You shouldn't need to include the *else if* statement, which checks *hWndNextViewer* for a non-NULL value. A NULL *hWndNextViewer* value would indicate that the program executing this code is the last viewer on the chain, in which case the message should never have gotten this far.

If your program is still in the clipboard viewer chain when it is about to terminate, you must remove your program from the chain. You can do this during processing of the WM_DESTROY message by calling ChangeClipboardChain.

```
case WM_DESTROY:
    ChangeClipboardChain (hWnd, hWndNextViewer);
    PostQuitMessage (0);
    break;
```

Windows also has a function that allows a program to obtain the window handle of the first clipboard viewer:

```
hWndViewer = GetClipboardViewer () ;
```

This function isn't normally needed. The return value can be NULL if there is no current clipboard viewer.

DATA EXCHANGE AND LINKS

Here's an example to illustrate how the clipboard viewer chain works. When Windows first starts up, the current clipboard viewer is NULL:

Current clipboard viewer: NULL

A program with a window handle of hWnd1 calls SetClipboardViewer. The function returns NULL, which becomes the hWndNextViewer value in this program:

Current clipboard viewer: hWnd1 hWnd1's next viewer: NULL

A second program with a window handle of hWnd2 now calls SetClipboardViewer and gets back hWnd1:

Current clipboard viewer: hWnd2 hWnd2's next viewer: hWnd1 hWnd1's next viewer: NULL

A third program (hWnd3) and then a fourth (hWnd4) also call SetClipboardViewer and get back hWnd2 and hWnd3:

Current clipboard viewer: hWnd4
hWnd4's next viewer: hWnd3
hWnd3's next viewer: hWnd2
hWnd2's next viewer: hWnd1
hWnd1's next viewer: NULL

When the contents of the clipboard change, Windows sends a WM_DRAWCLIPBOARD message to hWnd4, hWnd4 sends the message to hWnd3, hWnd3 sends it to hWnd2, hWnd2 sends it to hWnd1, and hWnd1 returns.

Now hWnd2 decides to remove itself from the chain by calling:

ChangeClipboardChain (hWnd2, hWnd1);

Windows sends hWnd4 a WM_CHANGECBCHAIN message with wParam equal to hWnd2 and the low word of lParam equal to hWnd1. Because hWnd4's next viewer is hWnd3, hWnd4 sends this message to hWnd3. Now hWnd3 notes that wParam is equal to its next viewer (hWnd2), so it sets its next viewer equal to the low word of lParam (hWnd1) and returns. The mission is accomplished. The clipboard viewer chain now looks like this:

Current clipboard viewer: hWnd4
hWnd4's next viewer: hWnd3
hWnd3's next viewer: hWnd1
hWnd1's next viewer: NULL

A Simple Clipboard Viewer

Clipboard viewers don't have to be as sophisticated as CLIPBRD.EXE. A clipboard viewer can, for instance, display only one clipboard format. The CLIPVIEW program, shown in Figure 17-2, is a clipboard viewer that displays only the CF_TEXT format.

```
clipview.obj : clipview.c

cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp clipview.c

clipview.exe : clipview.obj clipview.def

link4 clipview, /align:16, /map, slibw, clipview
```

```
/* CLIPVIEW.C -- Simple Clipboard Viewer */
#include <windows.h>
long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG) ;
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
     HANDLE hInstance, hPrevInstance;
     LPSTR
                lpszCmdLine ;
                nCmdShow ;
     int
                char szAppName [] = "ClipView" ;
     static
                hWnd ;
     HWND
     MRG
                msg ;
     WNDCLASS wndclass ;
     if (!hPrevInstance)
           wndclass.style
                                     = CS HREDRAW | CS VREDRAW ;
           wndclass.lpfnWndProc = WndProc;
          wndclass.cbClsExtra = 0;
wndclass.cbWndExtra = 0;
          wndclass.cbWndExtra
wndclass.hInstance = hInstance;
wndclass.hIcon = NULL;
wndclass.hIcon = LoadCursor (NULL, IDC_ARROW);
= LoadCursor (WHITE_BRUSH);
           wndclass.lpszMenuName = NULL ;
           wndclass.lpszClassName = szAppName ;
           if (!RegisterClass (&wndclass))
                 return FALSE :
     hWnd = CreateWindow (szAppName, "Simple Clipboard Viewer (Text Only)",
                            WS OVERLAPPEDWINDOW,
                            CW USEDEFAULT, 0,
                            CW USEDEFAULT, 0,
                            NULL, NULL, hinstance, NULL) ;
     ShowWindow (hWnd, nCmdShow) ;
     UpdateWindow (hWnd) ;
```

Figure 17-2. The CLIPVIEW program

```
while (GetMessage (&msg, NULL, 0, 0))
          TranslateMessage (&msg) ;
          DispatchMessage (&msg) ;
     return msg.wParam ;
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
     HWND
                hWnd ;
     unsigned
                 iMessage ;
     WORD
                wParam ;
    LONG
                 lParam ;
    static HWND hWndNextViewer ;
                hGMem ;
    HANDLE
    HDC
                 hDC :
                lpGMem ;
    LPSTR
    PAINTSTRUCT ps ;
    RECT
                rect ;
    switch (iMessage)
          case WM CREATE:
               hWndNextViewer = SetClipboardViewer (hWnd) ;
               break ;
          case WM CHANGECBCHAIN :
               if (wParam == hWndNextViewer)
                    hWndNextViewer = LOWORD (1Param) ;
               else if (hWndNextViewer)
                    SendMessage (hWndNextViewer, iMessage, wParam, 1Param) ;
               break :
          case WM_DRAWCLIPBOARD :
               if (hWndNextViewer)
                    SendMessage (hWndNextViewer, iMessage, wParam, 1Param) ;
               InvalidateRect (hWnd, NULL, TRUE) ;
               break;
          case WM PAINT:
               hDC = BeginPaint (hWnd, &ps) ;
               GetClientRect (hWnd, &rect) ;
               OpenClipboard (hWnd) ;
               if (hGMem = GetClipboardData (CF TEXT))
                    lpGMem = GlobalLock (hGMem) ;
                    DrawText (hDC, lpGMem, -1, &rect, DT_EXPANDTABS) ;
GlobalUnlock (hGMem) ;
               CloseClipboard () ;
               EndPaint (hWnd, &ps) ;
               break ;
```

```
NAME
              CLIPVIEW
DESCRIPTION
               'Simple Clipboard Viewer (C) Charles Petzold, 1987'
              'WINSTUB.EXE'
STUB
CODE
              MOVEABLE
              MOVEABLE MULTIPLE
DATA
HEAPSIZE
              1024
STACKSIZE
              4096
EXPORTS
              WndProc
```

CLIPVIEW processes WM_CREATE, WM_CHANGECBCHAIN, WM_DRAWCLIPBOARD, and WM_DESTROY messages as discussed above. The WM_PAINT message simply opens the clipboard and uses *GetClipboardData* with a format of CF_TEXT. If the function returns a global memory handle, CLIPVIEW locks it and uses *DrawText* to display the text in its client area. We could easily expand CLIPVIEW to handle the other four data formats, but we'll save that job for the CLIPFILE program coming up shortly.

A clipboard viewer that handles data formats beyond the five standard formats (as CLIPBRD.EXE does) has additional work to do, such as displaying the names of all the formats currently in the clipboard. You can do this by calling <code>EnumClipboardFormats</code> and obtaining the names of the nonstandard formats from <code>GetClipboardFormatName</code>. A clipboard viewer that uses the CF_OWNERDISPLAY format must send these four messages to the clipboard to display the data:

```
WM_PAINTCLIPBOARD WM_VSCROLLCLIPBOARD WM_HSCROLLCLIPBOARD
```

If you want to write such a clipboard viewer, you have to obtain the window handle of the clipboard owner using *GetClipboardOwner* and send that window these messages when you need to update the clipboard viewer's client area.

Loading and Saving the Clipboard

In some cases, you might want to save the clipboard contents in a file or load a file into the clipboard. With text, you can accomplish these tasks fairly easily using the NOTEPAD or WRITE program. But with bitmaps and metafiles, there's nothing to help you out.

Now there is. CLIPFILE is a clipboard viewer for the five standard formats (text, bitmaps, metafiles, SYLK files, and DIF files) that can save the clipboard contents in a file or load a file into the clipboard. Thus you can copy part of a PAINT painting to the clipboard or use BLOWUP to capture part of the display to the clipboard, and then you can use CLIPFILE to save the clipboard contents as a bitmap file with a .BMP extension. You can then make this bitmap a resource in one of your programs. Or you can use a drawing program to copy a metafile to the clipboard and then use CLIPFILE to save it as a metafile with a .WMF extension. Using the method presented in Chapter 14, you can make that metafile a user-defined resource in your program. The CLIPFILE program is shown in Figure 17-3. The CLIPFILE icon is a combination of the CLIPBRD icon and the MS-DOS Executive disk-drive icon. You'll also need the FILEDLG.H, and FILEDLG.DLG modules from Figure 11-8.

```
clipfile.obj : clipfile.c clipfile.h
    cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp clipfile.c

filedlg.obj : filedlg.c filedlg.h
    cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp filedlg.c

clipfile.res : clipfile.rc clipfile.h clipfile.ico filedlg.dlg filedlg.h
    rc -r clipfile.rc

clipfile.exe : clipfile.obj filedlg.obj clipfile.def clipfile.res
    link4 clipfile filedlg, /align:16, /map, slibw, clipfile
    rc clipfile.res
```

```
/* CLIPFILE.C -- Clipboard Load and Save */
#include <windows.h>
#include <string.h>
#include <stdio.h>
#include "winundoc.h"
#include "clipfile.h"
#include "filedlg.h"
extern BOOL DoFileOpenDlg (HANDLE, HWND, PSTR, PSTR, WORD, PSTR, POFSTRUCT)
extern BOOL DoFileSaveDlg (HANDLE, HWND, PSTR, PSTR, WORD *, PSTR, POFSTRUCT)
long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG) ;
typedef struct
    WORD dummy1 ;
    short bmType ;
    short bmWidth ;
    short bmHeight ;
     short bmWidthBytes ;
    BYTE bmPlanes;
BYTE bmBitsPixel;
    DWORD dummy2 ;
     BMFILEHDR ;
```

Figure 17-3. The CLIPFILE program

```
char szAppName [] = "ClipFile" ;
char *szFileSpecs [] = ( "*.TXT", "*.BMP", "*.WMF", "*.SYL", "*.DIF" ) ;
FARPROC
                 lpfnMFPInfo ;
                 hInst ;
LPMETAPILEPICT lpmfp ;
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
     HANDLE hinstance, hPrevinstance;
      LPSTR
                lpszCmdLine ;
      int
                nCmdShow ;
     HWND
               hWnd ;
     MSG
                msg ;
     WNDCLASS wndclass ;
     if (!hPrevInstance)
           wndclass.style = CS_HREDRAW | CS_VREDRAW ;
wndclass.lpfnWndProc ;
wndclass.cbClsExtra = 0 ;
wndclass.cbWndExtra = 0 ;
           wndclass.hInstance = hInstance;
wndclass.hIcon = LoadIcon (hInstance, szAppName);
wndclass.hCursor = LoadCursor (NULL, IDC ARROW);
           wndclass.hbrBackground = COLOR_WINDOW + 1 ;
           wndclass.lpszMenuName = szAppName ;
           wndclass.lpszClassName = szAppName ;
           if (!RegisterClass (&wndclass))
                 return FALSE ;
     hInst = hInstance ;
      hWnd = CreateWindow (szAppName, NULL,
                             WS OVERLAPPEDWINDOW,
CW_USEDEFAULT, 0,
CW_USEDEFAULT, 0,
                             NULL, NULL, hinstance, NULL) ;
      ShowWindow (hWnd, nCmdShow) ;
      UpdateWindow (hWnd) ;
      while (GetMessage (&msg, NULL, 0, 0))
            TranslateMessage (&msg) ;
           DispatchMessage (&msg) ;
      return msg.wParam ;
BOOL FAR PASCAL MFPInfoDlgProc (hDlg, iMessage, wParam, 1Param)
      HWND
                hDlg ;
      unsigned iMessage ;
      WORD
                wParam ;
      LONG
                1Param ;
      BOOL
                bTrans ;
```

```
switch (iMessage)
           case WM INITDIALOG:
                CheckRadioButton (hDlg, IDD_TEXT, IDD_ANISO, IDD_TEXT) ;
SetDlgItemInt (hDlg, IDD_XEXT, 0, FALSE) ;
SetDlgItemInt (hDlg, IDD_YEXT, 0, FALSE) ;
                lpmfp->mm = MM TEXT ;
                SetFocus (GetDlgItem (hDlg, IDD TEXT)) ;
                return FALSE ;
           case WM COMMAND:
                switch (wParam)
                      case IDD TEXT:
                      case IDD LOMET:
case IDD HIMET:
                      case IDD LOENG:
                      case IDD HIENG:
                      case IDD TWIPS:
                      case IDD ISOTR:
                            CheckRadioButton (hDlg, IDD_TEXT, IDD_ANISO, wParam)
                            lpmfp->mm = MM TEXT + wParam - IDD TEXT ;
                            break ;
                      case IDOK:
                            lpmfp->xExt = GetDlgItemInt (hDlg, IDD_XEXT,
                            &bTrans, TRUE) ;
lpmfp->yExt = GetDlgItemInt (hDlg, IDD_YEXT,
                                                               &bTrans, TRUE) ;
                            EndDialog (hDlg, TRUE) ;
                            break ;
                       case IDCANCEL:
                            EndDialog (hDlg, FALSE) ;
                            break :
                       default:
                            return FALSE ;
                 break :
           default:
                 return FALSE ;
     return TRUE ;
void OkMessageBox (hWnd, szMessage, szFileName)
     char *szMessage, szFileName ;
     char szBuffer [80] ;
     sprintf (szBuffer, szMessage, szFileName)
     MessageBox (hWnd, szBuffer, szAppName, MB_OK | MB_ICONEXCLAMATION) ;
```

```
void PrepareMetaFile (hDC, lpmfp, xClient, yClient)
     HDC
                      hDC :
     LPMETAFILEPICT 1pmfp ;
                      xClient, yClient ;
     short
                      xlScale, ylScale, lScale;
     long
     SetMapMode (hDC, lpmfp->mm) ;
     if (lpmfp->mm == MM ISOTROPIC || lpmfp->mm == MM ANISOTROPIC)
           if (lpmfp->xExt == 0)
                SetViewportExt (hDC, xClient, yClient) ;
           else if (lpmfp->xExt > 0)
                SetViewportExt (hDC,
                      (short) ((long) lpmfp->xExt *
                                 GetDeviceCaps (hDC, HORZRES) /
                                  GetDeviceCaps (hDC, HORZSIZE) / 100),
                      (short) ((long) lpmfp->yExt *
                                 GetDeviceCaps (hDC, VERTRES) / GetDeviceCaps (hDC, VERTSIZE) / 100));
           else if (lpmfp->xExt < 0)
                xlScale = 100L * (long) xClient *
                                             GetDeviceCaps (hDC, HORZSIZE) /
                                             GetDeviceCaps (hDC, HORZRES) /
                                                   -lpmfp->xExt ;
                ylScale = 100L * (long) yClient *
                                             GetDeviceCaps (hDC, VERTSIZE) /
GetDeviceCaps (hDC, VERTRES) /
                                                  -lpmfp->yExt ;
                1Scale = min (x1Scale, y1Scale) ;
                SetViewportExt (hDC,
                      (short) ((long) -lpmfp->xExt * 1Scale *
                                  GetDeviceCaps (hDC, HORZRES) /
                      GetDeviceCaps (hDC, HORZSIZE) / 100), (short) ((long) -lpmfp->yExt * lScale *
                                 GetDeviceCaps (hDC, VERTRES) / GetDeviceCaps (hDC, VERTSIZE) / 100)) ;
      lfilelength (hFile)
     HANDLE hFile ;
             lCurrentPos = _llseek (hFile, OL, 1) ;
     long
             lFileLength = _llseek (hFile, OL, 2) ;
     long
     _llseek (hFile, lCurrentPos, 0) ;
     return lFileLength ;
```

```
void LoadFile (hWnd, wFormat)
    HWND
           hWnd ;
    WORD
             wFormat :
     BMFILEHDR bmhdr :
    char
               szFileName [16] :
    HANDLE
               hFile, hGMem, hMF :
    HBITMAP
              hBitmap ;
    LPSTR
              lpGMem ;
    OFSTRUCT of :
    WORD
              wLength :
    if (!DoFileOpenDlg (hInst, hWnd, szFileSpecs [wFormat - IDM TXT],
              szFileSpecs [wFormat - IDM TXT] + 1, 0x4010, szFileName, &of))
         return ;
    if (-1 == (hFile = OpenFile (szFileName, &of, OF READ | OF REOPEN)))
         OkMessageBox (hWnd, "Cannot open file %s", szFileName) ;
         return ;
    if ( lfilelength (hFile) > 65535)
          lclose (hFile) ;
         OkMessageBox (hWnd, "File %s too large", szFileName) ;
    wLength = (WORD) lfilelength (hFile) ;
    if (NULL == (hGMem = GlobalAlloc (GHND, (DWORD) wLength + 1)))
          lclose (hFile) ;
         OkMessageBox (hWnd, "Cannot allocate memory for %s", szFileName) ;
         return :
    switch (wFormat)
         case IDM TXT:
         case IDM SYL:
         case IDM DIF:
              1pGMem = GlobalLock (hGMem) ;
              _lread (hFile, lpGMem, wLength);
_lclose (hFile);
              lpGMem [wLength] = '\0';
              GlobalUnlock (hGMem) ;
              break ;
         case IDM BMP:
              lread (hFile, (LPSTR) &bmhdr, sizeof (BMFILEHDR));
              wLength = bmhdr.bmPlanes * bmhdr.bmWidthBytes * bmhdr.bmHeight ;
              lpGMem = GlobalLock (hGMem) ;
              _lread (hFile, lpGMem, wLength) ;
              lclose (hFile) ;
```

Figure 17-3. Continued

```
hBitmap = CreateBitmap (bmhdr.bmWidth, bmhdr.bmHeight,
                              bmhdr.bmPlanes, bmhdr.bmBitsPixel, 1pGMem) ;
              GlobalUnlock (hGMem) ;
              GlobalFree (hGMem) ;
               if (NULL == (hGMem = hBitmap))
                    OkMessageBox (hWnd, "Could not create bitmap", NULL) ;
                    return ;
              break ;
         case IDM WMF:
              lpGMem = GlobalLock (hGMem) ;
              _lread (hFile, lpGMem, wLength) ;
                lclose (hFile) ;
               GlobalUnlock (hGMem) ;
              hMF = SetMetaFileBits (hGMem) ;
              hGMem = GlobalAlloc (GHND, (DWORD) sizeof (METAFILEPICT)) ;
               lpmfp = (LPMETAFILEPICT) GlobalLock (hGMem) ;
               lpmfp->hMF = hMF ;
               if (!DialogBox (hInst, "MFPInfo", hWnd, lpfnMFPInfo))
                    GlobalUnlock (hGMem) ;
                    GlobalFree (hGMem)
                    DeleteMetaFile (hMF) ;
                    return ;
               GlobalUnlock (hGMem) ;
               break ;
     OpenClipboard (hWnd) ;
     EmptyClipboard () ;
     SetClipboardData (wFormat, hGMem) ;
     CloseClipboard () ;
     return ;
void SaveFile (hWnd, wFormat)
     HWND
              hWnd ;
     WORD
              wFormat ;
     BMFILEHDR bmhdr ;
              szBuffer [80], szFileName [16];
     char
     DWORD
              dwLength ;
              hFile, hGMem, hMF;
     HANDLE
             hBitmap ;
     HBITMAP
     LPSTR
              lpGMem ;
     OFSTRUCT of ;
              wLength, wWriteBytes, wStatus;
     WORD
     if (!DoFileSaveDlg (hInst, hWnd, szFileSpecs [WFormat - IDM TXT],
               szFileSpecs (wFormat - IDM TXT) + 1, &wStatus, szFileName, &of))
          return ;
```

```
if (wStatus == 1)
     sprintf (szBuffer, "Replace existing %s", szFileName) ;
     return :
OpenClipboard (hWnd) :
if (NULL == (hGMem = GetClipboardData (wFormat)))
     CloseClipboard () ;
    OkMessageBox (hWnd, "Clipboard data has disappeared", NULL) ;
switch (wFormat)
     case IDM TXT:
     case IDM SYL:
     case IDM DIF:
         if (GlobalSize (hGMem) > 65535L)
               CloseClipboard () ;
              OkMessageBox (hWnd, "Data too large for file", NULL) ;
              return ;
         lpGMem = GlobalLock (hGMem) ;
         wLength = min (1strlen (1pGMem), (WORD) GlobalSize (hGMem)) ;
         break ;
     case IDM BMP:
         hBitmap = hGMem ;
         GetObject (hBitmap, sizeof (BITMAP), (LPSTR) &bmhdr.bmType) ;
         bmhdr.dummy1 = 0 ;
         bmhdr.dummy2 = 0;
         if ((dwLength = (DWORD) bmhdr.bmPlanes * bmhdr.bmWidthBytes *
                          (DWORD) bmhdr.bmHeight + sizeof (BMFILEHDR))
                                       > 65535L)
               CloseClipboard () ;
               OkMessageBox (hWnd, "Bitmap too large for file", NULL) ;
               return :
         wLength = (WORD) dwLength ;
         if (NULL == (hGMem = GlobalAlloc (GHND, dwLength)))
               CloseClipboard () ;
              OkMessageBox (hWnd, "Cannot allocate memory", NULL) ;
              return ;
         lpGMem = GlobalLock (hGMem) ;
          * (BMFILEHDR FAR *) lpGMem = bmhdr ;
         GetBitmapBits (hBitmap, dwLength - sizeof (BMFILEHDR), lpGMem + sizeof (BMFILEHDR));
         break :
```

```
case IDM WMF:
                 lpmfp = (LPMETAFILEPICT) GlobalLock (hGMem) ;
                 hMF = lpmfp->hMF ;
                 GlobalUnlock (hGMem) ;
                 hGMem = GetMetaFileBits (hMF) ;
                 if (GlobalSize (hGMem) > 65535L)
                       SetMetaFileBits (hGMem) ;
                       CloseClipboard () ;
                       OkMessageBox (hWnd, "Metafile too large for file", NULL) ;
                       return ;
                 wLength = (WORD) GlobalSize (hGMem) ;
                 lpGMem = GlobalLock (hGMem) ;
                 break ;
     if (-1 == (hFile = OpenFile (szFileName, &of, OF_CREATE | OF_REOPEN)))
    OkMessageBox (hWnd, "Cannot create file %s", szFileName);
     else
           wWriteBytes = lwrite (hFile, lpGMem, wLength) ;
lclose (hFile) ;
If (wWriteBytes < wLength)</pre>
                 OpenFile (szFileName, &of, OF_DELETE | OF_REOPEN) ;
                 OkMessageBox (hWnd, "Not enough disk space for %s", szFileName);
     GlobalUnlock (hGMem) ;
     if (wFormat == IDM BMP)
           GlobalFree (hGMem) ;
     else if (wFormat == IDM WMF)
           SetMetaFileBits (hGMem) ;
     CloseClipboard () ;
void PaintWindow (hWnd, hDC, wFormat)
                       hWnd ;
     HWND
                       hDC ;
     HDC
     WORD
                       wFormat ;
                       *szFormats [] = ( "Text", "Bitmap", "Metafile",
                                              "Text", "DIF" ), "MM LOMETRIC",
     static char
                        *szMapModes [] = ( "MM_TEXT",
                                              "MM TEXT", "MM LOMETRIC",
"MM HIMETRIC", "MM LOENGLISH",
"MM HIENGLISH", "MM TWIPS",
"MM ISOTROPIC", "MM ANISOTROPIC");
     BITMAP
                       bm ;
                       szBuffer [80] ;
     char
     HANDLE
                       hGMem, hMF;
                       hBitmap ;
     HBITMAP
     HDC
                       hMemDC ;
```

```
LPMETAFILEPICT lpmfp ;
LPSTR
             lpGMem ;
             rect ;
RECT
WORD
             wCaption, wLength ;
GetClientRect (hWnd, &rect) ;
OpenClipboard (hWnd) ;
wCaption = sprintf (szBuffer, "ClipFile: %s",
                  szFormats [wFormat - IDM TXT]) ;
if (hGMem = GetClipboardData (wFormat))
    switch (wFormat)
         case IDM TXT:
         case IDM SYL:
         case IDM DIF:
             lpGMem = GlobalLock (hGMem) ;
             wLength = min (lstrlen (lpGMem),
                           (WORD) GlobalSize (hGMem)) ;
             DrawText (hDC, 1pGMem, wLength, &rect, DT EXPANDTABS) ;
             GlobalUnlock (hGMem) ;
             break ;
         case IDM BMP:
             hBitmap = hGMem ;
              hMemDC = CreateCompatibleDC (hDC) ;
              SelectObject (hMemDC, hBitmap)
              GetObject (hBitmap, sizeof (BITMAP), (LPSTR) &bm);
              BitBlt (hDC, 0, 0, bm.bmWidth, bm.bmHeight,
             hMemDC, 0, 0, SRCCOPY);
DeleteDC (hMemDC);
             bm.bmBitsPixel, bm.bmBitsPixel == 1 ?
                      "" : "s", " per pixel");
             break :
         case IDM WMF:
              hGMem = GetClipboardData (CF_METAFILEPICT) ;
              lpmfp = (LPMETAFILEPICT) GlobalLock (hGMem) ;
              SaveDC (hDC) ;
              PrepareMetaFile (hDC, lpmfp, rect.right, rect.bottom) :
             PlayMetaFile (hDC, lpmfp->hMF) ;
RestoreDC (hDC, -1) ;
             lpmfp->xExt, lpmfp->yExt) ;
```

```
GlobalUnlock (hGMem) ;
                     break :
          else
               sprintf (szBuffer + wCaption, " (None)") ;
     CloseClipboard () ;
     SetWindowText (hWnd, szBuffer) ;
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
                hWnd ;
     HWND
     unsigned
                iMessage ;
     WORD
                 wParam ;
     LONG
                 lParam ;
     static HWND hWndNextViewer ;
     static WORD wFormat = IDM TXT ; /* = CF_TEXT */
                 hDC ;
     HMENU
                 hMenu ;
     PAINTSTRUCT ps ;
     switch (iMessage)
          case WM CREATE:
                lpfnMFPInfo = MakeProcInstance (MFPInfoDlgProc, hInst) ;
               hWndNextViewer = SetClipboardViewer (hWnd) ;
               break ;
          case WM_CHANGECBCHAIN :
               if (wParam == hWndNextViewer)
                     hWndNextViewer = LOWORD (1Param) ;
                else if (hWndNextViewer)
                     SendMessage (hWndNextViewer, iMessage, wParam, lParam) ;
                break ;
          case WM DRAWCLIPBOARD :
                if (hWndNextViewer)
                SendMessage (hWndNextViewer, iMessage, wParam, 1Param) ;
InvalidateRect (hWnd, NULL, TRUE) ;
                break;
          case WM_INITMENUPOPUP:
                if (lParam == 0)
                     EnableMenuItem (wParam, IDM SAVE,
                          IsClipboardFormatAvailable (wFormat) ?
                               MF ENABLED : MF GRAYED) ;
                break ;
          case WM_COMMAND:
                switch (wParam)
                     case IDM TXT:
                     case IDM BMP:
                     case IDM_WMF:
case IDM_SYL:
                     case IDM DIF:
                          hMenu = GetMenu (hWnd) ;
```

Figure 17-3. Continued

```
CheckMenuItem (hMenu, wFormat, MF UNCHECKED) ;
                    wFormat = wParam ;
                    CheckMenuItem (hMenu, wFormat, MF CHECKED) ;
                    InvalidateRect (hWnd, NULL, TRUE) ;
                    break ;
               case IDM LOAD:
                    LoadFile (hWnd, wFormat) ;
                    break :
               case IDM SAVE:
                    SaveFile (hWnd, wFormat) ;
                    break :
          break :
     case WM PAINT:
          hDC = BeginPaint (hWnd, &ps) ;
          PaintWindow (hWnd, hDC, wFormat) ;
          EndPaint (hWnd, &ps) ;
          break ;
     case WM DESTROY:
          ChangeClipboardChain (hWnd, hWndNextViewer) ;
          PostQuitMessage (0) ;
          break ;
     default:
         return DefWindowProc (hWnd, iMessage, wParam, 1Param) ;
return OL ;
```

```
#define IDM TXT
                        1 /* = CF TEXT, etc. */
#define IDM BMP
                         2
#define IDM WMF
                        3
#define IDM SYL
#define IDM DIF
                        5
#define IDM LOAD
                         6
#define IDM SAVE
                        7
#define IDD TEXT
                       10
#define IDD LOMET
                       11
#define IDD HIMET
                       12
#define IDD LOENG
                       13
#define IDD_HIENG
#define IDD_TWIPS
                       14
                       15
#define IDD ISOTR
                       16
#define IDD_ANISO
                       17
#define IDD_XEXT
#define IDD_YEXT
                       18
                       19
```

Figure 17-3. Continued

```
#include <style.h>
#include "clipfile.h"
#include "filedlg.h"
ClipFile ICON clipfile.ico
ClipFile MENU
     BEGIN
           POPUP "&File"
                 BEGIN
                                                      IDM LOAD
                       MENUITEM "&Load ... ",
                       MENUITEM "&Save...",
                                                      IDM SAVE
                 END
            POPUP "For&mat"
                 BEGIN
                       MENUITEM "&Text\a.TXT",
                                                     IDM TXT, CHECKED
                       MENUITEM "&Bitmap\a.BMP",
                                                       IDM BMP
                       MENUITEM "&Metafile\a.WMF", IDM_WMF
                       MENUITEM "&Sylk\a.SYL",
                                                        IDM SYL
                       MENUITEM "&DIF\a.DIF",
                                                        IDM DIF
                 END
      END
MFPInfo DIALOG 10, 20, 140, 104
CAPTION "Metafile Picture Information"
      STYLE WS BORDER | WS CAPTION | WS DLGFRAME | WS POPUP
      BEGIN
                                                                4, 4, 72, 12, WS_GROUP
            RADIOBUTTON
                           "MM TEXT",
                                                 IDD TEXT,
                                                                4, 16, 72, 12
4, 28, 72, 12
4, 40, 72, 12
4, 52, 72, 12
4, 64, 72, 12
                          "MM LOMETRIC",
                                                IDD LOMET,
            RADIOBUTTON
                           "MM HIMETRIC",
            RADIOBUTTON
                                                IDD HIMET,
                           "MM LOENGLISH",
            RADIOBUTTON
                                                IDD LOENG,
                                                 IDD_HIENG,
IDD_TWIPS,
IDD_ISOTR,
                           "MM HIENGLISH",
"MM TWIPS",
            RADIOBUTTON
            RADIOBUTTON
            RADIOBUTTON "MM ISOTROPIC",
                                                                4, 76, 72, 12
                                                 IDD ANISO, 4, 88, 72, 12
0, 76, 10, 24, 8,
IDD_XEXT, 102, 6, 32, 12
            RADIOBUTTON "MM ANISOTROPIC", IDD ANISO,
                            "&xExt:",
                                                                              8, WS GROUP
            LTEXT
            EDITTEXT
                                                 0,
                                                               76, 24, 24, 8, WS_GROUP
                            "&yExt:",
            LTEXT
                                                              102, 22, 32, 12
86, 66, 40, 14, WS_GROUP
86, 84, 40, 14
                                                 IDD YEXT,
            EDITTEXT
                                                 IDOK,
            DEFPUSHBUTTON "OK",
                                                 IDCANCEL,
            PUSHBUTTON
                           "Cancel",
      END
rcinclude filedlg.dlg
```



Figure 17-3. Continued

NAME CLIPPILE DESCRIPTION 'Clipboard Load and Save Program (C) Charles Petzold, 1987' 'WINSTUB. EXE' STUB CODE MOVEABLE DATA MOVEABLE MULTIPLE HEAPSIZE 1024 STACKSIZE 4096 EXPORTS WndProc FileOpenDlgProc FileSaveDlgProc MFPInfoDlgProc

CLIPFILE isn't intended to replace CLIPBRD. To keep the program simple, I didn't include facilities to let you use scroll bars to view all the data. If the data can't entirely fit in CLIPFILE's client area, then you'll see only the upper left corner. CLIPFILE's Format menu lets you select the format you want to work with. When you select a format, CLIPFILE serves as a clipboard viewer only for that format. You can then use the File menu to load a file from disk into the clipboard or to save the clipboard contents in a disk file.

Watch out when you use the Save dialog box in CLIPFILE. If you use the Cut or Copy command on text in the dialog box's edit field, that text replaces the clipboard contents. It's disconcerting to see this happen while the Save dialog box is still being displayed! CLIPFILE has a special message for this occurrence: "Clipboard data has disappeared." And here's another warning: When CLIPFILE loads a file from disk, it doesn't check to see if the contents of the file are in the correct format. If you load a text file when CLIPFILE thinks it's getting a metafile, Windows will crash when it attempts to play this phony metafile.

CLIPFILE displays certain information in its caption bar. For CF_TEXT, CF_SYLK, and CF_DIF formats, this is simply the length of the character data. For CF_BITMAP, it's the bitmap's dimensions and its color organization. For CF_METAFILEPICT, it's the mapping mode and the x and y extents suggested by the program that created the metafile. When CLIPFILE displays a metafile put in the clipboard by another program, and you save the metafile on disk, write down the information in the caption bar. This is part of the METAFILEPICT structure, but it isn't part of the metafile stored on the disk. If you use this metafile as a resource in one of your programs, you'll need this information to prepare to play the metafile. And if you use CLIPFILE to load one of these metafiles from disk, CLIPFILE will display a dialog box requesting the mapping mode and the extents. CLIPFILE uses this information to construct the METAFILEPICT structure that it passes to the clipboard.

Chapter 18

Dynamic Link Libraries

Dynamic link libraries (also called dynamic libraries, "dynalink" libraries, or library modules) are one of the most important structural elements of Windows. Most of the disk files associated with Windows are either program modules or dynamic library modules. So far we've been writing Windows programs; now it's time to take a stab at writing libraries. Many of the principles you've learned in writing programs are also applicable to writing dynamic libraries, but there are some important differences.

LIBRARY BASICS

As you've seen, a program is an executable file that generally creates one or more windows and uses a message loop to receive user input. Dynamic libraries are generally not directly executable, and they don't receive messages. They are separate files containing functions that can be called by programs and other libraries to perform certain jobs. A dynamic library is brought into action only when another module calls one of the functions in the library.

The term dynamic linking refers to the process that Windows uses to link a function call in one module to the actual function in the library module. "Conventional linking" occurs when you run LINK (for DOS programs) or LINK4 (for Windows programs) to create a EXE file from various object (.OBJ) modules and the normal C libraries (such as SLIBC.LIB). Dynamic linking occurs at run time.

In the "slow boot" version of Windows, the KERNELEXE, USER.EXE, and GDI.EXE files, the various driver files such as DISPLAY.DRV, SYSTEM.DRV, and SOUND.DRV, and the printer drivers are all dynamic link libraries. These are libraries that all Windows programs can use.

The font resource files—FONTS.FON, OEMFONTS.FON, COURX.FON, HELVX.FON, TMSRX.FON, MODERN.FON, ROMAN.FON, and SCRIPT.FON—are "resource-only" dynamic libraries. They contain no code and no data but instead have fonts that all Windows programs can use. Thus one purpose of dynamic libraries is to provide functions and resources that can be used by many different programs. In a conventional operating system, only the operating system itself contains routines that other programs can call on to do a job. In Windows, the process of one module calling a function in another module is generalized. In effect, by writing a dynamic link library, you are writing an extension to Windows. Or you can think of dynamic link libraries (including those that make up Windows) as extensions to your program.

Some dynamic libraries are designed for use only by a specific program. For instance, the MSDOS.EXE file is a Windows program that uses a dynamic library called MSDOSD.EXE, which contains machine-dependent functions to format disks. Windows can be adapted for different MS-DOS machines by changing only the MSDOSD.EXE library module rather than the larger MSDOS.EXE program module.

You'll generally find that dynamic libraries make most sense in the context of a large application. For instance, suppose you write a large accounting package for Windows that consists of several different programs. You'll probably find that these programs use many common routines. You could put these common routines in a normal object library (with the extension .LIB) and add them to each of the program modules during conventional linking with LINK4. But this approach is wasteful, because each of the programs in this package contains identical code for the common routines. Moreover, if you change one of these routines in this library, you'll have to relink all the programs that use the changed routine. If you put these common routines in a dynamic link library called (for instance) ACCOUNT.EXE, however, then you've solved both problems. Only the library module need contain the routines required by all the programs, and you can make changes to the library module without relinking any of the individual programs.

In the future, dynamic link libraries could themselves be viable products. For instance, suppose you write a collection of three-dimensional drawing routines and put them in a dynamic link library called GDI3.EXE. If you then interest other software developers in using your library, you can license it to be included with their graphics programs. A user who has several of these programs would need only one GDI3.EXE file.

Library: One Word, Many Meanings

Part of the confusion surrounding dynamic link libraries results from the appearance of the word *library* in several different contexts. Besides dynamic link libraries, we'll also be talking about "object libraries" and "import libraries."

An object library is a file with the extension .LIB containing code that is added to your program's .EXE file when you run the LINK4 linker during conventional linking. The normal Microsoft C object libraries that you link with small-model Windows programs are SLIBC.LIB and SLIBFA.LIB.

An import library is a special form of an object library file. Like object libraries, import libraries have the extension .LIB and are used by the LINK4 linker to resolve function calls in your source code. However, import libraries contain no code or, at the most, very little code. Instead, they provide LINK4 with information necessary to set up relocation tables within the .EXE file for dynamic linking. The SLIBW.LIB and SWINLIBC.LIB files included with the Windows Software Development Kit are import libraries for Windows functions. If you call *Rectangle* in a program, SLIBW.LIB tells LINK4 that this function is in the GDI.EXE library and has an "ordinal number" of 27. This information goes into the .EXE file so that Windows can perform dynamic linking with the GDI.EXE library when your program is executed.

Object libraries and import libraries are used only during program development. Dynamic libraries are used during run time. A dynamic library must be present on the disk when a program is run that uses the library. When Windows needs to load a dynamic library module before running a program that requires it, the library file must be stored in either the current directory or a directory accessible through the PATH string in the MS-DOS environment.

Examining Libraries with EXEHDR

Both program files and dynamic library files are in the New Executable format. You can get some sense of the workings of dynamic linking by running the EXEHDR program on the various files included with Windows and seeing what type of information the files contain. EXEHDR divides its output into five main sections, in this order:

- · The old MS-DOS .EXE header information
- · The New Executable format header information
- · A list of the code and data segments in the module
- · The exported functions of the module
- · Relocation information for each segment

Some of this information won't be present for resource-only library modules (such as the .FON files). You'll notice that the first line of the second section begins with either "Module," indicating a program module, or "Library," indicating a dynamic link library.

If you run EXEHDR on KERNELEXE, USER.EXE, or GDLEXE, you'll find that many of the names of the exported functions (the fourth section of the output) are familiar. These are the functions that the library makes available for other modules to call. Each exported function has an "ordinal number" associated with it. This is simply a positive number in the "ord" column of the EXEHDR output.

Both program modules and library modules can call functions that are exported from other library modules. To the module that makes the call, the function is said to be "imported." These imported functions show up in the last section of the EXEHDR display as relocation items, generally in the form of the library module name followed by a period and the ordinal number of the function.

When Windows loads a program into memory for execution, it must resolve the calls that the program makes to imported functions. If the library module containing these functions has not yet been loaded into memory, Windows loads at least the data segment and one code segment into memory and calls a short initialization routine in the library module. Windows also creates "reload thunks" (a topic discussed in Chapter 8) for the exported functions in the library. The calls in the program to external functions can then be resolved by inserting the addresses of the reload thunks in the code segment of the program.

The second section of the EXEHDR output points up some differences between programs and libraries. Windows programs have a line that reads:

Data: INSTANCE

This means that new data segments are created for each instance of the program. Because a single instance of a Windows library is shared by all programs that need it, this line is different for Windows libraries. It can be either:

Data: SOLO

or:

Data: NONE

depending on whether the library has one data segment or none.

A Windows program must have at least one data segment (called the automatic data segment), because this data segment contains the program's stack. You'll see in the EXEHDR output of a program file an indication of the stack address (in the "Stack" line) and the size of the stack ("Stack Allocation"). However, a library module doesn't have its own stack and thus won't show these lines. A library module always uses the stack of the program that calls the functions in the library. The absence of a stack for the library module has some significant implications that we'll cover later in this chapter.

Because each Windows program has its own stack, Windows must switch between these stacks when switching from one program to another. The presence of a stack in a program identifies the program as a distinct process that can receive messages from Windows. A library module is not a process and does not receive messages. When a program calls a function in a library module, no task switch takes place. To Windows, the program that makes the call to the library is still running even though code in the library is being executed.

STRPROG AND STRLIB

We'll begin by writing a program with a dedicated dynamic library and see how they work together. The program is called STRPROG ("string program"), and the dynamic link library is called STRLIB ("string library"). STRLIB has three exported functions that STRPROG calls. Just to make this interesting (and to force you to think about some of the implications), one of the functions in STRLIB uses a call-back function defined in STRPROG.

STRLIB is a dynamic library module that stores and sorts up to 256 character strings. The strings are capitalized and stored in STRLIB's own data segment. STRPROG can use STRLIB's three functions to add strings, delete strings, and obtain all the current strings from STRLIB. The program has two menu items (Add and Delete) that invoke dialog boxes to add and delete these strings. STRPROG lists all the current strings stored in STRLIB's data segment in STRPROG's client area.

This function defined in STRLIB adds a string to STRLIB's data segment:

```
BOOL AddString (lpString)
```

The parameter *lpString* is a far pointer to the string. The string is capitalized within the *Add-String* function. If an identical string already exists in STRLIB's data segment, this function adds another copy of the string. *AddString* returns TRUE (nonzero) if it is successful and FALSE (0) otherwise. A FALSE return value can result if the string has a length of 0, if memory could not be allocated to store the string, or if 256 strings are already stored.

This STRLIB function deletes a string from STRLIB's data segment:

```
BOOL DeleteString (lpString)
```

Again, the parameter *lpString* is a far pointer to the string. If more than one string matches, only the first is removed. *DeleteString* returns TRUE (nonzero) if it is successful and FALSE (0) otherwise. A FALSE return value indicates that the length of the string is 0 or that a matching string could not be found.

This STRLIB function uses a call-back function located in the calling program to enumerate the strings currently stored in STRLIB's data segment:

```
short GetStrings (lpfnGetStrCallBack, lpParam)
```

The call-back function must be defined as follows:

```
BOOL FAR PASCAL GetStrCallBack (lpString, lpParam)
```

The GetStrCallBack function must be exported from the program that calls GetStrings. The IpfnGetStrCallBack parameter to GetStrings must be obtained from MakeProcInstance. GetStrings calls GetStrCallBack once for each string or until the call-back function returns FALSE (0). GetStrings returns the number of strings passed to the call-back function. The IpParam parameter is a far pointer to programmer-defined data. Note that all the pointers passed as function parameters are far pointers, because STRLIB must reference data in the caller's data segment.

The STRLIB Library

Figure 18-1 (beginning on the following page) shows the four files necessary to create the STRLIB.EXE dynamic link library module. STRLIB has a lot in common with the Windows programs that we've been writing, but there are also some subtle (and some not-so-subtle) differences.

STRLIBC

```
libentry.obj : libentry.asm
    masm libentry ;

strlib.obj : strlib.c
    cl -c -Asnw -D LINT_ARGS -Gsw -Os -W2 -Zp strlib.c

strlib.exe : strlib.obj libentry.obj strlib.def
    link4 strlib libentry, /align:16, /map, swinlibc slibw, strlib
```

```
: LIBENTRY.ASM -- Entry point for library modules (small model)
          Extrn LibMain: Near
TEXT
          SEGMENT BYTE PUBLIC 'CODE'
          ASSUME CS: TEXT
PUBLIC LibEntry
LibEntry PROC FAR
          Push DI
                          ; hInstance
          Push DS
                         ; Data Segment
          Push CX
                          ; Heap Size
          Push ES
          Push SI
                          ; Command Line
          Call LibMain
          Ret
LibEntry ENDP
TEXT
          ENDS
End
          LibEntry
```

Figure 18-1. The STRLIB library

Figure 18-1. Continued

```
BOOL FAR PASCAL AddString (lpStringIn)
    LPSTR lpStringIn ;
     HANDLE hString ;
    NPSTR npString ;
short i, nLength, nCompare ;
     if (nTotal == 255)
          return FALSE ;
    if (0 == (nLength = 1strlen (1pStringIn)))
          return FALSE ;
     if (NULL == (hString = LocalAlloc (LHND, 1 + nLength)))
          return FALSE ;
     npString = LocalLock (hString) ;
     1stropy (npString, 1pStringIn) ;
     AnsiUpper (npString) :
     LocalUnlock (hString) ;
     for (i = nTotal ; i > 0 ; i--)
          npString = LocalLock (hStrings [i - 1]) ;
          nCompare = lstrcmp (lpStringIn, npString) ;
LocalUnlock (hStrings [i - 1]) ;
          if (nCompare > 0)
                hStrings [i] = hString ;
                break :
          hStrings [i] = hStrings [i - 1] ;
     if (i == 0)
          hStrings [0] = hString ;
     nTotal++ ;
     return TRUE ;
BOOL FAR PASCAL DeleteString (lpStringIn)
     LPSTR lpStringIn ;
     NPSTR npString ;
     short i, j, nCompare ;
     if (0 == lstrlen (lpStringIn))
          return FALSE :
     for (i = 0 ; i < nTotal ; i++)
          npString = LocalLock (hStrings [i]) ;
           nCompare = 1strcmp (npString, 1pStringIn) ;
          LocalUnlock (hStrings [i]) ;
          if (nCompare == 0)
                break ;
```

Figure 18-1. Continued

```
if (i == nTotal)
           return FALSE ;
     for (j = i ; j < nTotal ; j++)
          hStrings [j] = hStrings [j + 1] ;
     nTotal -- :
     return TRUE ;
short FAR PASCAL GetStrings (lpfnGetStrCallBack, lpParam)
     FARPROC lpfnGetStrCallBack;
LPSTR lpParam;
     BOOL bReturn;
NPSTR npString;
short i;
     for (i = 0 ; i < nTotal ; i++)
          npString = LocalLock (hStrings [i]) ;
          bReturn = (*lpfnGetStrCallBack) ((LPSTR) npString, lpParam) ;
          LocalUnlock (hStrings [i]) ;
          if (bReturn == FALSE)
               return i + 1 ;
     return nTotal ;
```

```
LIBRARY STRLIB

DESCRIPTION 'Library for STRPROG Program (C) Charles Petzold, 1987'

STUB 'WINSTUB.EXE'

CODE MOVEABLE

DATA MOVEABLE SINGLE

HEAPSIZE 1024

EXPORTS Addstring
DeleteString
GetStrings
```

The LIBENTRY.ASM Entry Point

The most obvious difference between STRLIB and our Windows programs is the use of an assembly-language file, LIBENTRY.ASM. Dynamic link libraries require at least one small routine coded in assembly language. This is the entry point to a function that Windows calls when the library module is first loaded into memory. The function performs initialization for the library module and then returns control to Windows. (Although LIBENTRY.ASM is written in conventional 8086 assembly language, you'll want to look into using the CMACROS.INC include file if you'll be doing extensive assembly-language programming in Windows.)

We haven't required a routine like this for our Windows programs, because program start-up code is included in the SLIBW.LIB file. When you link a Windows program with LINK4, a function called __astart is linked into the program. This is the entry point to the program. On entry to __astart, the CPU registers contain the following information:

```
BX Stack size
CX Heap size
DI Instance handle
SI Previous instance
ES Program segment prefix
```

The start-up code performs some initialization and then calls the WinMain function, which is the perceived entry point when you program for Windows in C.

For dynamic link libraries, no start-up code is provided in the Software Development Kit. That's why LIBENTRY.ASM (or something similar) is required. The last statement of this file marks the function *LibEntry* as the entry point to the library:

```
End LibEntry
```

Windows calls LibEntry once with the CPU registers set as follows:

DI	Instance handle
DS	Library's data segment
CX	Heap size
ES:SI	Command line

Note the differences between these registers and those for a Windows program. A register containing the stack size isn't required, because library modules don't have a stack. A register containing the previous instance handle isn't required, because library modules can't have multiple instances. For most uses of libraries, the command line parameter in ES:SI isn't used. LibEntry must return nonzero if initialization is successful and 0 if errors are encountered. A failed initialization is a serious problem and causes a fatal exit from Windows.

I have kept the assembly-language code in LIBENTRY.ASM to a minimum by passing the registers listed above to a function called *LibMain*, which is in the STRLIB.C file. *LibMain* looks like this:

The LocalInit function initializes the local heap of the library. You must call this function in any library module that contains a local heap. This allows the module to use local memory allocation functions such as LocalAlloc. Obviously, LibMain is so simple that we could have

added the code involved to the LIBENTRY.ASM file. However, if you need to do additional library initialization, you can use the same LIBENTRY.ASM file and do this initialization in C in the *LibMain* function rather than in assembler.

Note the differences implied here between programs and libraries. On entry to a program, the start-up code passes control to *WinMain*, which performs initialization and then enters a message loop. Multitasking takes place during *GetMessage* calls. The program exits the message loop (and *WinMain*) only when the program retrieves a WM_QUIT message from the message queue. On entry to a library, the start-up code must perform initialization and then return control to Windows with a nonzero value. The rest of the library sits dormant in memory until another module calls one of the exported functions.

Compiling the Library Source Code

Aside from the *LibMain* initialization function, STRLIB contains only the three functions that it will export to be used by other programs. All these functions are defined as FAR and PASCAL. They must be FAR because they will be called from the code segment of another module (STRPROG). You aren't required to define them as PASCAL, however. That's simply a convention used in other Windows libraries to save a few bytes of space. These three functions use Windows' local memory allocation functions to allocate space in the local heap for storing the character strings. Because the *AddString* function allocates moveable local blocks, we've essentially given Windows the job of reorganizing the local heap when necessary to allocate more memory.

The compile line in the STRLIB make file includes a compiler switch, -Asnw, that isn't required when compiling Windows programs. The -A switch is the flag for a "customized memory model." The s indicates that the code pointers are short, which is normal for small model. The n means that data pointers are near, which is also normal for small model. The w means that the compiler is to assume that the data segment isn't equal to the stack segment. This isn't normal, but it's important that you use this for a library module. The implications of the -Asnw switch are discusses in greater detail later in this chapter.

The Library Module Definition File

The module definition file for a library looks somewhat similar to the .DEF file for a program, but there are also significant differences between the two. For program modules, the module definition file contains a NAME statement indicating that the module is a program. For libraries, the first line is a LIBRARY statement:

LIBRARY STRLIB

This statement identifies the module as a library. The library CODE statement is similar to that used for programs:

CODE MOVEABLE

We could also have added LOADONCALL to the CODE statement. However, for a library with a single code segment, the segment must be loaded into memory so that the initialization routine can be executed.

For a Windows program, the DATA statement indicates that the data segment is MULTIPLE, which means that each instance of the program uses the same data segment. For the STRLIB library, the data segment is marked as SINGLE, because a library can have only one instance:

DATA MOVEABLE SINGLE

If the library doesn't include a data segment, the DATA statement is:

DATA NONE

Notice how these directives relate to the information obtained from EXEHDR.

Because we want STRLIB to use its local heap to store its character strings, we have to give it a local heap in the HEAPSIZE statement:

HEAPSIZE 1024

This is the initial size of the local heap. Windows can expand the data segment of the library to accommodate a larger heap if one is needed. Notice there's no STACKSIZE statement in the module definition file—a library module doesn't have its own stack.

For a Windows program, the EXPORTS section of the module definition file lists all far functions within the program that can be called by Windows. Generally, this list includes at least one window function. For a library, the EXPORTS section lists all far functions that can be called by programs and other library modules. This is the EXPORTS section of STRLIB.DEF:

EXPORTS AddString
DeleteString
GetStrings

Linking the Library Module

The last section of the make file creates the STRLIB.EXE file by conventional linking using LINK4:

link4 strlib libentry, /align:16, /map, swinlibc slibw, strlib

Note the inclusion of the LIBENTRY.OBJ file in the object module field. In the field that contains the nondefault libraries, we've used:

swinlibc slibw

When linking programs, we use only:

slibw

Both SLIBW.LIB and SWINLIBC.LIB are import libraries. For linking dynamic library modules, the SWINLIBC.LIB file must be used to override some of the function definitions in SLIBW.LIB.

The STRPROG Program

The STRPROG program, shown in Figure 18-2, is fairly straightforward. The two menu options (Enter and Delete) invoke dialog boxes that allow you to enter a string. STRPROG then calls AddString or DeleteString. When the program needs to update its client area, it calls GetStrings and uses the function GetStrCallBack to list the enumerated strings.

```
strprog.obj : strprog.c strprog.h
    cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp strprog.c

strprog.res : strprog.rc strprog.h
    rc -r strprog.rc

strprog.exe : strprog.obj strprog.res strprog.def
    link4 strprog, /align:16, /map, slibw, strprog
    rc strprog.res
```

```
/* STRPROG.C -- Program Using STRLIB Library */
#include <windows.h>
#include <string.h>
#include "winundoc.h"
#include "strprog.h"
#define MAXLEN 32
#define WM DATACHANGE WM USER
typedef struct
    HDC hDC ;
    short xText ;
    short yText ;
    short xStart ;
    short yStart ;
    short xIncr ;
    short yIncr ;
    short xMax ;
    short yMax ;
    CBPARM ;
BOOL FAR PASCAL AddString
                                            /* functions in STRLIB */
                             (LPSTR) ;
BOOL FAR PASCAL DeleteString (LPSTR) ;
short FAR PASCAL GetStrings
                            (FARPROC, CBPARM FAR *) ;
long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG) ;
char szAppName [] = "StrProg" :
char szString [MAXLEN] ;
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
    HANDLE hInstance, hPrevInstance;
    LPSTR
             lpszCmdLine ;
     int
             nCmdShow ;
```

Figure 18-2. The STRPROG program

Figure 18-2. Continued

```
HWND
              hWnd ;
     MSG
              msg ;
     WNDCLASS wndclass ;
     if (!hPrevInstance)
                                   = CS HREDRAW | CS VREDRAW ;
          wndclass.style
          wndclass.lpfnWndProc = WndProc;
wndclass.cbClsExtra = 0;
          wndclass.cbWndExtra = 0;
          wndclass.hInstance = hInstance;
          wndclass.hIcon
                                   = Loadicon (NULL, IDI APPLICATION) ;
          wndclass.hIcon = LoadIcon (NULL, IDI APPLICATIO
wndclass.hCursor = LoadCursor (NULL, IDC ARROW);
          wndclass.hbrBackground = GetStockObject (WHITE BRUSH) ;
          wndclass.lpszMenuName = szAppName ;
          wndclass.lpszClassName = szAppName ;
          if (!RegisterClass (&wndclass))
                return FALSE ;
     hWnd = CreateWindow (szAppName, "Library Demonstration Program", WS_OVERLAPPEDWINDOW,
                           CW USEDEFAULT, 0,
                           CW USEDEFAULT, 0,
                           NULL, NULL, hinstance, NULL) ;
     ShowWindow (hWnd, nCmdShow) ;
     UpdateWindow (hWnd) ;
     while (GetMessage (&msq, NULL, 0, 0))
          TranslateMessage (&msq) :
          DispatchMessage (&msg) ;
     return msg.wParam ;
BOOL FAR PASCAL DigProc (hDlg, iMessage, wParam, 1Param)
               hDlg ;
     unsigned iMessage ;
     WORD
             wParam ;
     LONG
               lParam ;
     switch (iMessage)
          case WM INITDIALOG:
                SendDlgItemMessage (hDlg, IDD STRING, EM_LIMITTEXT,
                                                             MAXLEN - 1, OL);
                break ;
          case WM COMMAND:
                switch (wParam)
                      case IDOK:
                           GetDlgItemText (hDlg, IDD_STRING, szString, MAXLEN) ; EndDialog (hDlg, TRUE) ;
                           break ;
```

Figure 18-2. Continued

```
case IDCANCEL:
                        EndDialog (hDlg, FALSE) :
                        break ;
                    default:
                        return FALSE ;
         default:
              return FALSE ;
    return TRUE ;
BOOL FAR PASCAL EnumCallBack (hWnd, 1Param)
    HWND hWnd ;
    LONG 1Param :
    char szClassName [16] ;
     GetClassName (hWnd, szClassName, sizeof szClassName) ;
     if (0 == strcmp (szClassName, szAppName))
         SendMessage (hWnd, WM DATACHANGE, 0, 0L) ;
    return TRUE ;
BOOL FAR PASCAL GetStrCallBack (lpString, lpcbp)
     LPSTR lpString;
     CBPARM FAR *lpcbp ;
    TextOut (lpcbp->hDC, lpcbp->xText, lpcbp->yText, lpString,
                                              1strlen (lpString));
    if ((lpcbp->yText += lpcbp->yIncr) > lpcbp->yMax)
          lpcbp->yText = lpcbp->yStart :
          if ((lpcbp->xText += lpcbp->xIncr) > lpcbp->xMax)
              return FALSE ;
     return TRUE ;
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
               hWnd ;
    HWND
                   iMessage ;
     unsigned
    WORD
                    wParam :
    LONG
                   1Param :
    static FARPROC lpfnDlgProc, lpfnGetStrCallBack, lpfnEnumCallBack; static HANDLE hInstance;
    static short xChar, yChar, xClient, yClient;
    CBPARM
                  cbparam ;
                   hDC ;
    HDC
    PAINTSTRUCT ps;
TEXTMETRIC tm:
    switch (iMessage)
         case WM CREATE:
              hInstance = ((LPCREATESTRUCT) 1Param) ->hInstance ;
```

Figure 18-2. Continued

```
lpfnDlqProc = MakeProcInstance (DlqProc, hInstance) ;
     lpfnGetStrCallBack = MakeProcInstance (GetStrCallBack,
     lpfnEnumCallBack = MakeProcInstance (EnumCallBack, hInstance) ;
     hDC = GetDC (hWnd) ;
     GetTextMetrics (hDC, &tm) ;
     xChar = tm.tmAveCharWidth ;
     yChar = tm.tmHeight + tm.tmExternalLeading ;
     ReleaseDC (hWnd, hDC) ;
     break ;
case WM COMMAND:
     switch (wParam)
          case IDM ENTER:
                if (DialogBox (hInstance, "EnterDlg", hWnd,
                                     lpfnDlgProc))
                     if (AddString (szString))
                           EnumWindows (lpfnEnumCallBack, OL) ;
                     else
                           MessageBeep (0) ;
                break ;
           case IDM DELETE:
                if (DialogBox (hInstance, "DeleteDlg", hWnd,
                                      lpfnDlgProc))
                      if (DeleteString (szString))
EnumWindows (lpfnEnumCallBack, OL);
                     else
                           MessageBeep (0) ;
                break ;
     break ;
case WM SIZE:
     xClient = LOWORD (1Param) ;
     yClient = HIWORD (1Param) ;
     break ;
case WM DATACHANGE:
     InvalidateRect (hWnd, NULL, TRUE) ;
     break :
case WM PAINT:
     hDC = BeginPaint (hWnd, &ps) ;
     cbparam.hDC = hDC ;
     cbparam.xText = cbparam.xStart = xChar ;
     cbparam.yText = cbparam.yStart = yChar ;
     cbparam.xIncr = xChar * MAXLEN ;
     cbparam.yIncr = yChar ;
     cbparam.xMax = cbparam.xIncr * (1 + xClient / cbparam.xIncr) ;
cbparam.yMax = yChar * (yClient / yChar - 1) ;
```

Figure 18-2. Continued

```
GetStrings (lpfnGetStrCallBack, &cbparam);

EndPaint (hWnd, &ps);
break;

case WM_DESTROY:
    PostQuitMessage (0);
    break;

default:
    return DefWindowProc (hWnd, iMessage, wParam, lParam);

return OL;
}

return OL;
```

```
#define IDM_ENTER 1
#define IDM_DELETE 2
#define IDD_STRING 0x10
```

```
#include <style.h>
#include "strprog.h"
StrProg MENU
              MENUITEM "&Enter!", IDM_ENTER
MENUITEM "&Delete!", IDM_DELETE
      END
EnterDlg DIALOG 24, 24, 190, 44
STYLE WS_POPUP | WS_DLGFRAME
       BEGIN
                                                     0, 4, 8, 24, 8
IDD STRING, 32, 6, 154, 12
IDOK, 44, 24, 32, 14
IDCANCEL, 114, 24, 32, 14
                                    "&Enter:",
              EDITTEXT
              DEFPUSHBUTTON
                                   "Ok",
                                    "Cancel",
              PUSHBUTTON
       END
DeleteDlg DIALOG 24, 24, 190, 44
STYLE WS_POPUP | WS_DLGFRAME
       BEGIN
                                                     0, 4, 8, 28, 8
IDD STRING, 36, 6, 150, 12
IDOK, 44, 24, 32, 14
                                    "&Delete:", 0,
              LTEXT
              EDITTEXT
              DEFPUSHBUTTON "Ok",
                                    "Cancel",
              PUSHBUTTON
                                                  IDCANCEL, 114, 24, 32, 14
       END
```

Figure 18-2. Continued

```
NAME
               STRPROG
               'Program using STRLIB Library (C) Charles Petzold, 1987'
DESCRIPTION
STUB
               'WINSTUB.EXE'
CODE
               MOVEABLE
               MOVEABLE MULTIPLE
DATA
HEAPSIZE
               1024
STACKSIZE
               4096
EXPORTS
               WndProc
               DigProc
               GetStrCallBack
               EnumCallBack
IMPORTS
               STRLIB. AddString
               STRLIB. DeleteString
               STRLIB. GetStrings
```

Near the top of the STRPROG.C source code file are declarations of the three functions in STRLIB that STRPROG will call:

```
BOOL FAR PASCAL AddString (LPSTR);
BOOL FAR PASCAL DeleteString (LPSTR);
short FAR PASCAL GetStrings (FARPROC, CBPARM FAR *);
```

If you plan to use library functions in several different programs, you'll want to put the declarations in a header file. This header file will be similar to (although I hope not as long as) WINDOWS.H.

These three functions are also listed in the IMPORTS section of STRPROG's module definition file:

```
IMPORTS STRLIB.AddString
STRLIB.DeleteString
STRLIB.GetStrings
```

These correspond to the three functions in the EXPORTS section of STRLIB.DEF. The IMPORTS section directs LINK4 to add information to STRPROG.EXE that allows Windows to dynamically link STRPROG's calls to these functions with the actual function routines in STRLIB.EXE. The EXPORTS section in STRLIB.DEF makes the functions in STRLIB.EXE available to other modules. The IMPORTS section in STRPROG.DEF indicates the module—STRLIB—and the functions in STRLIB that STRPROG requires.

Running STRPROG

Once you've created STRLIB.EXE and STRPROG.EXE, you're ready to run STRPROG. Before you do so, be sure that STRLIB.EXE is in the current directory or a directory that is listed in the PATH string of the MS-DOS environment. Windows must be able to load STRLIB.EXE when you execute STRPROG. If Windows can't find STRLIB.EXE, it will display a message box asking you to put the STRLIB.EXE disk in drive A.

When you execute STRPROG.EXE, Windows performs fixups to functions in external library modules. Many of these functions are in the normal KERNEL, USER, and GDI library modules. But Windows also sees that the program calls three functions from STRLIB, so Windows loads the STRLIB.EXE file into memory, creates reload thunks for the three functions, and calls STRLIB's initialization routine. The far calls within STRPROG to these three functions are dynamically linked with the reload thunks that branch to functions in STRLIB. You can then use STRPROG to add and delete strings from STRLIB's internal table. STRPROG's client area shows the strings currently in the table.

The calls from STRPROG to the *AddString, DeleteString*, and *GetStrings* functions in STRLIB are very efficient and have almost no overhead except for the reload thunk. In fact, the link between STRPROG and STRLIB is as efficient as if the three functions in STRLIB were simply in another moveable code segment in STRPROG. So what? you say. Why do I have to make this a dynamic link library? Can't I include these three routines in STRPROG.EXE?

Well, you could. In one sense, STRLIB is nothing more than an extension of STRPROG. However, you may be interested to see what happens when you execute a second instance of STRPROG. Because only one instance of STRLIB is loaded for both instances of the program, and because STRLIB uses its own local heap to store the character strings, all instances of STRPROG essentially share this data. (The EnumCallBack function in STRPROG serves to notify all STRPROG's instances that the contents of STRLIB's data segments have changed. EnumWindows causes Windows to call EnumCallBack with handles to all parent windows. EnumCallBack then checks to see if the class name of each window equals "StrProg"—if it does, the function sends the window a privately defined WM_DATACHANGE message.) And you can easily imagine an enhanced version of STRLIB managing a database that is shared by several instances of the same program or by single instances of different programs.

Far Function Prologs

In the discussion of memory management in Chapter 8, I went into great detail about how Windows moves code and data segments in memory and handles multiple instances of programs. Some of that discussion centered on the prolog that the compiler adds to far functions.

When Windows loads a code segment into memory, it alters the function prolog of all exported far functions in the segment. This table shows the results of that process:

Nonexported Far Function	Exported Function in a Program	Exported Function in a Library
PUSH DS	NOP	MOV AX,xxxx
POP AX	NOP	
NOP	NOP	
INC BP	INC BP	INC BP
PUSH BP	PUSH BP	PUSH BP
MOV BP,SP	MOV BP,SP	MOV BP,SP
PUSH DS	PUSH DS	PUSH DS
MOV DS,AX	MOV DS,AX	MOV DS,AX

These three prologs differ in the way that DS (the data segment address register) is set on entry to the function. In each case, the original value of DS is saved in the function prolog and restored in the function epilog.

The nonexported far function simply sets AX equal to DS and then DS equal to AX. This does nothing.

For an exported function in a program, Windows inserts NOPs in the first 2 bytes of the function. The resultant prolog then sets DS equal to AX. This prolog requires that AX be set to the data segment of the particular instance of the program. By itself, the function is incomplete. You must call *MakeProcInstance* for these exported functions so that Windows builds an "instance thunk" that sets AX equal to the data segment address of the instance. (The only case in which you don't need to call *MakeProcInstance* for an exported function is for window functions specified in a window class structure.)

The exported function in a library is somewhat simpler. Because the library can have only one instance, Windows can simply insert a 3-byte instruction that sets AX equal to the data segment address of the library. Thus you don't need to use *MakeProcInstance* with exported far functions in library modules. When a program calls a far function exported from a library module, this prolog sets the data segment equal to the library's data segment. The library function can then use its own data segment. It continues to use the stack segment of the program that called it.

The Use of Call-Back Functions

Now that we know what these function prologs look like, let's examine what happens when STRPROG calls the *GetStrings* function. *GetStrings* requires a call-back function in STRPROG called *GetStrCallBack*.

Because GetStrCallBack is exported, Windows inserts NOPs in the first 2 bytes of the function when STRPROG's code segment is loaded into memory. While processing the WM_CREATE message, STRPROG calls MakeProcInstance for this function:

```
lpfnGetStrCallBack = MakeProcInstance (GetStrCallBack, hInstance) ;
```

On return from MakeProcInstance, the variable IpfnGetStrCallBack points to code that Jooks like this:

```
MOV AX, yyyy
JMP GetStrCallBack
```

where yyyy is the data segment address of this instance of STRPROG.

STRPROG calls GetStrings to update its client area:

```
GetStrings (lpfnGetStrCallBack, &cbparam);
```

The GetStrings function is in STRLIB. The parameter cbparam is a structure containing information that GetStrings simply passes back to GetStrCallBack, which then uses the information to display the strings in the client area.

In STRLIB, the prolog to *GetStrings* sets AX equal to the data segment of the library, saves the current value of DS (the data segment of STRPROG), and sets DS equal to AX. Now the function can use its own data segment to obtain the strings currently stored. When it obtains a string, it calls the call-back function passed as a parameter to *GetStrings*:

```
bReturn = (*lpfnGetStrCallBack) ((LPSTR) npString, lpParam) ;
```

This actually calls the instance thunk for GetStrCallBack set up by MakeProcInstance. The instance thunk sets AX equal to STRPROG's data segment. The function prolog saves the current value of DS (the data segment of STRLIB) and sets DS equal to AX. Now GetStrCallBack is using STRPROG's own data segment and can process the string. When GetStrCallBack returns control to GetStrings, the function epilog restores the original value of DS, which is STRLIB's data segment. GetStrings is ready to find the next string.

When *GetStrings* is finished, the function epilog restores the value of DS to STRPROG's data segment. As you can see, although control bounces back and forth between STRPROG and STRLIB, each module is always using its own data segment. During this entire process, however, the stack segment never changes. It is always STRPROG's stack segment. For code in STRPROG, this situation is just fine. For code in STRLIB, it can pose some problems.

THE DS != SS ISSUE

The segmented architecture of the Intel 8086 family of microprocessors has been giving programmers grief for many years now. But nowhere does segmented architecture cause more problems than in Windows libraries. If you skipped the first half of Chapter 8, thinking that you'd never need to know about segmented architecture and the intricacies of near and far pointers, now is the time to read it. And even if you read it carefully, you might still benefit from this quick review.

The Intel 8086 family of microprocessors operating in real mode can address 1 megabyte of memory. This memory is addressed by a combination of a 16-bit segment address and a 16-bit offset address. The 16-bit segment address marks the beginning of a 64 KB area of memory. The offset address is relative to the beginning of the segment.

The 8086-family microprocessors have four registers that contain segment addresses: The code segment register (CS), the data segment register (DS), the stack segment register (SS), and the extra segment register (ES). The instruction pointer (IP) always addresses code within the code segment. The stack pointer (SP) always addresses the stack within the stack segment. Registers that address data can do so relative to any of the four current segments. When programming in Microsoft C, 16-bit pointers that specify only an offset address are called near or short pointers, and 32-bit pointers that contain both a segment address and an offset address are called far or long pointers.

In C, all variables defined as outside functions (on the external level) and all variables defined as *static* within functions are stored in static memory. The compiler uses near pointers relative to the 8086 data segment (DS) to address variables stored in static memory.

All parameters to functions and all variables within functions that are *not* defined as *static* are stored on the stack. The compiler uses near pointers relative to the 8086 stack segment (SS) to address the stack.

When you use a near pointer in a C program, the pointer can reference a variable either in static memory or on the stack. The compiler has no way to determine whether the near pointer is an offset to DS or SS. For this reason, C programs are normally constructed to use the same segment for data and the stack. Simply put, DS == SS. This is almost required for a C implementation on 8086-family microprocessors, because C makes no differentiation between pointers to static variables and pointers to stack variables.

Let's take an example. In a small-model or medium-model program, you can use the normal C strlen function to find the length of a string. The parameter to strlen is a near pointer to the string:

```
wLength = strlen (pString) ;
```

The string itself could be stored in either static memory or on the stack. You could define pString like this:

```
char *pString = "This is a string";
```

In this case, the string "This is a string" is stored in static memory, and the near pointer is relative to the beginning of the data segment. However, you could do something like this within a function:

In this case, the szString array takes up 20 bytes on the stack. When you refer to szString, you're actually referring to a near pointer relative to the stack segment.

How does the *strlen* function know whether the near pointer is an offset in the stack segment or in the data segment? It doesn't. If you take a look at the assembly-language code for *strlen* in the SLIBC.LIB library, this is what you'll find:

```
_strlen NEAR PROC

PUSH BP ; Prologue

MOV BP, SP

PUSH DI

PUSH DS ; Set ES equal to DS

POP ES

MOV DI,[BP+4] ; Get DI ptr off stack

XOR AX, AX

MOV CX, -1

REPNZ SCASB ; Search for zero in ES:DI
```

```
AX. CX
                           ; Calculate length
           MOST
           INC
                AX
           INC
                AX
           NEG
                           ; Epilogue
           POP
                DI
          MOV
                SP. BP
          POP
               BP
          RET
_strlen
          ENDP
```

The strlen function assumes that the near pointer is an offset in the data segment. It sets ES equal to DS using this code:

```
PUSH DS
```

It then uses ES to scan the string for a terminating 0. To write a *strlen* function that worked with a near pointer in the stack segment, you would need to replace these lines with:

```
PUSH SS
POP ES
```

But you've never had to worry about this little problem in Windows programs, because DS equals SS.

Windows dynamic libraries are another story. The data segment is the library's own data segment, but the stack segment is the stack of the caller. That is, DS != SS. If you call strlen in a Windows library for a string that is stored on the stack, the function won't work correctly, because the strlen function assumes that the near pointer is relative to the data segment. When you first realize the implications of this, you're likely to assume that programming Windows dynamic libraries is very difficult. Let's just say that it's not quite as carefree a process as writing a Windows program, but the job certainly isn't impossible. After all, the bulk of Windows consists of dynamic libraries—the KERNEL, USER, and GDI modules.

At one time, the recommended practice was to use *no* normal C library functions within a dynamic library and to instead write your own functions. This restriction has now been loosened, and information is available to let you use C library functions intelligently. The conventions followed in the *strlen* function hold in most of the functions in the normal C library distributed with the Microsoft C Compiler: Most functions that accept pointers assume that the pointer is relative to the data segment; these functions do not assume that DS is equal to SS. Several functions *cannot* be used in Windows libraries. They are:

- abort, exit, and _exit
- creat, chsize, and tmpfile
- All the printf functions, including sprintf
- · All the scanf functions, including sscanf
- All the exec and spawn functions

When you compile C source code for a small-model Windows library, include the switch -Asnw, and for a medium-model Windows library, include the switch -Alnw. These switches tell the compiler to assume that DS is not equal to SS. Nothing very magical happens here. The primary purpose of these switches is to alert you to possible problems in your code. For instance, within a function, you might define an array and a pointer:

```
f int array [3];
int *ptr;

If you say:
array [0] = array [1] + array [2];
```

the compiler uses SS to reference the elements of *array*, because the compiler knows that *array* is on the stack. However, you might have code like this:

```
ptr = array ;
*ptr = *(ptr + 1) + *(ptr + 2) ;
```

In the first statement, the compiler assigns the near address of *array* (which happens to be referenced from the stack segment) to the near pointer *ptr*. But when generating code for the second line, the compiler assumes that *ptr* references a variable in the data segment. That's wrong.

If you have a program with a construction like this and you compile with the -Asnw switch and a warning level of 1 or 2, you'll get a warning message for the assignment of the array address to ptr:

```
warning 58: address of frame variable taken, DS != SS
```

You can translate this message as: "You've assigned the address of a variable on the stack (or frame) to a near pointer. Future use of this near pointer will involve the data segment. You've specified that you want the compiler to assume DS is not equal to SS. This assignment statement contradicts your intentions."

You can fix this by making ptra far pointer, like so:

```
(
int array [3];
int far *ptr;
ptr = array;
```

Now the compiler assigns the full 32-bit address of *array* (the stack segment and the offset) to *ptr.* You're safe in using *ptr.* Or you can make *array* a static variable:

```
static int array [3];
int *ptr;
ptr = array;
```

The compiler now assumes that ptr references data in the data segment; this is correct, because array is defined as static.

Don't assume that you'll always be alerted to problems like this. Here's another example. You have a function that sums up the first 100 elements of an integer array:

```
int sumup (array)
    int array [] ;
    {
    int i, n = 0 ;

    for (i = 0 ; i < 100 ; i++)
        n += array [i] ;
    return n ;
}</pre>
```

If you call this function and the array happens to be on the stack, you're in trouble:

This won't even generate a warning message, but it's obviously incorrect. How do you get around it? Use far pointers. Define the function like this:

This is a better solution for an array of this size anyway, because it avoids putting 200 bytes on the calling program's stack.

You can avoid many of the DS!= SS problems simply by not using stack variables and instead defining all your local variables as *static*. If you want to use stack variables for some items to save space in the data segment, you should avoid using the stack either for arrays or for any variables that require pointers. Finally, if you use pointers with stack variables, make them far pointers.

The parameters to a library function are always on the stack. If you need to use a pointer to reference a function parameter, use a far pointer.

OTHER LIBRARY RESTRICTIONS

The start-up code that is added to a Windows program during linking with LINK4 uses the registers passed to the program on entry, together with some DOS function calls, to set various global variables in the program's data segment. These variables allow programs access to the DOS environment and to other information. This start-up code isn't present in Windows libraries. For this reason, you can't use the *getenv* or *putenv* functions in libraries, nor can you use the following global variables defined in Microsoft C:

_dosvermajor _dosverminor _osmajor _osminor _psp environ _argc _argv

I mentioned earlier that a dynamic library module doesn't receive messages. However, a library module can call *GetMessage* and *PeekMessage*. The messages the library pulls from the queue with these functions are actually messages for the program that called the library function. In general, the library works on behalf of the program calling it, a rule that holds for most Windows functions that a library calls. The obvious exceptions are local memory allocation functions. As you saw with the STRLIB library, these functions use the library's local heap.

A library can allocate global memory either for the program instance calling the library (in which case the global memory blocks are automatically freed when the program instance terminates) or for the library itself. If global memory is allocated using the GMEM_SHARE flag, then the memory block belongs to the library. It will be deleted only when the library is freed, which is when all programs that use the library terminate. (I'll discuss the freeing of libraries a little later in this chapter.)

A dynamic library can load resources (such as icons, strings, and bitmaps) either from the library file or from the file of the program that calls the library. The functions that load resources require an instance handle. If the library uses its own instance handle (which is passed to the library during initialization), then the library can obtain resources from its own file. To load resources from the calling program's .EXE file, the library function requires the instance handle of the program calling the function.

Registering window classes and creating windows in a library can be a little tricky. Both the window class structure and the *CreateWindow* call require an instance handle. Although you can use the library module's instance handle in creating the window class and the window, the window messages still go through the message queue of the program calling the library when the library creates the window. If you must create window classes and windows within a library, it's probably best to use the calling program's instance handle.

Because messages for modal dialog boxes are retrieved outside a program's message loop, you can easily create a modal dialog box in a library by calling *DialogBox*. The instance handle can be that of the library, and the *hWndParent* parameter to *DialogBox* can be set to NULL.

DIFFERENT METHODS FOR SPECIFYING LINKS

The module definition files for STRPROG and STRLIB show only one of several possible methods for listing functions to be exported from one module and imported in another. STRLIB'S EXPORTS section looks like this:

EXPORTS AddString
DeleteString
GetStrings

STRPROG'S IMPORTS section refers to both the library module and the function names:

IMPORTS STRLIB.AddString STRLIB.DeleteString STRLIB.GetStrings

Here's another method: The module definition file for STRLIB can assign "ordinals" to each of the functions. These are simply unique positive integers preceded by an @:

EXPORTS AddString 81
DeleteString 82
GetStrings 83

STRPROG's IMPORTS section then references these numbers:

IMPORTS AddString = STRLIB.1
DeleteString = STRLIB.2
GetStrings = STRLIB.3

This method gives STRPROG a smaller .EXE file, because the file simply stores the ordinal numbers rather than the names of all the functions. For a large number of imported functions, this method provides a significant reduction in .EXE size. It's a little trickier to use than the first method, because you have to be sure you get the numbers right.

You can also use different function names in the program than in the library. For instance, suppose that in STRPROG you use the names AddStr, DelStr, and GetStr instead of AddString, DeleteString, and GetStrings. You can reference these aliases to the real function names in the IMPORTS section:

IMPORTS AddStr = STRLIB.AddString
 DelStr = STRLIB.DeleteString
 GetStr = STRLIB.GetStrings

Or if the module definition file for STRLIB defines ordinals for each of the functions, the IMPORTS section will look like this:

IMPORTS AddStr = STRLIB.1
DelStr = STRLIB.2
GetStr = STRLIB.3

Even if you don't explicitly specify ordinal numbers for the exported functions in the library module definition file, LINK4 assigns ordinal numbers to the functions. You can determine these ordinal numbers by running EXEHDR on the library module.

USING IMPORT LIBRARIES

I implied earlier that in writing your own library module, you're adding an extension to Windows—an extension that serves you very much like the standard KERNEL, USER, and GDI library modules. So, you ask, why do I have to list all the names of imported functions from my own dynamic libraries when I don't have to specifically import the KERNEL, USER, and GDI functions that I use? Well, in the early days of Windows programming (long before the introduction of the product), programmers had to do precisely that. They ended up with module definition files that looked like this:

IMPORTS USER.RegisterClass USER.CreateWindow [etc, etc, etc.]

This process was simplified greatly by the use of "import libraries." Import libraries are much like object libraries in that LINK4 uses them to resolve function calls within a program. But the import library contains no (or very little) code, only a reference that reconciles the function name you use in your program with the library module containing this function and the actual function name. This is exactly what you do in the IMPORTS section of a .DEF file. An import library for STRLIB would allow LINK4 to know that a function call to <code>AddString</code> is really an imported function from STRLIB called <code>AddString</code> or an imported function from STRLIB with an ordinal number of 1.

When you link a Windows program, the SLIBW.LIB import library reconciles all the normal Windows functions you use in the program (mostly from KERNEL, USER, and GDI) and the ordinal numbers. That's why this import library must be specified in the library field of the LINK4 command line when linking a Windows program. Likewise, the SWINLIBC.LIB and SLIBW.LIB import libraries must be specified in this field when linking a dynamic library. Think of it this way: LINK4 has to resolve all calls that a program makes to external functions. It can do this in one of three ways: extract the function itself from an object library, get a reference to a library module name and function name (or ordinal) from an import library, or get a library module name and function name (or ordinal) from the IMPORTS section of the module definition file.

You can create an import library for a dynamic library module by running the IMPLIB program included with the Windows Software Development Kit. The syntax is:

IMPLIB libname.LIB libname.DEF

IMPLIB looks only at the EXPORTS section of the module definition file. It creates a file with the extension .LIB. After the import library is created, you can add normal object modules to the .LIB file using the LIB.EXE program included with the Microsoft C Compiler.

Figure 18-3 (on the following page) shows a revised make file and module definition file for STRLIB; Figure 18-4 (also on the following page) shows a revised make file and module definition file for STRPROG. The new STRLIB make file creates an import library called STRLIB.LIB. In the STRPROG make file, this import library must be specified in the library field of the LINK4 command line. The new STRPROG.DEF file requires no IMPORTS section.

STRPROG

```
STRPROG DEF
```

```
libentry.obj : libentry.asm
    masm libentry ;

strlib.obj : strlib.c
    cl -c -Asnw -D LINT_ARGS -Gsw -Os -W2 -Zp strlib.c

strlib.exe : strlib.obj libentry.obj strlib.def
    link4 strlib libentry, /align:16, /map, swinlibc slibw, strlib

strlib.lib : strlib.def
    implib strlib.lib strlib.def
```

STRLIB LIBRARY DESCRIPTION 'Library for STRPROG Program (C) Charles Petzold, 1987' STUB 'WINSTUB. EXE' CODE MOVEABLE DATA MOVEABLE SINGLE HEAPSIZE 1024 EXPORTS AddString 91 DeleteString 82 GetStrings 03

Figure 18-3. A revised make file and module definition file for the STRLIB library

```
STRPROG 'Program using STRLIB Library (C) Charles Petzold, 1987'
NAME
DESCRIPTION
STUB
               'WINSTUB.EXE'
CODE
               MOVEABLE
DATA
               MOVEABLE MULTIPLE
HEAPSIZE
               1024
STACKSIZE
               4096
EXPORTS
               WndProc
               DigProc
               GetStrCallBack
               EnumCallBack
```

Figure 18-4. A revised make file and module definition file for the STRPROG program

INTERCEPTING WINDOWS FUNCTION CALLS

One interesting use of dynamic libraries is in debugging. For instance, you might want to write a dynamic link library that extensively checks the parameters your program is passing to the normal Windows functions. Such a library for checking parameters to the GDI functions might be called CHECKGDI; a typical function in CHECKGDI.C would look something like this:

You can give this function any name you want, as long as it's not the same as the name of a real Windows function. (I've called it xRectangle.) The FatalExit function causes the debugging version of Windows to display a stack trace on a terminal attached to the COM1 port.

The EXPORTS section of CHECKGDI.DEF lists all these checking functions but gives each of them an external name that is the name of the actual Windows function:

```
EXPORTS Rectangle = xRectangle @1
Ellipse = xEllipse @2
LineTo = xLineTo @3
[and so forth]
```

You compile and link this CHECKGDI library the same way as STRLIB. The creation of the CHECKGDI.LIB import library looks like this:

```
implib checkgdi.lib checkgdi.def
```

Now if you have a program in development that calls normal GDI functions, you can do parameter checks during run time by linking the program as shown below. (I'll assume the program is called MYPROG):

```
link4 myprog, /align:16, /map /line, checkgdi slibw, myprog
```

Because you have included the CHECKGDLLIB library in the library field of LINK4, any calls in your program to *Rectangle*, *Ellipse*, *LineTo*, and so forth will actually reference the *xRectangle*, *xEllipse*, and *xLineTo* functions in the CHECKGDLEXE library. In CHECKGDI the functions perform the checks you want and then call the actual GDI functions.

Once you're done debugging, you can make the program call the regular Windows GDI functions simply by deleting MYPROG.EXE and relinking like this without the CHECKGDI.LIB import library:

```
link4 myprog, /align:16, /map /line, slibw, myprog
```

Now LINK4 will use SLIBW.LIB to reconcile your GDI calls with the functions in the normal GDI module. Because this approach requires no changes to your program source code, it is a clean way of inserting debugging code between your calls to Window functions and the actual functions.

DYNAMIC LINKING WITHOUT IMPORTS

Rather than have Windows perform dynamic linking when your program is first loaded into memory, you can link a program with a library module while the program is running. We used this technique in Chapter 16 when we had to call the <code>DeviceMode</code> function in a printer driver module.

For instance, you would normally call the Rectangle function like this:

```
Rectangle (hDC, xLeft, yTop, xRight, yBottom);
```

You can also call Rectangle by first defining two variables:

```
HANDLE hLibrary;
FARPROC lpfnRectangle;
```

Now you set hLibrary to the handle of the library and lpfnRectangle to the address of the Rectangle function:

```
hLibrary = LoadLibrary ("GDI.EXE") ;
lpfnRectangle = GetProcAddress (hLibrary, MAKEINTRESOURCE (27)) ;
```

The LoadLibrary function returns an MS-DOS error code (less than 32) if the library file can't be found. In GetProcAddress, the second parameter is a number (27) that you convert to a far pointer to a string by setting the segment address equal to 0—27 is the ordinal number of Rectangle obtained from the EXEHDR listing of GDLEXE. Now you can call the function and then free the library:

```
(*lpfnRectangle) (hDC, xLeft, yTop, xRight, yBottom); FreeLibrary (hLibrary);
```

For libraries in which the module definition file doesn't define ordinals for the exported functions, you can use the function name in the GetProcAddress call:

```
lpfnFunction = GetProcAddress (hLibrary, "FunctionName") ;
```

Don't use this method for linking to modules that use ordinal numbers for the exported functions. The names of the functions in a library remain resident in memory only if the module definition file doesn't include ordinals or if the keyword RESIDENTNAME is used with the functions in the EXPORTS statement.

Although this technique doesn't make much sense for the *Rectangle* function, it will definitely come in handy. You need to use it when you don't know the name of the library module until run time, as is the case with the *DeviceMode* function in the printer drivers.

The code above uses the *LoadLibrary* and *FreeLibrary* functions. Windows maintains "reference counts" for all library modules, *LoadLibrary* causes the reference count to be incremented. The reference count is also incremented when Windows loads any program that uses the library. *FreeLibrary* causes the reference count to be decremented, as does the termination of an instance of a program that uses this library. When the reference count is 0, Windows can discard the library from memory, because the library is no longer needed.

If the library module has a .EXE extension, you can cause the library to be loaded into memory (and the reference count to be incremented) by "running" the library from the MS-DOS Executive. The initialization routine of the library will be executed, and the library will be ready for use by other programs. This can cause a problem, however. Although the code segment can be discarded from memory (if it's moveable), the data segment will remain in memory until the Windows session is ended.

LIBRARIES THAT USE THE CALLER'S DATA SEGMENT

Because dynamic libraries don't have stacks, they don't, strictly speaking, require data segments. You can direct LINK4 to create a library without a data segment by using this statement in the module definition file:

DATA NONE

In this case, the module definition file should not contain a HEAPSIZE statement. Such a library can have no definitions of static data and no implied static data. If your library includes a statement like this:

lstrlen ("A string") ;

the string is normally in static memory. You can't do this if the library module doesn't have a data segment.

When a library has no data segment, Windows doesn't alter the prolog of the exported function. The function prolog sets AX equal to DS, saves the original DS, and then sets DS equal to AX. The data segment address on entry to the function remains in effect. If you allocate local memory in such a library, the block is allocated from the caller's local heap.

A library can also have its own data segment but use the caller's data segment for selected exported functions. This arrangement is specified in the module definition file:

EXPORTS functionname NODATA

D

Be careful when you use this statement, however—within the function, you can't refer to any static data in the library's data segment. If you do, the compiler won't give you a warning message, because it doesn't know you'll be using NODATA in the module definition file. The code will seem to compile without errors, but the function will really be accessing the data segment of the caller.

RESOURCE-ONLY LIBRARIES

You've seen that library modules have no stack and don't require their own data segment. You can also create a library that doesn't even have a code segment. No code? No data? Then what does the module contain? The answer is resources.

Let's say you're working on a Windows application that requires a number of bitmaps. Normally, you would list these in the resource script of the program and load them into memory with the *LoadBitmap* function. But perhaps you want to create several sets of bitmaps, each set customized for one of the major display adapters used with Windows. It would make most sense to store these different sets of bitmaps in different files, because a user would need only one set of bitmaps on the fixed disk. These files are resource-only libraries.

Figure 18-5 shows how to create a resource-only library file called BITLIB.BML that contains 10 bitmaps. The extension .BML ("bitmap library") isn't standard. The DUMMY.ASM file generates no code and simply provides a DUMMY.OBJ file to be specified during linking. The BITLIB.RC file lists all the separate bitmap files and assigns each one a number. To create BITLIB.BML you need 10 bitmaps named BITMAP1.BMP, BITMAP2.BMP, and so forth. You can create these bitmaps in ICONEDIT.

```
dummy.obj : dummy.asm
  masm dummy ;
bitlib.bml : dummy.obj bitlib.def bitlib.rc
  link4 dummy, bitlib.bml /align:16, NUL, , bitlib
  rc bitlib.rc bitlib.bml
```

```
DUMMY.ASM for resource-only libraries;
```

Figure 18-5. The BITLIB library

Figure 18-5. Continued

```
1 BITMAP bitmap1.bmp
2 BITMAP bitmap2.bmp
3 BITMAP bitmap3.bmp
4 BITMAP bitmap4.bmp
5 BITMAP bitmap5.bmp
6 BITMAP bitmap5.bmp
7 BITMAP bitmap6.bmp
7 BITMAP bitmap7.bmp
8 BITMAP bitmap8.bmp
9 BITMAP bitmap9.bmp
10 BITMAP bitmap10.bmp
```

```
LIBRARY
DESCRIPTION 'Bitmap Library for Color EGA, 350 Scan Lines (for example)'
STUB
DATA
NONE

BITLIB
'Bitmap Library for Color EGA, 350 Scan Lines (for example)'
NONE
```

The SHOWBIT program, shown in Figure 18-6, reads the bitmap resources from BITLIB and copies them to the clipboard. SHOWBIT also reads bitmaps from the clipboard and displays them in the client area of its window. You can cycle through the bitmaps by pressing a key on the keyboard.

```
showbit.obj : showbit.c
cl -c -D LINT_ARGS -Gsw -Os -W2 -Zp showbit.c
showbit.exe : showbit.obj showbit.def
link4 showbit, /align:16, /map, slibw, showbit
```

```
/* SHOWBIT.C -- Shows bitmaps in BITLIB library */
finclude <windows.h>
long FAR PASCAL WndProc (HWND, unsigned, WORD, LONG);
int PASCAL WinMain (hInstance, hPrevInstance, lpszCmdLine, nCmdShow)
    HANDLE hInstance, hPrevInstance;
    LPSTR lpszCmdLine;
    int nCmdShow;
    (
        static char szAppName [] = "ShowBit";
        HWND hWnd;
        MSG msg;
        WNDCLASS wndclass;
```

Figure 18-6. The SHOWBIT program

Figure 18-6. Continued

```
if (!hPrevInstance)
           wndclass.style
                                    = CS HREDRAW | CS VREDRAW :
           wndclass.lpfnWndProc = WndProc ;
          wndclass.cbClsExtra = 0;
wndclass.cbWndExtra = 0;
wndclass.hInstance = hInstance;
wndclass.hIcon = NULL;
wndclass.hCursor = LoadCursor (NULL, IDC_ARROW);
           wndclass.hbrBackground = GetStockObject (WHITE BRUSH) ;
           wndclass.lpszMenuName = NULL ;
           wndclass.lpszClassName = szAppName ;
           if (!RegisterClass (&wndclass))
                return FALSE ;
     hWnd = CreateWindow (szAppName, "Show Bitmaps from BITLIB (Press Key)",
                           WS OVERLAPPEDWINDOW,
                           CW USEDEFAULT, 0,
                           CW USEDEFAULT, 0,
                           NULL, NULL, hInstance, NULL) ;
     ShowWindow (hWnd, nCmdShow);
     UpdateWindow (hWnd) ;
     while (GetMessage (&msg, NULL, 0, 0))
           TranslateMessage (&msg) ;
           DispatchMessage (&msg) ;
     return msg.wParam ;
void DrawBitmap (hDC, xStart, yStart, hBitmap)
     HDC hDC;
short xStart, yStart;
     HBITMAP hBitmap ;
     BITMAP bm ;
     DWORD
            dwSize ;
     HDC
             hMemDC ;
     POINT
            pt;
     hMemDC = CreateCompatibleDC (hDC) ;
     SelectObject (hMemDC, hBitmap)
     SetMapMode (hMemDC, GetMapMode (hDC)) ;
     GetObject (hBitmap, sizeof (BITMAP), (LPSTR) &bm) :
     pt.x = bm.bmWidth ;
     pt.y = bm.bmHeight ;
     DPtoLP (hDC, &pt, 1) ;
     BitBlt (hDC, xStart, yStart, pt.x, pt.y, hMemDC, 0, 0, SRCCOPY) :
     DeleteDC (hMemDC) ;
long FAR PASCAL WndProc (hWnd, iMessage, wParam, 1Param)
     HWND
                   hWnd ;
     unsigned
                    iMessage ;
```

Figure 18-6. Continued

```
WORD
             wParam :
            1Param ;
LONG
static HANDLE hLibrary :
static short nCurrent = 1 ;
        hBitmap ;
HANDLE
HDC
             hDC ;
PAINTSTRUCT ps ;
switch (iMessage)
     case WM CREATE:
          if ((hLibrary = LoadLibrary ("BITLIB, BML")) < 32)
               MessageBeep (0) ;
          break :
     case WM CHAR:
          if (hLibrary >= 32)
               if (NULL == (hBitmap = LoadBitmap (hLibrary,
                                        MAKEINTRESOURCE (nCurrent))))
                    nCurrent = 1 ;
                    hBitmap = LoadBitmap (hLibrary,
                                         MAKEINTRESOURCE (nCurrent)) ;
               if (hBitmap)
                    OpenClipboard (hWnd) ;
                    EmptyClipboard () ;
SetClipboardData (CF_BITMAP, hBitmap) ;
                    CloseClipboard () ;
          nCurrent++ :
          InvalidateRect (hWnd, NULL, TRUE) ;
          break :
     case WM PAINT:
          hDC = BeginPaint (hWnd, &ps) ;
          OpenClipboard (hWnd) ;
          if (hBitmap = GetClipboardData (CF BITMAP))
               DrawBitmap (hDC, 0, 0, hBitmap) ;
          EndPaint (hWnd, &ps) ;
          break ;
     case WM DESTROY:
          if (hLibrary >= 32)
              FreeLibrary (hLibrary) ;
          PostQuitMessage (0) ;
          break ;
     default:
          return DefWindowProc (hWnd, iMessage, wParam, 1Param) ;
return OL :
```

Figure 18-6. Continued

```
NAME SHOWBIT
DESCRIPTION 'Program to show bitmaps from BITLIB (C) Charles Petzold, 1987'
STUB 'WINSTUB.EXE'
CODE MOVEABLE
DATA MOVEABLE MULTIPLE
HEAPSIZE 1024
STACKSIZE 4096
EXPORTS WndProc
```

During processing of the WM_CREATE message, SHOWBIT gets a handle to BITLIB.BML:

```
if ((hLibrary = LoadLibrary ("BITLIB.BML")) < 32)
    MessageBeep (0);</pre>
```

If BITLIB.BML isn't in the current directory or a directory accessible through the PATH string in the MS-DOS environment, Windows displays a message box asking the user to insert the BITLIB.BML disk in drive A. If the user presses Cancel, *LoadLibrary* returns an MS-DOS error code (less than 32), in which case SHOWBIT simply beeps.

SHOWBIT can obtain a handle to a bitmap by calling *LoadBitmap* with the library handle and the number of the bitmap:

```
hBitmap = LoadBitmap (hLibrary, MAKEINTRESOURCE (nCurrent)) ;
```

This returns an error if the bitmap corresponding to the number *nCurrent* isn't valid or if not enough memory exists to load the bitmap.

While processing the WM_DESTROY message, SHOWBIT frees the library:

```
FreeLibrary (hLibrary) ;
```

When the last instance of SHOWBIT terminates, the reference count of BITLIB.BML drops to 0 and the memory it occupies is freed. As you can see, this is a simple method of implementing a "clip art" program that loads precreated bitmaps (or metafiles) into the clipboard for use by other programs.

One of the most common forms of resource-only library files is the font resource file, with the extension .FON. The make file for a font resource file looks the same as that for BITLIB. For a font resource file called MYFONTS.FON, the make file looks like this:

```
dummy.obj : dummy.asm
    masm dummy ;

myfonts.fon : dummy.obj myfonts.def myfonts.rc
    link4 dummy, myfonts.fon /align:16, NULL, , myfonts
    rc myfonts.rc myfonts.fon
```

The MYFONTS.RC resource script file contains a list of the individual font files:

```
1 FONT font1.fnt
2 FONT font2.fnt
3 FONT font3.fnt
```

These .FNT files can be created in the FONTEDIT utility included with the Windows Software Development Kit. The DESCRIPTION line of the module definition file generally contains the word FONTRES, the resolution of the fonts, and the names of the individual fonts:

```
LIBRARY MYFONTS

DESCRIPTION 'FONTRES 133,96,72 : Font1, Font2, Font3'

STUB 'WINSTUB.EXE'

DATA NONE
```

(A more extensive discussion of the format of the DESCRIPTION statement is included in the Windows Programming Guide.) Once you create MYFONTS.FON, you can use the CONTROL program to add these fonts to the *[fonts]* section of the WIN.INI file. Windows will then make these fonts available to programs whenever Windows is run.

It is also possible for a program to add the font resource to Windows' font table without using CONTROL or WIN.INI. The program calls:

```
AddFontResource ("MYFONTS.FON");
to add the fonts to Windows' font table and:
```

```
RemoveFontResource ("MYFONTS.FON") ;
```

to remove them. This process doesn't restrict use of the fonts to the program that calls *Add-FontResource*. Other Windows programs (such as WRITE) will also find the fonts when they call *EnumFonts*. The fonts won't be removed from the font table until all programs are finished using them.

INDEX

Abort dialog box. See Printing dialog	Bitmap(s) 339, 601-40	BTNLOOK program 227-29
function	"blt" functions and 609-27	Button class, as a child window control
Abort function in printing 723-29	brushes and 573	227-38
banding and 743-48	clipboard used with 768-69	BTNLOOK program 227-29
AbortProc 724-25	creating/using bitmap brushes	changing button text 236
banding and 744, 747	575-77	check boxes 234
implementing 726-29	drawing on the printer 748-55	colors and 238-44
modifying for a dialog box 730,	file format 340-42	creating child windows 230-31
732-33	in icons and cursors 330-31	group boxes 235
Windows use of 725-26	memory device context and 607-8	input focus and 237-38
ABOUT1 program 416 –19	metafiles (see Metafiles)	messages to parents 231-32
ABOUT2 program 429-34	monochrome, used to define icons	notification code 232
ABOUT3 program 442-47	and cursors 329-30	parent messages to child 232-33
customized push button 448	as objects and files 602-7	push buttons 233
AboutDlgProc 422-23, 424, 438	bitmap dimensions 606-7	radio buttons 235
Active window 127–28	color bitmap format 605	user-defined buttons 235
Address in memory. See Offset register; Segment registers	creating bitmaps in a program 602-4	visible/enabled buttons 236-37
AddString 809, 814, 816, 822, 831	as files 606	C
Animation 624-27	monochrome bitmap format	CALENDAR program 197
ANSI character set 152-53, 644	604-5	Call-back functions 198, 206–11,
ANSI_FIXED_FONT 645	tag image file format (TIFF) 607	645, 674
AnsiLower 154	resource-only libraries for 836-41	proper use of 210-12
AnstNext 154, 467, 685	using in menus 384-99	STRPROG and use of 823-24
AnsiPrev 154, 467, 685	adding a keyboard interface 399	Cancel push button, in dialog boxes
AnsiToOem 126, 155-56	creating bitmaps 393-94	437-38
AnsiUpper 154	creating bitmaps with text	Caption bar 48, 62
ANSI_VAR_FONT 645 Application program interface	395-96	in modeless dialog boxes 479-80
(API) 4, 25	GRAFMENU program 384-93	Capture block, drawing 194-95
Application programs II	memory device context 394 putting menus together 397–99	Casting 31-32
relationship to MS-DOS/ROM	scaling bitmaps 396-97	CF_BITMAP 764
BIOS/hardware 12-14	using to create brushes, in	CF_DIF 764
Windows and 14-17	RESOURCE2 program 342-46	CF_METAFILEPICT 764, 775-79
Arc 542, 544, 561	Bitmap fonts. See Raster font	CF_SYLK 764
ARCS program 562-66	BLOWUP program 189-92	CF_TEXT_NULL 764
ASCII character set 150	revised, to use the clipboard, 769-72	ChangeClipboardChain 787
AskAboutSave 478	"Blt" 609-27	ChangeMenu 372-73, 377-79, 393, 397
AskConfirmation 413	animation 624-27	Character(s)
Asynchronous interrupt 126, 200	color conversions 621-22	dead 146
	coordinates 611-13	internationalization of 154
В	DrawBitmap 614-15	versus keystrokes 128 messages 143-46
Background color 46, 63-64	drawing on bitmaps with 618-21	newline 642
changing 549-50, 643	mapping mode conversions 622	sets 150-53
in COLORSCR program 254-55	PatBlt 609-11	size 98-99
Banding technique 701, 740-57	StretchBlt 623-24	Character strings 347-50
abort function 743-48	transferring bits with BitBlt 613-14	graying with GrayString 645-48
defining 741-43	using different ROP codes 615-18	memory space and 349-50
intercepting keystrokes in Windows	BMP extension. See Bitmap(s)	using with MessageBox 348-49
755-57	BOUNCE program 624-27	Check boxes 234, 437
printing the screen with 748-55	Bounding box 558–62 Brushes	CheckDlgButton 437
BEEPERI program 204 –5	alignment 578-80	CHECKER1 program 173-75
BEEPER2 program 208-10	bitmaps and 573-74	CHECKER2 program 178 -81
BeginPaint 92, 502, 518	brushing interiors 570-72	CHECKER3 program 183 –86
Binary raster operation. See ROP2	creating/using bitmap brushes	CheckMenuItem 371, 380
(binary raster operation)	575-77	CheckRadioButton 436
BitBlt 192, 612, 646, 775	creating with bitmap resource in	Child window(s) 62
mapping mode conversions with 622 printer driver 715	RESOURCE2 program 342-46	basic facts about 84-85
transferring bits with 613-14	definition 46	creating 78-79, 230-31 hit-testing with 182-83
BITLIB library 836-37	and the second second	THE STREET WILLIAM TO STREET
DULLID HURALY 030 +3/	origin 578 styles 571	CHECKER example 183-88

Child window controls 225-77	CLIPVIEW program 789-91	CreateMenu 372-73, 379
button class 227–38	Clock, using the timer for a 218-24	CreateMetaFile 503, 628, 630, 633
colors and 238-44	CLOCK program 197	CreatePatternBrush 572-73
	Close box 84	CreatePen 545, 546-47
dialog box 427-28		2000 TEXAS TO SEE SEE SEE SEE SEE SEE SEE SEE SEE SE
edit class 257-63	CloseClipboard 765-66	CreatePenIndirect 545, 547
listbox class 263-77	CloseMetaFile 503, 628, 630	CreatePolygonRgn 583
scrollbar class 245-57	CLOVER program 585 –88	CreateRectRgn 582, 588
static class 244-45	Code and data segments 289-96	CreateRectRgnIndirect 583
ChildWndProc 83, 186-88, 225	avoiding movement problems 292-94	CreateSolidBrush 63, 255, 571, 572,
Chord 557, 561	compact and large memory models	637, 648
C language	and 292-93	CreateWindow 44, 47-49, 52
dynamic link libraries and 824-28	libraries that use caller's data	child windows and 78, 83, 226
memory allocation functions 320-21	segments 835-36	button class parameters 230-3
HAND WELL 10 MET 10 ME		dialog box 428
menu creation 372, 373	locking data segments 317–18	
Clicking a mouse 158	multiple code segments 290-92	edit class 257, 260
Client area, painting text on 87–122.	program segment attributes 294-96	listbox class 263
See also Text	in varying memory models 289-90	static class 244
background color (see Background	CODE statement segment attributes	popup windows 72-73, 76
color)	294, 815	in WELCOME3 program 67
GDI introduction 91-107 (see also	Color(s)	window style parameter 61-63
Graphics Device Interface	background (see Background color)	in WinMain versus WndProc 187
([GDI])	bitmaps 340, 341, 342	Creating and displaying windows
	format 605	creating a program with a window
painting and repainting 89-91		
scroll bars 108-22	controls for 238-44	42-72
size of 106-7	button colors 241	creating popup and child windows
Client-area mouse messages 159-68	system colors 239-40	72-85
coordinates, and screen coordinates	WM_CTLCOLOR message	from source code to executable
170	241-44	35-41
double-clicks 166-67	converting bitmaps to 621-22	CS (code segment) 23, 824
double-click time 167-68	determining memory organization for	CS_HREDRAW 45, 89
POINT, RECT, and IParam 164-65	516-17	CS_VREDRAW 45, 89
	in icons and cursors 330-31	CUR file format 334-35
shift key processing 166		Cursor(s) 326-38
simple mouse processing example	design rules 331-32	
160-64	ROP2 and 555-56	alternate 337-38
Clipboard 411, 763-804	text 643-44	bitmaps in 330-31, 617
advanced use 779-85	COLORSCR program 247-51	color design rules 331-32
delayed rendering 781-82	revised, to use a modeless dialog box	.CUR file format 334-35
multiple data items 780-81	481 -84	defining 46, 64
private data formats 783-85	CombineRgn 583, 584, 588	defining with monochrome bitmap
clipboard viewer (see Clipboard	CONNECT program 160-62	329-30
viewer)	Context code 130-31	mouse 157-58, 176
	Control 700	changing the 193-94
simple use 763-79		RESOURCI program 326-29
BLOWUP program 769-74	CONTROL EXE color identifiers 240	
functions of 767	CONTROL program 197	shift and cursor keys 134-35
getting text from 766-67	colors and 238-44	size of 332-34
metafile/metafile picture 775-79	CopyMetaFile 637	translating into scroll bar messages
opening/closing 768	CopyRect 582	252-53
standard data formats 764	CountClipboardFormat 781	
transferring text to 765-66	CreateBitmap 394, 395, 573-74,	D
using with bitmaps 768-69	576, 602	The second secon
	CreateBitmapBits 574	Data formats, private 783-85
Clipboard owner 781–82	CreateBitmapIndirect 394, 602-3, 605	Data Interchange Format (DIF) 764
messages sent by clipboard viewer		Data segments. See Code and data
to 784	CreateBrushIndirect 573, 577, 638	segments
Clipboard viewer 785-804	CreateCompatibleBitmap 394, 602, 608	DATA statement segment attributes
chain 785	CreateCompatibleDC 394, 503, 607	295, 815
CLIPVIEW program 789-91	CreateDC 194, 502-3	Data type prefixes 33
functions/messages 786-88	printer 700, 704-7	
loading/saving clipboard contents	CreateDialog, to create modeless dialog	Debugging
791-804	boxes 479-83, 492	assertion message box and 450-51
messages sent to clipboard owner	CreateDiscardableBitmap 602	dynamic link libraries and 833-34
		.DEF file. See Module definition file
by 784	CreateEllipticRgn 583	DefHookProc 756-57
CLIPFILE program 792-804	CreateFont 656, 657, 666	DefWindowProc 49, 59
Clipping	CreateFontIndirect 656, 657, 666, 669	processing WM_PAINT 92-93
rectangles 94, 97, 584-85	CreateHatchBrush 63-64, 571, 572	Delayed rendering technique 781
regions 584-85	CreateIC 222, 503, 511-12	and an extracting transmiter to

Displays. See also Client area, painting EndDialog 423, 438 DeleteMetafile 630, 631, 633 EndPaint 92, 502, 518 DeleteObject 255, 396, 548, 572 text on; Graphics Device logical font 657 Interface (GDI): Screen Enhanced Graphics Adapter (EGA) DeleteString 816, 822 color (see Color(s)) display 67, 513 DestRect 582 coordinate system 522-25 EnumAllFaces 683, 696 DestroyWindow 58, 171, 413 EGA 67, 513 EnumAllSizes 696 to end modeless dialog boxes 481 IBM Graphics 513, 514 EnumClipboardFormats 781 EnumFants 674-75, 696, 758 DEVCAPS program 504-11 icon and cursor size 332-34 ENVIRON program 268-70 revised, for printing 707-13 information context handle for 511 Device-based fonts 648 Epilog code 38, 297-300, 824 size of 515-16 Device context (DC) 91-92 DLGBOX utility 493-96 Error codes, printer 739-40 Graphics Device Interface (GDI) DlgDirList 453, 465-66 ES (extra segment) 23, 824 501-20 DlgDirSelect 465-66 Escape, spooling, printing and attributes 517-18, 643-44 DoCaption 478 700-704, 715-18, 738 color 516-17 DoFileOpenDlg 464 banding and 741-42, 747, 748 DEVCAPS program 504-14 DoFileOpenDlgProc 464, 478 error codes and 739 device size 515-16 DoFileSaveDlg 464 for multipage printing 738 getting handles to 501-3 DoFileSaveDlgProc 464, 478 subfunctions 716 getting information 504 Dot-matrix printer, banding for 741-43 ExcludeClipRect 584 saving 518-20 Double-clicks, mouse 158, 166-67 EXE files 10, 40. See also New mapping mode 520-40 time of 167-68 Executable file format memory (see Memory device context) DoubleClickSpeed 167-68 EXEHDR program 27 printer 700, 704-15 Dragging a mouse 158 examining libraries with 807-8 Device context attribute DrawBitmap 614-15 Exported functions 26-27, 52 default and functions to change/get Drawlcon 337, 589 dialog function 423-24 517, 518 Drawing modes 550~51 EXPORT statement 52-53, 830 text 643-44 Extended character set 150-53 DrawMenuBar 379 Device context handles DrawRuler 696 ExtTextOut 642 getting to the device context 501-3 DrawText 96, 217, 642, 684 two methods for getting 92-93, 95 DS (data segment) 23, 24 DEVICEDEFAULT_FONT 645 DS != SS issue and dynamic link Far call 23 Device drivers 12-13. See also Device libraries 824-28 far keyword 29 context (DC) Dynamic link libraries 10, 25-26, FAR PASCAL, call-back functions keyboard 125-26 805 - 41defined as 206 mouse 158-59 basics 805-8 Far pointer 24, 282 printer 701, 702 (see also Printer caller's data segment used by 835-36 functions 297-300, 822-23 device context) DS != SS issue 824-28 prefix 22 relationship to Windows 15, 16 import libraries 831-32 FatalExit 38, 451, 833 system 199 instance thunks unnecessary 303-4 File(s) 452-78 DeviceMode 713-15 intercepting Windows function calls bitmaps as 606 DGROUP 287 833-34 dialog boxes for open/save 458-64 local heap organization 289 linking without imports 834-35 DlgDirList and DlgDirSelect memory organization in 288 methods for specifying links 830 465-66 DialogBox 424-25, 426, 829 other library restrictions 829 file 1/O 455-56 Dialog box(es) 6, 7, 62, 415-96 printer driver 714, 715 undocumented functions 456-58 abort (see Printing dialog function) reference count 715, 835 getting valid filenames 466-67 DLGBOX utility 493-96 resource-only 836-41 listing with list box 271-72 message box 449-51 STRPROG program and STRLIB OpenFile 452-54 modal 416-48 library 808-24 POPPAD program 467-78 modeless 479-93 tag image file format (TIFF) 607 printing 729-34 undocumented string functions 458 working with files 452-78 ECHO statement 68 File and Edit popups, use in menus 372 Dialog box controls 427-28 File attribute code 271 EDIT class, as a child window control defining your own 442-48 257-63 FILEDLG files 458-64 working with 434-37 edit control notification 261 FileLength 457 Dialog box manager 415 messages to 261-62 Filenames, getting valid 466-67 Dialog box template 419~21 FileOpenDlgProc 465, 466 POPPAD program 257-60 HEXCALC program 492 FileSaveDlgProc 465 styles 260 Dialog function 415, 421-23 using 261 Filled areas, drawing 557-80 DIGCLOCK program 218-21 EllipPushWndProc 447-48 ARCS program 562-66 Disable 126, 158 Ellipse 557, 559, 700 bounding box 558-62 Discardable memory 285-86 EmptyClipboard 767, 773, 780, 782 brush alignment 578-80 DispatchMessage 20, 57, 58, 143 Enable 126, 158 brushes and bitmaps 573-74 printing 725, 727 EnableMenuItem 380, 411-12 brushing the interior 570-72 EnableWindow 442

Filled areas, drawing (continued) peteny 270 GlobalUnlock 307, 309, 637, 765, 767 creating/using bitmap brushes GetErrorText 739 GRAFMENU program 386-93 Graphical interface. Windows as 10-11 575-77 GetInstanceData 357 pie chart trigonometry 566-69 Graphics, drawing 541-99 GetKevState 133-34, 166 Polygon and polygon filling 569-70 GetMenu 379 filled areas 557-80 GetMenuString 714 lines 542-56 FillRect 581, 611 GetMessage 20, 26 miscellaneous functions 589-94 FillRen 583 points 541-42 casting 31-32 FindResource 350, 351, 636 dynamic link libraries and 829 programs that draw "forever" 594-99 Fixed memory segments 284-85 locking data segments 317-18 rectangles, regions, and clipping Fixed pitch 650 Fixed size windows 64-68 581-89 within a message loop 56, 57 Graphics Device Interface (GDI) 14. FloodFill 589 modeless dialog box 480, 485 Font(s) 98-100. See also Text nonpreemptive multitasking with 91-107, 499-540 59-60 character size 98-99 enumerating 674-84 client area size 106-7 internationalization 153-56 translating keystrokes into bitmaps (see Bitmap[s]) leading and spacing 654-55 accelerators 404 device context 91-92, 501-20 logical 656-73 translating keystrokes into character font-mapping algorithm 669-70 drawing graphics (see Graphics, messages 143 GetMetaFile 631, 633, 636 drawing) getting information on 670-73 PICKFONT program 658-66 GetObject 395, 396, 547, 572, 574, 774 formatting text 100-102 structure of 666-69 GetParent 225 GDI fonts 648-50, 652 (see also variable-pitch text 673 GetPrinterDC 717 Font[s]) getting device context handles GetPrinterIC 512 logical inches 653-54 92-93.95 GetProcAddress 714, 834-35 logical twips 655-56 mapping mode 520-40 GetProfileInt 168, 223 OEM/ANSI characters and 153 metafiles (see Metafiles) GetProfileString 223, 512, 705, 706, 714 points, twips 653 printers and 757-59 objects (see Bitmap(s): Brushes; GetStockObject 46, 545, 557, 644-45 GetStrCallBack 816, 823-24 Logical fonts; Pens; Regions) system 98, 644 GetStrings 816, 822, 823-24 paint information structure 93-95 typeface families 650-51 philosophy of 499-501 GetSysColor 239-40 types of 648-50 printers/plotters (see Printer and using stock 644-45 GetSystemMenu 379 plotter) FONTLIST program 675 -83 GetSystemMetrics 66-67, 102, 246, SYSMETS1 program 102-6 Font-mapping algorithm 669-70 264, 504 system font 98 Font resource files 648, 651-52 SYSMETS program to display FONTS.FON 98, 648, 652 information from 102-5 text metrics details 99-100 (see also Text) Format of text 100-102 GetTempFileName 630-31 GetTextCharacterExtra 644 TextOut 91, 96-97 FORMFEED program 716-17 GetTextColor 643 GrayString 645-47 FrameRect 581 easy use of 647-48 GetTextExtent 395, 673, 685, 686 FrameRen 583 GetTextFace 657, 670-71 Group boxes 235 FreeLibrary 714, 835, 840 in dialog boxes 438-41 Free memory 283 GetTextMetrics 522 calculating 217 to get character dimensions 98-99, 100, 654 FREEMEM program 213-15 Function calls, intercepting 833-34 logical fonts 657, 670-71 Handles 28, 285 GetUpdateRect 91, 584 device context 92-93, 95, 501-3 GetVieuportOrg 527 icon 335-36 GetWindowDC 502 instance 36-37 GetBitmapBits 574 GetWindowLong 253-54 not to be used as pointers 320 GetBitmapDimension 606-7 GetWindowOrg 527 GetBitmapFont 395, 397, 398 typedef definitions 30 GetWindowText 261 Hardware GetBkColor 549 GetWindowTextLength 261 relationship to MS-DOS 12-14 GetBkMode 550 GetWindowWord 188, 231 relationship to Windows 14, 15 GetClassWord 254 GlobalAlloc 306, 307-14, 319, 351, Header file 28-31 GetClientRect 442, 524-25 765, 766 HEAD program 272-76 GetClipboardData 766, 767, 768, 773, GlobalCompact 217, 310 HEAPWALK program 28 780-81, 782 GlobalFlags 312 HEXCALC program 487-90 GetClipboardOwner 783 GlobalLock 307, 309, 312, 313-14, 351, GetCursorPos 177 HiliteMenuItem 380 603, 765, 766 Hit-testing in programs 172-88 GetDC 95, 502, 518 Global memory 283 CHECKER1 program 173-76 GetDeviceCaps 504, 512-14, 652 discardable 311-12 CHECKER2 program with keyboard banding and 740, 742, 743 huge blocks 313-14 interface 178-82 color and 516-17 layout 286, 287 child windows for 182-83 printing 715, 723 memory allocation 305-14 child windows in CHECKER3 183-88 size of display index 515-16 text to clipboard with 765-66 hypothetical example 172 GetDlgltemInt 486, 493 GlobalReAlloc 310, 311 GetDlgItemText 466

Hit-testing in programs (continued)	Interrupt ICH 200	Keystroke(s), See also Keyboard
keyboard emulation of the mouse	Interrupt 21H 12, 14	versus characters 128
176-78	Function 2AH 222	ignoring 127
Hit-test message 170-71	Function 2CH 222	intercepting 755-57
Hot spot, cursor 157-58, 334	Function 3CH 455	messages 128-35
HTCLIENT 170-71	Function 3DH 455	IParam variable 129-31
Hungarian notation 32-33	Function 3EH 455	shift states 133-34
	Function 3FH 455	system and nonsystem 129
1	Function 40H 455	using 134-35
IBMBIO.COM 12	Function 42H 455	virtual key codes 132-33
IBMDOS.COM 12	Function 57H 452	sending messages in KEYLOOK
	IntersectClipRect 585	146-50
IBM Graphics Display 513, 514, 515, 516	IntersectRect 582	translating to use accelerators 404-5
JCO file formats 334-35	Intersegment call 23	KillTimer 198, 199, 212
Icon(s) 326-38	Intrasegment call 23) \$ 11 p. 1 o 12 p. 10 t. 10 t
bitmaps in 330-31, 617	InvalidateRect 90, 91, 255, 584	1
color design rules 331-32	structuring programs for painting	L
COLORSCR program as an 257	with 116-17	Landscape mode 713
creative use of 215-16	InvalidateRgn 90, 584	banding in 742, 743
defining 46, 64		Leading 654-55
defining with monochrome bitmaps	Invalid rectangle 90 InvertBlock 194	LibEntry 813
329-30		LIBENTRY.ASM file, in dynamic link
forcing 216-17	InvertRect 581	libraries 812-14
handles 335-36	InvertRgn 583	LibMain 813-14
.ICO file format 334-35	IO.SYS 12	Libraries. See Dynamic link libraries
maintaining status as 217	IsClipboardFormatAvailable 31, 411,	LIBRARY statement 814
RESOURCE1 program 326~29	766, 780	Line(s), drawing 542–56
size of 332-34	IsDialogMessage 480-81, 733	
using in programs 336–37	IsDlgButtonChecked 437	avoiding device dependencies 549
ICONEDIT utility 215, 329, 601	IsRectEmpty 582	color 555-56
IDC_ARROW 158	CONTRACTOR	creating/selecting/deleting pens
IDC_CROSS 158	J	545-49
		drawing modes 550~51
IDC_WAIT 158, 193	JUSTIFY program 687–95	filling in gaps 549-60
IMPLIB program 831		ROP2LOOK program 552-55
Import libraries 26-27, 806-7, 830. See	K	using stock pens 544-45
also SLIBW.LIB	KERNEL module 14	LineDDA 590-94
dynamic linking without 834-35	file functions 455, 458	LINEDDA program 591-93
using 831-32	Kerning 673	LineProc 590, 594
Index parameter 102		LineTo 542-44
InflateRect 582	Keyboard 125-56. See also Keystroke(s) basics 125-28	LINK4 26
Information context 503, 511-12		creating libraries without data
Input focus 19, 127-28	character messages 143-46	segments 835
buttons and 237-38	emulating the mouse with 176-78	parameters 40-41
Input/output, file	hook chain 756	Listbox class, as a child window control
methods of 455-56	interface for CHECKER 178-82	263-77
undocumented functions 456-58	interface for GRAFMENU 399	ENVIRON program 268-71
Inquire 126, 158	interface for scroll bar messages	HEAD program 272–77
Instance handle 36-37	252-53	
Instance thunk 302-3, 424, 824	interface for SYSMETS 135-43	listing files 271–72
not needed in dynamic libraries	internationalization concerns 153-56	putting strings into 264-65
	message queue 19, 20	receiving messages from 267
303-4	messages 128-35, 146-50	selecting/extracting entries in
Instruction pointer (IP) 824	Windows character sets 150-53	265-67
Intel 8086 microprocessor family	Keyboard accelerators 399-414	styles 263-64
dynamic link libraries and	accelerator table 401-3	ListProc 276
architecture of 824-28	loading 403	LoadAccelerators 403
memory segments 282-83	enabling menu items 411-12	LoadBitmap 345-46, 393, 606, 840
programming for Windows 22-24	POPPAD program with 406-11	LoadCursor 46, 337, 338
Internationalization issues 153		LoadIcon 46, 335, 337, 338
character sets 154	processing menu items 412-14	LoadLibrary 714, 715, 834, 840
clock program 222-23	reasons for using 400	LoadMenu 379-80
MS-DOS and 154-56	receiving messages from 405	LoadMenuIndtrect 373-74
number pad 156	-1 - 1 - 1 - 100 (0)	
	rules on assigning 400-401	LoadResource 350, 636
Interrupt 08H 199, 200	translating keystrokes 404~5	LoadResource 350, 636
Interrupt 08H 199, 200 Interrupt 09H 126	translating keystrokes 404-5 KEYBOARD.DRV 125-26	LoadResource 350, 636 LoadString 34748, 349, 357
Interrupt 08H 199, 200 Interrupt 09H 126 Interrupt 16H 126	translating keystrokes 404~5	LoadResource 350, 636

PROGRAMMING WINDOWS

LocalCompact 317	Memory device context 394, 503, 607-8	Message(s) (continued)
LocalDiscard 317	animation 624-27	keystroke 128–35
LocalFlags 317	"blt" functions 609-15	menus and 364-67
LocalFree 315, 319	color conversions 621-22	message queue 18, 19
LocalLock 315-17, 318	drawing with 618-21	in modeless dialog boxes 480
allocation shortcuts with 318-19	mapping mode conversions 622	message retrieval 21
Local memory 287–89	stretching bitmaps 623-24	messages sent to window
memory allocation 305, 314-17	using different ROP codes 615-18	functions 22
LocalReAlloc 317	Memory management 9-10, 281-321	mouse events and 19 20
locking data segments 317-18	allocating memory within programs	nonclient-area mouse 169-71
localtime 222	305-21	queued and nonqueued 58-59
LocalUnlock 315	locking data segments 317-18	receiving, from list boxes 267
Lock count 306	locking memory blocks 306-7	scroll bar 111-12
LockData 318	shortcuts 318-20	timer 20, 199, 200-201
LockResource 351, 356-57, 636	calculating free 217	WndProc 50-51
LOGFONT structure 666-69	character strings and 349-50	MessageBeep 204
		MessageBox 72, 449
Logical fonts 656–73	code and data segments 289-96	
font-mapping algorithm 669-70	fixed memory (see Thunk)	using character strings with 348-49
getting information on 670-73	flagged code segments as 27-28	Message boxes 72, 449~51
PICKFON'T program 658-66	moving/reloading program segments	assertion 450-51
structure 666-69	296-305	for no available timers
variable-pitch text 673	resources and 338-46	choice options 204
Logical inch	segmented, in Intel 8086 chips	"friendly termination" 203
pixels per 653	282-83	popup information in 451
reasons for 653-54	Windows memory organization	Message loop 20
Logical twips 655-56, 758	283-89	in continuous drawing 595-97
per pixel 653	Memory models 24	in modeless dialog boxes 480-81, 485
	code/data segments and 289-90,	in printing 725
Long call 23	292-93	in WELCOME2 program 55-58
Long pointer. See Far pointer		
IParam parameters 51	Menu(s) 359-84	Metafiles 503, 602, 627-40
accelerator messages 405	accelerators and, in POPPAD program	clipboard and metafile picture
color messages 242	406-11	775-79
edit control notification 261	enabling menu items 411-12	dos and don'ts 638-40
keystroke messages 129-31	processing menu options 412-14	looking at 637-38
menu messages 365, 366, 367	additional definition methods 372-74	playing into the device driver 701
mouse messages 159, 164-65, 169	bitmaps in 384-99	simple use of 628-30
scroll bar 245	creating 393-94	storing on disk 630-31
nervin and a cy	creating, with text 395-96	using as resources 633-37
**	GRAFMENU program 385-95	using preexisting 631-33
M	keyboard interface 399	MFCREATE program 632
Make file 41	memory device context and 394	MFRESORC program 634-36
MakeIntResource 351	putting menus together 397–99	Microsoft C Compiler, memory
MAKEPOINT structure 165, 527		models 24
MakeProcInstance	scaling 396-97	
creating instance thunk for functions	ChangeMenu 377-79	MM_ANISOTROPIC 521, 531, 535-36,
with 302-3	commands 379-80	629, 775
dialog box 424	dialog box 426	MM_HIENGLISH 521, 528
	etiquette 372	MM_HIMETRIC 521, 528
drawing graphics 590	MENUDEMO program 367-72	MM_ISOTROPIC 521, 531-35, 775
STRPROG use of 823-24	menu template 360-63	MM_LOENGLISH 521, 522, 528, 529-30
use in call-back functions 207, 210,	top-level versus popup 361	MM_LOMETRIC 521, 528
211, 212, 646	messages and 364-67	MM_TEXT mapping mode 521
MapDialogRect 442	NOPOPS program 380-84	working with 525-28
Map file 41	referencing, in programs 363-64	x/y coordinates 97
Mapping modes 97, 520-40	structure 360	MM_TWIPS 521, 528
changeable 531-36	using the system menu 374-77	Modal dialog boxes 416-48
conversions of 622		ABOUTI program 416-19
device coordinates/logical	MENUDEMO program 367-71	ABOUT2 program 428-34
coordinates 522	Message(s) 18-22	
device coordinate system 522-23	accelerator 404, 405	ABOUT3 program 442-48
logical twip 655–56, 758	button 232-33	controls
"metric" 528-31	character 143-46	defining your own 442-48
table of 521	client-area mouse 159-68	working with 434-37
	color 241-44	defining controls 427-28
viewport and window 523-25	default processing 51-52	dialog box function in 421-23
WHATSIZE program 537-40	to edit control 261-62	exporting 423-24
working with MM_TEXT 525-28	keyboard events and 19, 20	dialog box template 419-21

Modal dialog boxes (continued)	NOTEPAD program 257	Pie charts, trigonometry of 566-69
invoking 424-25	NOTHING.C program 36	Pitch
versus modeless dialog boxes 479-81	compiling 38-39	fixed 650, 651
OK and Cancel buttons in 437-38	.DEF file 39	variable 650, 651, 673
other functions and 442	make file 41	Pixels 67, 97, 500-501
painting on 441-42	Number pad 156	coordinate system 522-23
style 425-26		per logical inch/logical twip 653
tabs and groups 438-41	0	"read" and "write" 541
Modeless dialog boxes 479-93	Object library 806-7	"White" and "Screen" 334
HEXCALC program 486-93		PlayMetaFile 629
versus modal dialog boxes 479-81	Object module file 40	POEPOEM program 351-56
revised COLORSCR program 481-86	Object-oriented programming 17	Pointers, handles not to be used as 320.
using control IDs 493	OEM character set 151-56, 644	See also Far pointer; Near
Module definition file 39-41	OEM_FIXED_FONT 98, 153, 644	pointer
Monochrome bitmap 329-30	OEMFONTS.FON 98	Points
color conversion of 621-22	OEM Scan Code 130	drawing 541-42
format 604~5	OemToAnsi 126, 155	type size 653
Mouse 157-95	OffsetClipRgn 585	POINT structures 164-65
basics 157-59	OffsetRect 582	Polygon 557, 569-70
capturing the 189-95	Offset register 23	Polygon filling modes 569-70
client-area messages 159-68	OFSTRUCT fields 452	PolyLine 542, 544
cursor 157-58, 176	OKMsgBox 451	POORMENU program 374-76
changing the 193-94	OK push button, in dialog boxes 437-38	POPPAD program 257-59
hit-testing programs 172-88	OpenClipboard 765, 766, 768, 773, 782	revised, with dialog boxes 467-78
keyboard emulation of 176-78	OpenFile 155, 452-54, 466	with menu and accelerators 406-11
message queue 19, 20	OpenJob 700	with printing facility 734 -37
nonclient-area messages 169-71	Operating System/2 3, 4	Popup windows 8, 9, 62. See also
MOUSE,DRV 158	OS/2. See Operating System/2	Dialog box(es)
Moveable entry point 300	Overlapped windows 72, 77-78	creating 72–77
Moveable memory segments 284-85	PARTY program with 79-85	DIGCLOCK program 218-24
discardable (see Discardable	523	parent programs and 77–78
memory)	P	PARTY program with 79–85
MoveTo 542, 544	Pagemaker (software) 292-93	PopupWndProc 83
MoveWindow 188, 226, 260, 442	Paint	Portrait mode 713
MS-DOS	client area (see Client area, painting	banding in 743
actual relationship to applications/	text on)	PostMessage 757
ROM BIOS/hardware 13, 14	dialog boxes 441-42	PostQuitMessage 57–58, 71, 171
internationalization 154-56	scroll bars 116-17	Presentation Manager 3, 4
prompt 5	Paint information structure 90, 93-95	Previous Key State 131
relationship to Windows 14, 15	PaintRgn 583	PRINT1 program 722 =23
theoretical relationship to	PAINTSTRUCT 92, 93-95, 502	PRINT2 program 728-29
applications/ROM BIOS/	PaintTheBlock 441	PRINT3 program 730 –32
hardware 12, 13	PaintWindow 441-42	PRINT4 program 744 –47
MS-DOS applications and Windows 11.	Paragraphs	PRINT.C file 719-21
See also Applications programs	formatting/justifying text 686-96	PrintDlgProc 729-34
MS-DOSD.EXE 806	memory 283	Printer and plotter 699–759
MS-DOS.EXE 806	Parent programs, and popup windows	banding techniques 740-57
MS-DOS Executive 5	77–78	fonts and 757–59
hit-testing 172	Parent window handle 73, 77	information context handle for 512
MSDOS.SYS 12	PARTY program 79-83	printing, spooling, and Escape
MSG message structure 55-56	Pascal calling sequence 25	700-704, 715-18, 738, 747-48
Multiple instances 256	pascal keyword 29	printing fundamentals (see Printing)
Multitasking and Windows 8-9	PatBlt 194, 609-11, 646	printing graphics and text 719-40
nonpreemptive 59-60	correcting parameters of 612-13	Printer device context 700, 704–15
110018000000000000000000000000000000000	PeekMessage 60	BitBlt capability 715
N	drawing graphics with 595-97	CreateDC parameters 704-7
The state of the s	dynamic link libraries and 829	DeviceMode call 713-15
Near call 23	locking data segments 317–18	
Near pointer 24, 282	printing with 725, 726-27, 730, 733	revised DEVCAPS program 707–13 Printing 715–40
prefix 33	Pens	fundamentals of 715–18
New Executable file format 10, 26-27,	creating/selecting/deleting 545-49	
807-8	drawing modes 550-51	graphics and text 719-40
Newline character 642	styles 546	abort function in 723-29
Nonclient-area mouse messages 169-71	using stock 544-45	adding printing to POPPAD 734-38
Nonclient hit test 170-71	PICKFONT program 658-65	dialog box 729-34
Nonpreemptive multitasking 59-60	Pie 557, 561, 566-69	error codes 739_40

PROGRAMMING WINDOWS

Printing dialog function 729-34 PRINT3 program 730-31	Resource(s) 323–26. See also Bitmap(s); Character strings;	Segment registers 23 SEGMENT statement segment attributes
PrintMyPage 723, 725, 732-34	Cursor(s); Dialog box(es);	295, 296
PrintScreen 757	Font(s); Icon(s); Keyboard	SelectClipRgn 584, 589
Private data formats 783-85	accelerators; Menu(s); User-	SelectObject 394
Programming for Windows 22-34	defined resources	drawing graphics with 545, 548,
calling window functions 24-25	compiling 324-25	557-58, 566, 572, 584
casting 31-32	memory and 338-46	metafiles and 637-38
dynamic linking 25-26	resource-only libraries 836-41	selecting logical fonts 656, 657, 669
handles 28	Resource script 324	SendDlgItemMessage 436
header files 28-31	Reverse video 63	SendMessage 20, 411
Hungarian notation 32-33	rgbColor 541-42, 643	adding keyboard interface to
Intel 8086 architecture 22-23	ROM BIOS	SYSMETS with 136-38
learning curve for 33-34	relationship to MS-DOS 12-14	putting text strings into list box with 264-65
memory management 27-28	relationship to Windows 14, 15	selecting/extracting entries with
New Executable format 26-27	ROP (raster operation) 550, 609	265-67
object-oriented 17	supported by BitBlt 613-14 supported by PatBlt 610	to spooler 701
Pascal calling sequence 25	using different 615~18	Serifs 650
Program segment(s)	ROP2 (binary raster operation) 550	SetBitmapBit 574
attributes 294-96	color and 555-56	SetBitmapDimension 606-7
moving and reloading 296~305 dynamic library differences	drawing modes 551	SetBkColor 242, 246, 549, 622, 643
	ROP2LOOK program 552-54	SetBkMode 550, 643
303-4 far function treatment 297-300	RoundRect 557, 560	SetCapture 189
	ROUTHERECT 321, 300	SetClassWord 254, 336
program execution 300-302 role of MakeProcInstance 302-3		SetClipboardData 765-66, 767,
walking the stack 304-5	S	779-84, 788
Prolog code 38, 297-305, 822-23	SaveDC 520	SetCursor 193
Protected mode 23, 281	SCRAMBLE program 619-20	SetDlgItemInt 486
PilnRect 582	Screen, See also Displays	SetDlgItemText 465-66
Push buttons 233	initial Windows 6	SetDoubleClickTime 168
r dati Cattonia 200	printing the 748-55	SetInternational 223
D.	standard elements of 7	SetMenu 379, 380
R	Scroll bar(s) 62, 108-22	SetMetaFileBits 636
Radio buttons 235	building a better scroll 117-22	SetPixel 541-42
dialog box 436, 439	keyboard interface for 252-53	SetRect 581-82
RANDRECT program 597-99	messages 111-12	SetRectEmpty 582
Raster devices 500	range and position 109-10 scrolling SYSMETS 112-16	SetROP2 558
Raster font 98, 648, 649	structuring programs for painting	SetScrollPos 252
Raster operation. See ROP (raster	116-17	SetSysColor 239-40
operation)	thumbs 108, 109; 110	SetSysModalWindow 426
RC extension. See Resource(s)	types of 109	SetTextAlign 641-42
ReadFile 478	vertical 108	SetTextCharacterExtra 644
Real mode 23, 282	Scrollbar class controls 109	SetTextColor 242, 246, 622, 643
Rectangle 557, 558, 637, 747 Rectangles	as child window controls 245-57	SetTextJustification 686
clipping 584–85	automatic keyboard interface	SetTimer 198, 199
valid and invalid 90-91, 94	252-53	method one use of 201-12
working with 581–82	coloring scroll bars 255-56	method two use of 206-12
RECT structure 502, 581-82	coloring the background 254-55	method three use of 212
banding and 741	COLORSCR as an icon 257	SetVieuportExt 532, 775-76
transferring to POINT 165	COLORSCR program 246-52	SetViewportOrg 525-26, 530, 589
Reference count 715, 835	dealing with multiple instances	SetWindowExt 532, 775-66
Regions	256	SetWindowLong 253-54
clipping 584–85	window subclassing 252-54	SetWindowOrg 525, 526-27, 528,
creating and painting 582-84	Scroll bar controls 109	530, 533 SetWindowsHook 755-56
RegisterClass 44, 47, 51, 226	ScrollDC 589-90	SetWindowText 71, 236, 252, 261, 270,
creating instance thunk with 302-3	ScrollWindow 90, 589-90	478, 486
ReleaseCapture 189	Segmented memory. See also Code and	SetWindowWord 188
ReleaseDC 95, 502, 518	data segments; Program	Shift keys
Reload thunk 300-301, 808	segment(s)	keyboard states 133-34
Repeat count 130	discardable 285-86	mouse processing 166
RESOURC1 program 326-29	fixed and moveable 284-85	Short call 23
RESOURC2 program 342-45	global memory layout 286-87	Short pointer. See Near pointer
The second secon	in the Intel 8086 family 282-83	SHOWBIT program 837-40
	local memory 287–89	

ShowWindow 44, 48, 52, 60-61, Text (continued) Variable pitch 650, 673 formatting 100-102, 684-96 Vector devices 500 in modeless dialog boxes 480 one-line 685-86 Vector (stroke) fonts 648, 649, 650, 652 Simonyi, Charles 32 paragraph justification 686-96 Viewport (device) coordinates 523-25 getting from clipboard 766-67 SizeTheWindow 222 Virtual key codes 131-33 SLIBW.LIB 26, 41, 831 graving character strings 645-47 Visual interface, Windows 5 Slow boot 17, 805 mapping mode (see MM_TEXT usprintf 451 Spooling 700-704 mapping mode) SPOOLER program operation 702 painting on client areas (see Client sprintf 71 area, painting text on) WaitMessage 60 formatting text with 102 transferring to clipboard 765-66 locking data segments 317-18 SS (stack segment) 23 using stock fonts 644-45 Walking the stack 304-5 DS != SS issue and dynamic link TEXTMETRIC structure 98, 99-100, wAttr 271 libraries 824-28 WELCOMEI program 42-43 Stack fields 671-73 WELCOME2 program 53-55 after prolog instruction execution TextOut 91, 96-97, 641-42, 684, 685 WELCOME3 program 65-66 208 Thunk 28, 211-12 WELCOME4 program 69-70 after Windows prolog 299 instance 302-4, 424, 824 WELCOME5 program 73-76 frame 297-98 reload 300-301, 808 WHATSIZE program 537-39 walking the 304-5 TIFF. See Tag image file format (TIFF) WIN200.BIN 17 Stack pointer 824 Timer 197-224 WIN200.OVL 17 Static class, as a child window control basics 198-201 WinAssert 450-51 244-45 message queue 20 Window Status reports, using timer for 212-17 no available 202-4 defined 17-18 strchr 467 three use methods 201-12 logical coordinates of 523-25 StretchBitmap 396, 397 using for a clock 218-23 Window class 44-47 StretchBlt 192, 194, 397, 623-24, 755. using for a status report 212-17 as child window control (see Child 768, 773 Windows standard time 224 window controls) Strings TimerProc 206-8 defining icon/cursor in 64 putting into list boxes 264-65 tmAveCharWidth 100 many windows from one 68-72 undocumented functions, in files 458 tmExternalLeading 100 PARTY program 83 strlen 825-28 tmInternalLeading 100 for popup windows 76 STRLIB library 810-12 ToAscii 126 Window function 45. See also WndProc revised make file and module Tracking 164 message handling 20-22, 50-51, definition file 832 Transition State 131 58-59 Stroke width 650 TranslateAccelerator 400, 404, 405 Window functions 18 STRPROG program 816-21 TranslateMessage 56-57 calling 24-25 revised make file and module keystrokes to character messages 143 Windows 3-34 definition file 832 printing 725, 727 advantages of, to users and strrch 467 typedef declarations in WINDOWS.H programmers 5-12 Subclassing. See Window subclassing 29, 314 client-area text (see Client area, Symbolic Link 764 for each handle 20 painting text on) Symbols, type 650 Typeface creating/displaying (see Creating and SYSMETS1 program 104-5 families 650-51 displaying windows) SYSMETS2 program 112-15 leading and spacing 654-55 history of 4 SYSMETS3 program 117-21 points/logical inches 653-54 input (see Keyboard; Mouse; Timer) SYSMETS.H header file 103 memory organization 283-89 SYSMETS program 138-42 modules (see Graphics Device SYSTEM.DRV, and the timer 199 UnhookWindowsHook 756-57 Interface [GDI]: KERNEL System font 98, 644 UnionRect 582 module: USER module) System menu 374-77 UnrealizeObject 243, 578, 580 programming for 22-34 on child windows 84 UpdateWindow 44, 48, 52, 89 standard time in 224 in modeless dialog boxes 479-81 structuring programs for painting structure of 12-22 Systems Application Architecture with 117 Window scroll bars 109 (SAA) 4 User(s), advantages of Windows to 5-12 WINDOWS.H header file. See Header User-defined resources 350-57 Windows Software Development Kit 26, metafiles as 633-37 Tab stops in dialog boxes 438-41 POEPOEM program 351-56 27, 28, 493 Tag image file format (TIFF) 607 User interface 6-7 Window style 61-63 Terminal fonts 98 USER module 14 dialog box 425-26 Text 641-48. See also Font(s) edit 260 device context attributes for 643-44 list box 263-64 drawing functions 641-43 Window subclassing 253-54, 276 ValidateRect 584 easy use of GrayString 647-48 WIN.INI file 167 ValidateRgn 584 identifiers for system colors 240

PROGRAMMING WINDOWS

WinMain 36, 44, 51-52 CreateWindow in, versus in WndProc 187 WINPRTSC program 748-55 WINUNDOC.H header file 456 WM_CHANGECLIPBOARD 787 WM_CHAR 143, 144, 145, 493 WM_CHILD 62 WM_CLOSE 171, 480 WM_COMMAND 234, 235, 493 WM_CREATE 101, 786 WM_CTLCOLOR 241-44 WM_DEADCHAR 143, 146 WM_DESTROY 71, 787 WM_DRAWCLIPBOARD 786 WM_HSCROLL 111, 122, 245 WM_KEYDOWN 128, 134-35, 143, 144, 182, 493, 755 adding to SYSMETS program 135-36, 138 WM_KEYUP 144, 755 WM_KILLFOCUS 177, 237 WM_MOUSEMOVE 166 WM_NCHITTEST 170-71 WM_PAINTCLIPBOARD 786 WM_PAINT message 89-90 clipboard 786

WM_PAINT message (continued) filling polygons 570 saving device contexts 518 structuring programs to paint client areas in response to 116-17 WM SETFOCUS 177, 237 WM_SIZE 107 WM_SYSCHAR 143 WM_SYSDEADCHAR 143, 146 WM_SYSKEYDOWN 128, 129 WM_SYSKEYUP 129 WM_TIMER 199, 200 WM_USER 232 WM_VSCROLL 111, 122, 245 WndProc 45. See also Child window(s) CreateWindow in, versus in WinMain 187 dialog box 424 PARTY program 83 role of 49-51, 52, 57, 71 using to set up window class 49 wParam parameter and messages 51 accelerator messages 405 edit control messages 261 menu messages 365, 366, 367 mouse messages 159, 169 scroll bar 111, 112 virtual key codes and 131-33

WriteFile 478 WriteProfileString 168 WriteSpool 701 WS_BORDER 62 WS_CAPTION 62 WS_CHILD 62 WS_CLIPCHILDREN 63 WS_CLIPSIBLINGS 63 WS_DISABLED 63 WS_DLGFRAME 62 WS_HSCROLL 62, 109 WS_MAXIMIZE 63 WS_MAXIMIZEBOX 62, 68, 73 WS_MINIMIZE 63 WS_MINIMIZEBOX 62 WS_OVERLAPPEDWINDOW 61, 62 WS_POPUP 61, 72 WS_SYSMENU 62 WS_THICKFRAME 62, 68, 73 WS_VISIBLE 63 WS_VSCROLL 62, 109



Xerox Palo Alto Research Center 8

Charles Petzold

Charles Petzold is a full-time freelance writer and a contributing editor to *PC Magazine*, where he currently writes about OS/2 in the "Environments" column. He has also written articles about Microsoft Windows and OS/2 programming for the *Microsoft Systems Journal*. **PROGRAMMING WINDOWS** is his first book.

The manuscript for this book was prepared and submitted to Microsoft Press in electronic form. Text files were processed and formatted using Microsoft Word.

Cover design by Ted Mader and Associates
Interior text design by Darcie S. Furlan
Illustrations by Nick Gregoric and Rick Bourgoin
Principal typography by Lisa G. Iversen
Principal production art by Becky Geisler-Johnson and Peggy Herman

Text composition by Microsoft Press in ITC Garamond with display in Helvetica Black, using the MAGNA composition system and the Linotronic 300 laser imagesetter.

ORDER CARD

For information on the set of Companion Disks for Programming Windows, please see page x. YES...please send me ______ set(s) of the Companion Disks to Sales Tax (See rate chart below.) California - 5% (plus local option tax): Connecticut -7.5%; Florida - 6%; Massachusetts - 5%; Minnesota - 6%; Missouri - 4 225%; New York - 4% (plus local option tax), Washington - 7.8% Postage and Handling Charges: \$2.50 per disk set (domestic orders) \$6.00 per disk set (foreign orders) . Please check correct box: 51/4-inch format 31/2-inch format TOTAL 097-000-142 097-000-139 Name. Please Print Address Daytime Phone #: (__ City. State Payment: Check/Money Order VISA MasterCard American Express (15 numbers) Credit Card No. Signature All domestic orders shipped 2nd day air.



NO POSTAGE NECESSARY IF MAILED IN THE UNITED STATES

BUSINESS REPLY CARD

FIRST CLASS

PERMIT NO. 108


BELLEVUE, WA

POSTAGE WILL BE PAID BY ADDRESSEE

MICROSOFT PRESS

Attn: Programming Windows Companion Disk Offer 21919 20th Ave SE Box 3011 Bothell, WA 98041-3011

Hardcore Computer Books



THE NEW PETER NORTON PROGRAMMER'S GUIDE TO THE IBM PC® & PS/2®

Peter Norton and Richard Wilton

A must-have classic on mastering the inner workings of IBM microcomputers — now completely updated to include the PS/2 line. Sharpen your programming skills and learn to create simple, clean, portable programs with this successful combination of astute programming advice, proven techniques, and solid technical data. Covers the microprocessors; ROM BIOS basics and ROM BIOS services; video, disk and keyboard basics; DOS basics, interrupts, and functions (through version 4); device drivers and video programming; and programming in C, QuickBasic, and TurboPascal. Accept no substitutes; this is the book to have.

\$22.95 [Book Code 86-96635]


INSIDE OS/2


Gordon Letwin

"The best way to understand the overall philosophy of OS/2 will be to read this book." Bill Gates

Here — from Microsoft's Chief Architect of Systems Software — is an exciting technical examination of the philosophy, key development issues, programming implications, and a look at the role of OS/2 in the office of the future. Letwin provides the first indepth look at each of OS/2's design elements. This is a valuable and revealing programmer-to-programmer discussion of the graphical user interface, multitasking, memory management, protection, encapsulation, interprocess communication, and direct device access. You can't get a more inside view.

\$19.95 [Book Code 86-96288]





ADVANCED OS/2 PROGRAMMING

Ray Duncan

Authoritative information, expert advice, and great assembly-language code make this comprehensive overview of the features and structure of OS/2 indispensable to any serious OS/2 programmer. Duncan addresses a range of significant OS/2 issues: programming the user interface; mass storage; memory management; multitasking; interprocess communications; customizing filters, device drivers, and monitors; and using OS/2 dynamic link libraries. A valuable reference section includes detailed information on each of the more than 250 system service calls in version 1.1 of the OS/2 kernel.

\$24.95 [Book Code 86-96106] [Available 12/20/88]

PROGRAMMING WINDOWS

Charles Petzold

Your fastest route to successful application programming with Windows. Full of indispensable reference data, tested programming advice, and page after page of creative sample programs and utilities. Topics include getting the most out of the keyboard, mouse, and timer; working with icons, cursors, bitmaps, and strings; exploiting Windows' memory management; creating menus; taking advantage of child window controls; incorporating keyboard accelerators; using dynamic link libraries; and mastering the Graphics Device Interface (GDI). A thorough, up-to-date, and authoritative look at Windows' rich graphical environment.

\$24.95, softcover [Book Code 86-96049] \$34.95, hardcover [Book Code 86-96130]



Available wherever books and software are sold. Or order directly from Microsoft Press.

Solid Technical Information. Expert Advice.



ADVANCED MS-DOS® PROGRAMMING, 2nd ed.

Ray Duncan


The preeminent source of MS-DOS information for assembly-language and C programmers — now completely updated with new data and programming advice covering: ROM BIOS for the IBM PC, PC/AT, PS/2, and related peripherals; MS-DOS through version 4; version 4 of the L1M EMS; and OS/2 compatibility considerations. Duncan addresses key topics, including character devices, mass storage, memory allocation and management, and process management. In addition, there is a healthy assortment of updated assembly-language and C listings that range from code fragments to complete utilities. And the reference section, detailing each MS-DOS function and interrupt, is virtually a book within a book.


\$24.95 [Book Code 86-96668]

THE MS-DOS® ENCYCLOPEDIA

The ultimate reference for insight, data, and advice to make your MS-DOS programs reliable, robust, and efficient. 1600 pages packed with version-specific data. Annotations of more than 100 system function calls, 90 user commands, and a host of key programming utilities. Hundreds of hands-on examples, thousands of lines of code, and handy indexes. Plus articles on debugging, writing filters, installable device drivers, TSRs, Windows, memory management, the future of MS-DOS, and much more. Researched and written by a team of MS-DOS experts — many involved in the creation and development of MS-DOS. Covers MS-DOS through version 3.2, with a special section on version 3.3.

\$134.95 [Book Code 86-96122]





MICROSOFT® QUICKC® PROGRAMMING

The Waite Group

Your springboard to the core of Microsoft QuickC, This book is loaded with practical information and advice on every element of QuickC, along with hundreds of specially constructed listings. Included are the tools to help you master QuickC's built-in libraries; manage file input and output; work with strings, arrays, pointers, structures, and unions; use the graphics modes; develop and link large C programs; and debug your source code.

\$19.95 [Book Code 86-96114]

MICROSOFT® QUICKBASIC, 2nd ed.


Douglas Hergert

"No matter what your level of programming experience, you'll find this book irreplaceable when you start to program in Quick BASIC."

Online Today

This new edition of MICROSOFT QUICKBASIC — completely updated for version 4
— is a great introduction to all the development tools, features, and user-interface
enhancements in Microsoft QuickBASIC. And there's more — six specially designed,
full-length programs including a database manager, an information-gathering and dataanalysis program, and a chart program that reenforce solid structured programming
techniques.

\$19.95 [Book Code 86-96387]




American Express VISA Postage & Handling Charges: WA state residents CREDIT CARD NO MA and MD residents EXP. DATE Check/Money Order One book Each additional book MasterCard CA residents... PAYMENT: Price Sales Tax Shipping & Handling TOTAL All orders are shipped via UPS ground delivery. YES...please send me the books listed below: Oly. Order Code Place your credit card order by calling 800-638-3030 (In MD call collect, 824-7300). 8:15 AM to 4:15 PM. Monday through ware are sold. Or you can order directly from Microsoft Press Microsoft Press books are available wherever books and soft riday. Or use this order form. ORDER FORM ADDRESS NAME

3dd 8.1%

BBSS

Unbeatable Programmers' References



THE PROGRAMMER'S PC SOURCEBOOK

Thom Hogan


Here is important factual information — previously published in scores of other sources — organized into one convenient reference. Focusing on IBM PCs and compatibles, PS/2s and MS-DOS, the hundreds of charts and tables cover: mumeric conversions and character sets medical DOS commands and utilities medical DOS function calls and support tables medical other interrupts, mouse, and EMS sup-

port # keyboards, video adapters, and peripherals # chips, jumpers, switches, and registers # and more. \$24.95 [Book Code 86-96296]


PROGRAMMER'S GUIDE TO PC® & PS/2® VIDEO SYSTEMS

Richard Wilton

No matter what your hardware configuration, here is all the information you need to create fast, professional, even stunning video graphics on IBM PCs, compatibles, and PS/2s. No other book offers such detailed, specialized programming data, techniques, and advice to help you program directly to the hardware. And no other book offers such invaluable



source code examples. Whatever graphic output you want — text, circles, region fill, alphanumeric character sets, bit blocks, animation — the info is here. \$24.95 [Book Code 86-96163]



THE MICROSOFT® QUICKBASIC PROGRAMMER'S TOOLBOX

John Clark Craig

This essential library of subprograms, functions, and utilities designed to supercharge your QuickBASIC programs addresses common and unusual programming tasks: ANSLSYS screen control # mouse support # pop-up windows # graphics # string manipulations # bit manipulation # editing routines # game pro-

gramming ■ interlanguage calling ■ and more. You're guaranteed to turn to this superb collection again and again \$22.95 [Book Code 86-96403]

Available wherever books and software are sold.

Or order directly from Microsoft Press.

POSTAGE WILL BE PAID BY ADDRESSEE FIRST CLASS PERMIT NO. 108

Redmond, WA 98073-9717

Box 97017

16011 NE 36th Way

Attn: Consumer Sales Dept.

Microsoft Press

BELLEVUE, WA



Programmer's Quick References

At last! Now you can have instant access to key programming information. Whether you're an assembly-language or C programmer, you'll find these books exceptionally useful. The guides include overviews of each service along with a list of the parameters or arguments the service requires, the results it

returns, version dependencies, and valuable programming notes and warnings. All at your fingertips!

IBM® ROM BIOS

Ray Duncan

All the core information on each of the ROM BIOS services.

\$5.95 [Book Code 86-96478]

MS-DOS FUNCTIONS

Ray Duncan

Covers DOS through version 3.3. \$5.95 [Book Code 86-96411]

ESSENTIAL OS/2 FUNCTIONS

Ray Duncan

Great for anyone involved in OS/2 application programming! Here is the most accurate, up-to-date information on the OS/2 1.0 Kernel functions calls within the applications program interface (API).

\$9.95 [Book Code 86-96866]



PROGRAMMING

WINDOWS


CHARLES PETZOLD


Whether you're looking for a better understanding of Windows' dynamics and structure or are ready and eager to start programming in Windows, your key to success is *Programming Windows*.

A rich source of information for serious programmers, *Programming Windows* is your fastest route to better application programming with Windows 2.0 and Windows/386. It's full of indispensable reference data, tested programming advice and insight gleaned from Microsoft's Windows development team, and page after page of creative, efficient sample programs and utilities. Topics covered include: getting the most out of the keyboard, the mouse, and the timer • working creatively with icons, cursors, bitmaps, and strings • exploiting Windows' powerful memory management


- · creating menus through both conventional and unorthodox methods
- taking advantage of child window controls incorporating keyboard accelerators • using the clipboard and the dynamic link libraries • mastering the Graphics Device Interface (GDI).

Programming Windows. The most thorough, up-to-date, and authoritative look at Windows' rich graphical environment.





U.S.A. \$24.95 U.K. £22.95 Aust. \$37.95





WINDOWS

CHARLES PETZOLD

Microsot P R E S